


# Sapera LT™ 8.10

## Basic Modules Reference Manual

sensors | cameras | frame grabbers | processors | **software** | vision solutions



**P/N: OC-SAPM-BMR00**  
[www.teledynedalsa.com](http://www.teledynedalsa.com)

 **TELEDYNE DALSA**  
Everywhere you look™

## **NOTICE**

© 2015 Teledyne DALSA, inc. All rights reserved.

This document may not be reproduced nor transmitted in any form or by any means, either electronic or mechanical, without the express written permission of TELEDYNE DALSA. Every effort is made to ensure the information in this manual is accurate and reliable. Use of the products described herein is understood to be at the user's risk. TELEDYNE DALSA assumes no liability whatsoever for the use of the products detailed in this document and reserves the right to make changes in specifications at any time and without notice.

Microsoft® is a registered trademark; Windows®, Windows® XP, Windows® Vista, Windows® 7, Windows® 8 are trademarks of Microsoft Corporation.

All other trademarks or intellectual property mentioned herein belongs to their respective owners.

Printed on December 1, 2015

Document Number: OC-SAPM-BMR00

Printed in Canada

## **About This Manual**

This manual exists in Windows Help, and Adobe Acrobat® (PDF) formats (printed manuals are available as special orders). The Help and PDF formats make full use of hypertext cross-references. The Teledyne DALSA home page on the Internet, located at <http://www.teledynedalsa.com/imaging>, contains documents, software updates, demos, errata, utilities, and more.

## **About Teledyne DALSA**

Teledyne DALSA is an international high performance semiconductor and electronics company that designs, develops, manufactures, and markets digital imaging products and solutions, in addition to providing wafer foundry services.

Teledyne DALSA Digital Imaging offers the widest range of machine vision components in the world. From industry-leading image sensors through powerful and sophisticated cameras, frame grabbers, vision processors and software to easy-to-use vision appliances and custom vision modules.

# Contents

<b>INTRODUCTION</b>	<b>4</b>
OVERVIEW OF THE MANUAL .....	4
<b>SAPERA LT C API OVERVIEW</b>	<b>5</b>
SAPERA ARCHITECTURE .....	5
<i>Application Architecture</i> .....	5
<i>Definition of Terms</i> .....	5
<i>Library Architecture</i> .....	6
DESCRIPTION OF SAPERA MODULES .....	7
THE THREE SAPERA APIS .....	9
HEADER FILES AND LIBRARIES (C API) .....	9
CREATING A SAPERA C APPLICATION .....	9
<i>Visual C++ 2005 / 2008 / 2010 / 2012 /2013</i> .....	9
<i>Borland C++ Builder XE</i> .....	10
API NAMING CONVENTIONS .....	10
<i>Functions</i> .....	10
WORKING WITH HANDLES .....	12
<i>Getting a Server Handle</i> .....	12
<i>Getting the Resource Handle</i> .....	13
ERROR MANAGEMENT .....	15
<i>Interpreting Status Codes</i> .....	15
<i>Monitoring Sopera Errors</i> .....	16
CAPABILITIES AND PARAMETERS .....	17
<i>What is a Capability?</i> .....	17
<i>Accessing a Capability</i> .....	17
<i>What is a Parameter?</i> .....	17
<i>Accessing a Parameter</i> .....	17
<b>ACQUIRING IMAGES</b>	<b>18</b>
REQUIRED MODULES .....	18
FRAME GRABBER ACQUISITION EXAMPLE .....	18
MODIFYING THE FRAME GRABBER PARAMETERS .....	21
<i>Modifying Parameters Individually</i> .....	21
<i>Modifying Parameters by Group</i> .....	22
USING AN INPUT LOOKUP TABLE .....	23
CAMERA ACQUISITION EXAMPLE .....	24
MODIFYING THE CAMERA FEATURES .....	25
<i>Accessing Feature Information and Values</i> .....	25
<i>Writing Feature Values by Group</i> .....	29
<b>DISPLAYING IMAGES</b>	<b>30</b>
REQUIRED MODULES .....	30
DISPLAY EXAMPLE .....	30
MODIFYING THE VIEW PARAMETERS .....	31
<i>View Modes</i> .....	31
<i>Source and Destination Windows and Zooming</i> .....	31
DISPLAYING IN A WINDOWS APPLICATION .....	32

<b>WORKING WITH BUFFERS</b>	<b>34</b>
ROOT AND CHILD BUFFERS .....	34
BUFFER TYPES .....	35
READING AND WRITING A BUFFER .....	37
<i>Simple Buffer Data Access</i> .....	37
<i>Buffer Data Access Using Pointers</i> .....	39
<b>SAPERA FRAME GRABBER ACQUISITION</b>	<b>40</b>
ACQUISITION PARAMETERS & CAPABILITIES.....	40
ACQUISITION FUNCTIONS .....	40
CAMERA MODULE FUNCTIONS .....	54
VIC MODULE FUNCTIONS .....	57
<b>SAPERA CAMERA ACQUISITION</b>	<b>60</b>
ACQDEVICE MODULE.....	60
<i>AcqDevice Parameters</i> .....	60
<i>AcqDevice Functions</i> .....	62
FEATURE MODULE .....	89
<i>Feature Parameters</i> .....	89
<i>Feature Functions</i> .....	96
EVENTINFO MODULE .....	106
<i>EventInfo Parameters</i> .....	106
<i>EventInfo Functions</i> .....	109
<b>SAPERA BASIC MODULES</b>	<b>110</b>
OVERVIEW .....	110
<i>Sapera Function General Return Codes</i> .....	111
BUFFER MODULE.....	111
<i>Capabilities</i> .....	111
<i>Parameters</i> .....	112
<i>Macros</i> .....	118
<i>Functions</i> .....	119
DISPLAY MODULE.....	149
<i>Parameters</i> .....	149
<i>Functions</i> .....	152
FILE MODULE .....	156
<i>Parameters</i> .....	156
<i>Functions</i> .....	159
I/O MODULE .....	169
<i>Definitions</i> .....	169
<i>Capabilities</i> .....	169
<i>Parameters</i> .....	173
<i>Functions</i> .....	176
MODULE .....	183
<i>Parameters</i> .....	183
<i>Functions</i> .....	185
MANAGER MODULE .....	198
<i>CORMAN_SAPERA_VERSION_INFO Structure Definition</i> .....	198
<i>Functions</i> .....	198
TRANSFER MODULE .....	215
<i>Capabilities</i> .....	215
<i>Parameters</i> .....	223
<i>CORXFER_DESC Structure Definition</i> .....	231

<i>Functions</i> .....	232
VIEW MODULE .....	246
<i>Capabilities</i> .....	246
<i>Parameters</i> .....	252
<i>Functions</i> .....	260
<i>CORVIEW_BLIT_DESC Structure Definition</i> .....	268
PCI DEVICE MODULE .....	269
<i>Functions</i> .....	269
<b>ERROR MESSAGES</b> .....	<b>274</b>
BIT DESCRIPTION .....	274
STATUS ID .....	274
LEVEL .....	288
MODULE ID .....	288
<b>MACRO DEFINITIONS</b> .....	<b>289</b>
SAPERA MACROS .....	289
<b>DATA DEFINITIONS</b> .....	<b>291</b>
DATA TYPES.....	291
DATA FORMATS .....	293
<b>APPENDIX A: SERVER MANAGEMENT</b> .....	<b>307</b>
THE SERVER DATABASE .....	307
SERVER MANAGEMENT DIAGRAM.....	307
GETTING A SERVER HANDLE (REVISITED) .....	309
<b>APPENDIX B: FILE FORMATS</b> .....	<b>310</b>
BUFFER FILE FORMATS .....	310
<i>Buffer Data Formats Supported as Input by FileSave Functions</i> .....	312
LUT FILE FORMAT .....	313
<b>APPENDIX C: OBSOLETE MODULES</b> .....	<b>314</b>
GRAPHIC MODULE [OBSOLETE] .....	314
<i>Capabilities [Obsolete]</i> .....	314
<i>Parameters [Obsolete]</i> .....	314
<i>Functions [Obsolete]</i> .....	316
<b>CONTACT INFORMATION</b> .....	<b>327</b>
SALES INFORMATION.....	327
TECHNICAL SUPPORT.....	327

# Introduction

---

## Overview of the Manual

The *Sapera LT Basic Modules Reference Manual* is the main reference for the Sapera C API. The manual is divided in two: the first part presents an overview of how to use the API, the second part describes the API's functions and parameters.

The *Sapera Acquisition Parameters Reference Manual* complements the Sapera LT Basic Modules Reference manual with a description of all the acquisition parameters, capabilities and definitions.

This manual covers the following topics:

- **Sapera C API Overview**

Information and examples on using the Sapera C API

- **Sapera Acquisition Modules API**

Description of the Sapera Acquisition modules and their functions.

Refer to the *Sapera LT Acquisition Parameters Reference Manual* for a description of the acquisition parameters and capabilities.

- **Sapera Basic Modules API**

Description of the Sapera Basic modules and their functions.

- **Error Messages**

Description of the error message returned by Sapera function calls.

- **Macro Definitions**

Description of all Sapera supplied macros.

- **Data Definitions**

Description of all data types used in Sapera.

- **Appendix A: Server Management**

Descriptions of acquisition controls including camera parameters and capabilities.

- **Appendix B: File Formats**

Description of all buffer, graphic font, and LUT file formats supported by Sapera LT.

- **Teledyne DALSA Contact Information**

Phone numbers, web site, and important email addresses.


# Sapera LT C API Overview

## Sapera Architecture

The following section describes application architecture, related terms, and illustrates Sapera's library architecture.

### Application Architecture

Whichever API is used (Sapera++, Sapera .NET, or Standard C), the Sapera LT modular architecture allows applications to be distributed on different Sapera LT servers. Each server can run either on the host computer or on a Teledyne DALSA device. Sapera LT calls are routed to different servers via the Sapera LT messaging layer in a fashion completely independent of the underlying hardware.



## Definition of Terms

### What is a server?

A Sapera Server is an abstract representation of a physical device like a frame-grabber, a processing board, or a desktop PC. In general, a Teledyne DALSA board is a server. Some processing boards, however, may contain several servers; this is true when using multi-processor boards.

A server allows Sapera applications to interact with the server's resources.

### What is a static resource?

Resources attached to a physical device are called static resources. For example, a frame grabber can have an acquisition resource, display resource, and a processor resource. These resources can be manipulated to control a physical device through a Sapera Server.

## What is a dynamic resource?


A dynamic resource is an abstract representation of data storage (such as a buffer, lookup table, object, and so forth) or links that connect the data storage to static resources. Unlike static resources, dynamic resources are not dependent on physical devices; therefore, users on a specified server can freely create dynamic resources.

## What is a module?

A module is a set of functions used to access and/or control a static or a dynamic resource. The complete Sopera API is composed of a series of modules organized in a particular architecture. These modules are described in the Description of Sopera Modules section.

## Library Architecture

The following block diagram illustrates the Sopera Library architecture illustrating all the module interconnections. In this diagram, standard rectangles represent *dynamic resource modules* while rounded rectangles represent *static resource modules*.





---

# Description of Sopera Modules

Below is a brief description of the modules (blocks) and their connections to other modules.

## Acquisition Module (Acq)

The Acquisition module refers to a static resource. It is used to control an acquisition device that is present on any Teledyne DALSA board that supports an acquisition section. The Acquisition module includes the functionality to read and write the acquisition parameters individually. Optionally, it can work in conjunction with both the Cam and Vic modules for grouping and storing parameters. The Transfer module, however, is required for synchronizing (starting or stopping) the acquisition process. This module is used by the Transfer module and uses the Cam and Vic modules.

## Cam and Vic Modules

These two modules refer to dynamic resources. They are used for grouping and storing acquisition parameters related to the camera (cam) and video-input-conditioning (vic), respectively. Examples of *Cam* parameters include video format, number of input bits and the pixel clock, while examples of *Vic* parameters include brightness, contrast, and saturation.



**Note:** The *Cam* and *Vic* modules are strictly dedicated to the usage of cameras hooked to a frame grabber. To manipulate a GigE camera refer to the *AcqDevice* module.

## AcqDevice Module

The AcqDevice module refers to a static resource. It is used to control a Teledyne DALSA camera device (for example, a GigE camera). The AcqDevice module includes the functionality to read and write the feature values individually or all at once. The module also allows to save/restore the features to/from a file. The Transfer module, however, is required for synchronizing (starting or stopping) the acquisition process. This module is used by the Transfer module and uses the Feature module.

## Feature Module

The Feature module refers to a dynamic resource. It is used to retrieve the feature information from the AcqDevice module. Each feature supported by the AcqDevice module provides a set of capabilities such as name, type, access mode, and so forth, that can be obtained through the feature module.

## EventInfo Module

The EventInfo module refers to a dynamic resource. It is used to retrieve information from the events sent by the AcqDevice module. Each event supported by the AcqDevice module provides a set of parameters that can be accessed individually through the EventInfo module.

## Transfer Module (Xfer)

The Transfer module refers to a dynamic resource. It is used to establish a connection and perform a data transfer between a source and a destination resource. For example, it is used to control an acquisition process by using the Acquisition resource as the source and a Buffer resource as the destination. The Transfer module uses the Acq, AcqDevice, and Buffer modules.

## Buffer Module

The Buffer module refers to a dynamic resource. The module includes the functionality to manipulate a generic buffer that can be either one-dimensional (a vector) or two-dimensional (an image). Buffers are the base data storage resources of Sopera. The Buffer module is used by the Transfer, View and Graphic modules.

## **LookUp Table Module (Lut)**

The LookUp Table module refers to a dynamic resource. The module includes the functionality to manipulate a generic LookUp table. The LookUp Table may be used as an input (in an acquisition process), an output (in a display process), or processing LookUp Table. The Lookup Table module is used by the Acq, AcqDevice, and View modules.

## **View Module**

The View module refers to a dynamic resource. It is used to establish a connection and perform a data transfer between the Buffer and Display resources. For example, it is used to display a buffer by transferring its data from system memory to video memory. The View module uses the Buffer and Display modules.

## **File Module**

The File module refers to a dynamic resource. It is used to exchange images between buffers and files. Various file formats are supported (for example, TIFF, BMP, RAW, JPEG, AVI, and the Teledyne DALSA Custom Format - CRC).

## **Display Module**

The Display module refers to a static resource. It is used to control a display device that is present on the system display (your computer video card) or on any Teledyne DALSA board supporting a display section. The Display module includes the functionality to read and write display parameters. In cases where the buffer is located outside video memory (system memory or off-screen memory), the View module transfers data to video memory. The Display module is used by the View module.

---

# The Three Sopera APIs

Three different APIs are available under Sopera:

- Sopera++ classes (based on C++ language)
- Sopera .NET classes (based on .NET languages)
- Sopera Standard API (based on C language)

The following sections will illustrate the standard C API. For C++ and .NET API information consult the Sopera++ Programmer's Manual and the Sopera .NET Programmer's Manual respectively.

---

## Header Files and Libraries (C API)

The following files are provided for building C applications with Sopera LT.

File Name	Description	Location
<b>corapi.h</b>	Main header file	<b>Sopera\Include</b>
<b>corapi.lib</b>	32-bit C library for Visual C++	<b>Sopera\Lib\Win32</b>
<b>corapi.lib</b>	32-bit C library for Borland C++ Builder XE1 to XE5	<b>Sopera\Lib\Win32\Borland</b>
<b>corapi.lib</b>	64-bit C library for Visual C++	<b>Sopera\Lib\Win64</b>

---

## Creating a Sopera C Application

The following sections describe how to create a Sopera C application in Visual C++ 2005/2008/2010/2012/2013, and Borland C++ Builder XE1 to XE5.

### Visual C++ 2005 / 2008 / 2010 / 2012 / 2013

To compile and link an application that uses the Sopera C library:

- Include corapi.h in the program source code (it includes all other required headers)
- Add \$(SAPERADIR)\Include in Project | Properties | C/C++ | General | Additional Include Directories.
- For a 32-bit application, insert \$(SAPERADIR)\Lib\Win32\corapi.lib in Project | Add Existing Item ...
- For a 64-bit application, insert \$(SAPERADIR)\Lib\Win64\corapi.lib in Project | Add Existing Item ...
- In Project | Properties | C/C++ | Code Generation | Runtime Library, choose the option Multi-threaded DLL (in release mode) or Multi-threaded Debug DLL (in debug mode).

## Borland C++ Builder XE

Follow the steps below to compile and link a 32-bit application that uses the Sopera C library:

- Include corapi.h in the program source code (it includes all other required headers).
- Add \$(SAPERADIR)\Include in Project | Options... | C++ Compiler | Paths and Defines | Include search path.
- Insert \$(SAPERADIR)\Lib\Win32\Borland\corapi.lib in Project | Add to Project ...

---

### Writing Windows Applications (.exe) that use the Sopera LT Libraries

When using the Standard C API, you must call CorManOpen before any other API function. You must also call CorManClose after the last API function.

---

### Writing Windows DLLs that use the Sopera LT Libraries

When using the Standard C API, you must call CorManOpen before any other API function. You must also call CorManClose after the last API function. However, you must not call these from theDllMain function.

---

## API Naming Conventions

The following describes naming conventions for API functions.

### Functions

The API functions follow standard naming conventions. First, all API functions are prefixed with “Cor”, derived from “Coreco”. This prefix is followed by the module name, as described before in the architecture, and next by the function name. All functions also return an error code. Below is the syntax description with some examples.

```
CORSTATUS Cor<module name><function name>(...)
```

Examples:

```
CORSTATUS status;           // Status code
status = CorBufferClear(...) // Clear function of Buffer module
status = CorXferStart(...)   // Start function of Transfer module
status = CorLutNormal(...)   // Generate a normal lookUp table
```

---

### Handles

All API functions refer to a server and/or a module handle (see Working with Handles). The server handle is always named CORSERVER. The module handles use the following syntax: COR<module name>

Examples:

```
CORSERVER hServer; // Handle to a server
CORBUFFER hBuffer; // Handle to a buffer
CORACQ hAcq;       // Handle to an acquisition
CORDISPLAY hDisplay; // Handle to a display
```

---

## Capabilities and Parameters

Each resource may have a series of capabilities and parameters (see Capabilities and Parameters) that follow the syntax below:

For a capability number:

- COR<module name>\_CAP\_<capability name>

For a parameter number:

- COR<module name>\_PRM\_<capability name>

And for each of the possible values:

- COR<module name>\_VAL\_<capability name>\_<value description>

### Examples:

```
CORACQ_CAP_CHANNEL           // Capability Channel of Acquisition module
CORACQ_PRM_CHANNEL           // Parameter Channel of Acquisition module

CORACQ_VAL_CHANNEL_SINGLE    // Single channel value for Acquisition module
CORACQ_VAL_CHANNEL_DUAL      // Dual channel value for Acquisition module
```

---

## Enumerated Arguments

A function may have one or more enumerated arguments. The list of possible values for such arguments are as follows:

- COR<module name>\_<value description>

Example:

```
CORBUFFER_FILEFORMAT_BMP     // Bitmap file format in the buffer module
CORBUFFER_FILEFORMAT_TIFF    // TIFF file format in the buffer module
```

---

# Working with Handles

Accessing resource data in Sopera can only be accomplished by calling an API function. Therefore, servers and resources are all assigned a handle. A handle is a structure containing the necessary information to access internal resource data. To get a handle to a resource involves two steps:

- Getting a server handle.
- Getting the resource handle.

## Getting a Server Handle

There are three ways to get a server handle in Sopera:

- The default server, on which the current application is running, is obtained by calling the following function:

```
CORSERVER hServer;    // Declare a server handle

// Initialize Sopera API
CorManOpen();

// Get the default server handle
hServer = CorManGetLocalServer();
```

- You may also enumerate all of the currently available Sopera Servers, using for each an index that ranges from 0 to *nServer*-1, where *nServer* is the number of servers found by the API.

```
CORSTATUS status;      // Declare status code
UINT32 nCount;         // Declare a server count
UINT32 nIndex;         // Declare a server index
char szName[64];       // Declare a character string for returned name
CORSERVER hServer;     // Declare a server handle

// Initialize Sopera API
status = CorManOpen();

// Get the server count
status = CorManGetServerCount(&nCount);

// Get the server handle from an index
status = CorManGetServerByIndex(nIndex, szName, &hServer);
```

- You may also specify the exact server name.

```
CORSTATUS status;      // Declare status code
CORSERVER hServer;     // Declare a server handle

// Initialize Sopera API
status = CorManOpen();

// Get the server handle by specifying a name
status = CorManGetServerByName("X64-CL_1", &hServer);
```

Use the following function to release the server handle when you have finished using it:

```
CORSTATUS status;      // Declare status code
CORSERVER hServer;     // Declare a server handle

// Release the specified server handle
status = CorManReleaseServer(hServer);
```

A more comprehensive discussion on this topic is found in [Appendix A: Server Management](#).

## Getting the Resource Handle

The following describes getting static and creating dynamic handle resources.

---

### Getting a Handle to a Static Resource

As noted in the Architecture Section, static resources are related to devices on a server. Therefore, their number depends on the specific server where they are located. Each static resource module includes a function to access the resource count, as in the following example:

```
CORSTATUS status;           // Declare status code
CORSERVER hServer;          // Declare a server handle
UINT32 nAcqCount;           // Declare a acquisition count
UINT32 nDisplayCount;       // Declare a display count

// Initialize Sopera API
status = CorManOpen();

// Get server handle
...

status = CorAcqGetCount(hServer, &nAcqCount);           // Get acquisition count
status = CorDisplayGetCount(hServer, &nDisplayCount);    // Get display count
```

You then obtain the resource handle by specifying an index ranging from 0 to *nxxxCount*-1. When the handle is no longer used, it must be released.

```
CORSTATUS status;           // Declare status code
CORSERVER hServer;          // Declare a server handle
CORACQ hAcq;                // Declare an acquisition handle
CORDISPLAY hDisplay;        // Declare an display handle

// Initialize Sopera API
status = CorManOpen();

// Get server handle
...

// Get resource handles
status = CorAcqGetHandle(hServer, 0, &hAcq);
status = CorDisplayGetHandle(hServer, 0, &hDisplay);

// Use them
...

// Release handles when finished
status = CorAcqRelease(hAcq);
status = CorDisplayRelease(hDisplay);

// Close Sopera API
status = CorManClose();
```

---

## Creating a Handle for a Dynamic Resource

Because dynamic resources are not device-based their potential number is unlimited. Each dynamic resource has its own creation arguments. Below is an example showing the creation of a buffer and a lookup table.

```
CORSTATUS status;      // Declare status coed
CORSERVER hServer;     // Declare a server handle
CORBUFFER hBuffer;     // Declare a buffer handle
CORKUT hLut;           // Decalre a LUT handle

// Initialize Sopera API
status = CorManOpen();

// Get server handle
...

// Create resource handles
status = CorBufferNew(hServer, 640, 480, CORBUFFER_VAL_FORMAT_UINT8, 0, &hBuffer);
status = CorLutNew(hServer, 256, CORKUT_VAL_FORMAT_UINT8, &hLut);

// Use them
...

// Free handles when finished
status = CorBufferFree(hBuffer);
status = CorLutFree(hLut);

// Close Sopera API
status = CorManClose();
```



---

# Error Management

The following describes interpreting status codes and monitoring Sapera errors.

## Interpreting Status Codes

All Sapera functions return a status code. If the function executes successfully, it returns the `CORSTATUS_OK` status code. If an error is detected, the status code describes the nature and the level of the error within the called function. Some status codes also contain additional information related to the specific error. Furthermore, all status codes include a module identifier that indicates which module the function belongs to. The example below demonstrates how to get the different fields of the status code.

```
CORSTATUS status;      // Status code
UINT32 errorId;        // Error identifier
UINT32 errorInfo;      // Additional specific information
UINT32 errorLevel;     // Error level
UINT32 module;         // Module of the function called

// Initialize Sapera API
status = CorManOpen();

// Call an API function
status = CorXXX(...);

// Extract the status code's ID
// If the function succeeds will return CORSTATUS_OK,
// otherwise will return CORSTATUS_xxx.
// See Reference Manual for the complete list of error ID's

errorId = CORSTATUS_ID(status);

// Extract the status code's additional information
// This information is specific to the status code's ID
// Some status code don't support this field
// See Reference Manual for a detailed description of the values.

errorInfo = CORSTATUS_INFO(status);

// Extract the status code's level
// Will return one of the following values:
// CORSTATUS_LEVEL_FAT    Fatal error
// CORSTATUS_LEVEL_ERR    General error
// CORSTATUS_LEVEL_WRN    Warning
// CORSTATUS_LEVEL_INF    Information

errorLevel = CORSTATUS_LEVEL(status);

// Extract the module
// Will return one of the module identifier:
// CORSTATUS_MODULE_ACQ
// CORSTATUS_MODULE_BUFFER
// ...
// See Reference Manual for the complete list of modules

module = CORSTATUS_MODULE(status);

// Close Sapera API
status = CorManClose();
```

You can obtain an associated description string by calling the function `CorManGetStatusText`, which returns a string including a description of the status code.

```
CORSTATUS status;      // Status code
char szText[256];      // Status text

// Call an API function
status = CorXXX(...);

// Get the associated text string
CorManGetStatusText(status, szText, sizeof(szText), NULL, 0);
```

You can also obtain more detailed information by calling the function `CorManGetStatusTextEx`, which returns a string for each field of the status code.

```
CORSTATUS status;
char id[128], info[128], level[64], module[64];

// Call an API function
status = CorXXX(...);

// Get the associated text strings
CorManGetStatusTextEx(status, id, sizeof(id), info, sizeof(info), level, sizeof(level), module, sizeof(module));
```

## Monitoring Sapera Errors

The **logview.exe** utility program included with Sapera provides an easy way to view status code returned by API functions. **logview.exe** is a simple Windows program that includes a list box that stores the status code description strings as soon as they are logged in the API. Options allow you to modify the different fields for display.

It is recommended to start **LogView** before starting your application and then let it run so it can be referred to any time a detailed error description is required. However, errors are also stored by a low-level service (running in the background), even if **LogView** is not running. Therefore, it is possible to run it only when a problem occurs while running your application.

---

# Capabilities and Parameters

Resources can be characterized by a set of capabilities and parameters. Together they define a resource's ability and current state.

## What is a Capability?

A capability, as its name implies, is a value or set of values that describe what a resource can do. Capabilities are used to determine the possible valid values that can be applied to a resource's parameters. They are read-only.

## Accessing a Capability

A capability can be obtained from a resource by using the `Cor<module name>GetCap` function. It has the following prototype:

```
CorxxxGetCap(CORxxx handle, UINT32 cap, void *value)
```

- *handle*: valid handle to a resource
- *cap*: valid capability of the resource
- *value*: buffer of proper size to store the capability value(s). The size of a capability can be obtained by using the macro `CORCAP_GETSIZE(cap)`

## What is a Parameter?

A parameter describes a characteristic of a resource. It can be read/write or read-only.

## Accessing a Parameter

A parameter can be read by using the `Cor<module name>GetPrm` function. It has the following prototype:

```
CorxxxGetPrm(CORxxx handle, UINT32 prm, void *value)
```

- *handle*: valid handle to a resource
- *prm*: valid parameter of the resource
- *value*: buffer of proper size to store the parameter value. The size (in bytes) of a parameter can be obtained by using the macro `CORPRM_GETSIZE(prm)`

You can write parameters with the `Cor<module name>SetPrm` and `Cor<module name>SetPrmEx` functions. They have the following prototypes:

```
CorxxxSetPrm(CORxxx handle, UINT32 prm, UINT32 value)
CorxxxSetPrmEx(CORxxx handle, UINT32 prm, const void *value)
```

- *handle*: valid handle to a resource
- *prm*: valid parameter of the resource
- *value*: buffer of proper size to store the parameter value. The size in bytes of a parameter can be obtained by using the macro `CORPRM_GETSIZE(prm)`

The "Ex" function is used to write to a parameter whose value is greater than four bytes.

# Acquiring Images

---

## Required Modules

You need three Spera modules to initiate the acquisition process:

- **Acq or AcqDevice:** The “Acq” module is needed if you are using a frame grabber while the “AcqDevice” module is needed if you are using a camera directly connected to your PC, such as a GigE camera.
- **Buffer:** Dynamic resource used to store the acquired data. The buffer can be allocated using most buffer types to enable the transfer (see the “Working with Buffers” section for more information about buffer types).
- **Transfer:** Dynamic resource used to link the acquisition to the buffer and to synchronize the acquisition operations.

---

## Frame Grabber Acquisition Example

The example below demonstrates how to grab a live image into a buffer allocated in system memory, using the X64-CL board as an acquisition device.

As shown in this example, acquiring an image requires two files to configure the acquisition hardware: a CAM file and a VIC file. The former defines the characteristics of the camera whereas the latter defines how the camera and the acquisition hardware will be used. Refer to the CamExpert online help file for information on CAM and VIC video source parameter files.

Once the acquisition module is initialized using the CAM and VIC files, some parameters are retrieved from it (acquisition width, height, and format) and are used to create a compatible buffer.

Before starting the transfer, you must create a transfer path between the acquisition resource and the buffer resource. Furthermore, when requesting a transfer stop, you must call *CorXferWait* to wait for the transfer process to terminate completely.

```

// Transfer callback function: called each time a complete frame is transferred
//
CORSTATUS CCONV XferCallback (void *context, UINT32 eventType, UINT32 eventCount)
{
    // Display the last transferred frame
    CorViewShow(*(CORVIEW*) context);
    return CORSTATUS_OK;
}

//
// Example program
//
main()
{
    CORSTATUS status;        // Error code
    CORSERVER hSystem;       // System server handle
    CORSERVER hBoard;        // Board server handle
    CORCAM hCam;              // CAM handle
    CORVIC hVic;              // VIC handle
    CORACQ hAcq;              // Acquisition handle
    CORBUFFER hBuffer;        // Buffer handle
    CORXFER hXfer;            // Transfer handle
    CORVIEW hView;            // View handle
    CORDISPLAY hDisplay;     // Display handle
    UINT32 width, height, format;

    // Initialize Sopera API
    status = CorManOpen();

    // Get server handles (system and board)
    hSystem = CorManGetLocalServer();
    status = CorManGetServerByName("X64-CL_1", &hBoard);

    // Get acquisition handle
    status = CorAcqGetHandle(hBoard, 0, &hAcq); // 0 = First instance

    // Create CAM/VIC handles
    status = CorCamNew(hSystem, &hCam); // Camera
    status = CorVicNew(hSystem, &hVic); // Video-Input-Conditionning

    // Load CAM/VIC parameters from file into system memory
    // The acquisition hardware is not initialized at this point
    status = CorCamLoad(hCam, "rs170.cca");
    status = CorVicLoad(hVic, "rs170.cvi");

    // Download the CAM/VIC parameters to the acquisition module
    // The acquisition hardware is now initialized
    status = CorAcqSetPrms(hAcq, hVic, hCam, FALSE);

    // Create a buffer compatible to acquisition
    status = CorAcqGetPrm(hAcq, CORACQ_PRM_SCALE_HORZ, &width);
    status = CorAcqGetPrm(hAcq, CORACQ_PRM_SCALE_VERT, &height);
    status = CorAcqGetPrm(hAcq, CORACQ_PRM_OUTPUT_FORMAT, &format);
    status = CorBufferNew(hSystem, width, height, format,
        CORBUFFER_VAL_TYPE_SCATTER_GATHER, &hBuffer);

    // Create a transfer handle to link acquisition to buffer
    status = CorXferNew(hBoard, hAcq, hBuffer, NULL, &hXfer);

    // Register a callback function on "End-Of-Frame" events
    status = CorXferRegisterCallback(hXfer, CORXFER_VAL_EVENT_TYPE_END_OF_FRAME,
        XferCallback, (void *)&hView);

    // Activate the connection between acquisition and buffer
    status = CorXferConnect(hXfer);

    // Get display handle
    status = CorDisplayGetHandle(hSystem, 0, &hDisplay);

    // Create a view handle and assign it to a HWND
    status = CorViewNew(hSystem, hDisplay, hBuffer, CORVIEW_VAL_MODE_AUTO_DETECT,
        &hView);
    status = CorViewSetPrm(hView, CORVIEW_PRM_HWND, -1); // -1: create new window

    // Start a continuous transfer (live grab)
    status = CorXferStart(hXfer, CORXFER_CONTINUOUS);
}

```

```

printf("Press any key to stop grab\n");
getchar(); // wait until a key has been hit

// Stop the transfer and wait (timeout = 5 sec)
status = CorXferStop(hXfer);
status = CorXferWait(hXfer, 5000);

// Break the connection between acquisition and buffer
status = CorXferDisconnect(hXfer);

printf("Press any key to terminate\n");
getchar();

// Release handles when finished (in the reverse order)
status = CorViewFree(hView);
status = CorDisplayRelease(hDisplay);
status = CorXferFree(hXfer);
status = CorBufferFree(hBuffer);
status = CorVicFree(hVic);
status = CorCamFree(hCam);
status = CorAcqRelease(hAcq);

// Close Sopera API
status = CorManClose();

return 0;
}

```

---

# Modifying the Frame Grabber Parameters

The following describes how to modify frame grabber parameters individually or by group.

## Modifying Parameters Individually

Acquisition parameters can be modified individually by using the *CorAcqSetPrm* and/or *CorAcqSetPrmEx* functions. When a new parameter value is requested, that value is verified against the current state of the acquisition module and the acquisition module capabilities. If the modification request is denied because the parameter is dependent on other parameters, then all the parameters in question must be modified by group, in which case you must refer to the next section.

```
CORSTATUS status;          // Error code
CORSERVER hSystem;         // System server handle
CORSERVER hBoard;          // Board server handle
CORACQ hAcq;               // Acquisition handle
UINT32 capSync;            // Sync capability (as an example)

// Initialize Spera API
status = CorManOpen();

// Get server handles
hSystem = CorManGetLocalServer();
status = CorManGetServerByName("X64-CL_1", &hBoard);

// Get acquisition handle
status = CorAcqGetHandle(hBoard, 0, &hAcq);          // 0 = First instance

// Verify if sync on composite sync is supported
status = CorAcqGetCap(hAcq, CORACQ_CAP_SYNC, &capSync);
if (!status && (capSync & CORACQ_VAL_SYNC_COMP_SYNC))
{
    // Change the sync source to Composite Sync
    status = CorAcqSetPrm(hAcq, CORACQ_PRM_SYNC, CORACQ_VAL_SYNC_COMP_SYNC);
}

// Do something else
...

// Release handles when finished
status = CorAcqRelease(hAcq);

// Close Spera API
status = CorManClose();
```

## Modifying Parameters by Group

Acquisition parameters can be modified by group using the *CorAcqSetPrms* function. When a new set of values is requested, all modified parameters are verified against the given state and capabilities of the acquisition module.

```
CORSTATUS status;          // Error code
CORSERVER hSystem;         // System server handle
CORSERVER hBoard;          // Board server handle
CORACQ hAcq;               // Acquisition handle
CORCAM hCam;               // CAM handle
CORVIC hVic;               // VIC handle

// Initialize Sopera API
status = CorManOpen();

// Get server handles
hSystem = CorManGetLocalServer();
status = CorManGetServerByName("X64-CL_1", &hBoard);

// Get acquisition handle
status = CorAcqGetHandle(hBoard, 0, &hAcq);      // 0 = First instance

// Create a CAM resource (Camera)
status = CorCamNew( hSystem, &hCam);

// Create a VIC resource (Video-Input-Conditioning)
status = CorVicNew( hSystem, &hVic);

// Get current state of the acquisition module and lock parameters
status = CorAcqGetPrms(hAcq, hVic, hCam, TRUE);

// Modify parameters individually
status = CorVicSetPrm(hVic, CORVIC_PRM_CROP_WIDTH, 640);
status = CorVicSetPrm(hVic, CORVIC_PRM_CROP_HEIGHT, 480);
status = CorVicSetPrm(hVic, CORVIC_PRM_SCALE_HORZ, 640);
status = CorVicSetPrm(hVic, CORVIC_PRM_SCALE_VERT, 480);

// Apply the modified parameters on the acquisition module
status = CorAcqSetPrms(hAcq, hVic, hCam, TRUE);

// Do something else
...

// Release handles when finished
status = CorCamFree(hCam);
status = CorVicFree(hVic);
status = CorAcqRelease(hAcq);

// Close Sopera API
status = CorManClose();
```



---

# Using an Input Lookup Table

An Input Lookup Table is first created using the LUT module API and then transferred to the acquisition module (if it has input lookup table capability). The example below illustrates the steps required.

```
CORSTATUS status;           // Error code
CORSERVER hSystem;          // System server handle
CORSERVER hBoard;           // Board server handle
CORACQ hAcq;                // Acquisition handle
CORLUT hLut;                // Lut handle
UINT32 nLut;                // Number of Acquisition LUT
UINT32 pixelDepth;          // Number of bits/pixel to acquire
UINT32 lutFormat;           // Acquisition LUT format
UINT32 entries;             // Total number of entries in the LUT

// Initialize Sapera API
status = CorManOpen();

// Get server handles
hSystem = CorManGetLocalServer();
status = CorManGetServerByName("X64-CL_1", &hBoard);

// Get acquisition handle
status = CorAcqGetHandle(hBoard, 0, &hAcq);    // 0 = First instance

// Check if the acquisition device has at least one lookup table available
status = CorAcqGetPrm(hAcq, CORACQ_PRM_LUT_MAX, &nLut);

if( nLut > 0)
{
    // Create a LUT resource
    // Get the pixel depth and current LUT format from the acquisition module
    status = CorAcqGetPrm(hAcq, CORACQ_PRM_PIXEL_DEPTH, &pixelDepth);
    status = CorAcqGetPrm(hAcq, CORACQ_PRM_LUT_FORMAT, &lutFormat);

    // Calculate the number of entries needed for the LUT
    entries = 1 << pixelDepth;

    // Create LUT resource
    status = CorLutNew(hSystem, entries, lutFormat, &hLut);

    // Initialize a reverse LUT
    status = CorLutReverse(hLut);

    // Load LUT to acquisition module LUT #0
    status = CorAcqSetLut(hAcq, hLut, 0);

    // Select LUT #0 as the active LUT
    status = CorAcqSetPrm(hAcq, CORACQ_PRM_LUT_NUMBER, 0);

    // Enable LUTs
    status = CorAcqSetPrm(hAcq, CORACQ_PRM_LUT_ENABLE, TRUE);

    // Release handles when finished
    status = CorLutFree(hLut);
}
status = CorAcqRelease(hAcq);

// Close Sapera API
status = CorManClose();
```

---

# Camera Acquisition Example

The example below demonstrates how to grab a live image into a buffer allocated within system memory using the *Genie M640* camera as an acquisition device.

Acquiring an image can be performed either by using the camera default settings (feature values stored in the camera) or by loading a configuration file. The configuration file can be generated using *CamExpert*.

Once the AcqDevice module is initialized (with or without using a configuration file), some parameters are retrieved from it (acquisition width, height, and format) and are used to create a compatible buffer.

Before starting the transfer, you must create a transfer path between the AcqDevice resource and the buffer resource. Furthermore, when requesting a transfer stop, you must call *CorXferWait* to wait for the transfer process to terminate completely.

```
// Transfer callback function: called each time a complete frame is transferred
//
CORSTATUS CCONV XferCallback (void *context, UINT32 eventType, UINT32 eventCount)
{
    // Displays the last transferred frame
    CorViewShow(*(CORVIEW*) context);
    return CORSTATUS_OK;
}

//
// Example program
//
main()
{
    CORSTATUS status;           // Error code
    CORSERVER hSystemServer;    // System server handle
    CORSERVER hAcqServer;       // Camera server handle
    CORACQDEVICE hAcqDevice;    // Camera handle
    CORBUFFER hBuffer;          // Buffer handle
    CORXFER hXfer;              // Transfer handle
    CORVIEW hView;              // View handle
    CORDISPLAY hDisplay;        // Display handle
    UINT32 width, height, format;

    // Initialize Sapera API
    status = CorManOpen();

    // Gets server handles (system and camera)
    hSystemServer = CorManGetLocalServer();
    status = CorManGetServerByName("Genie_M640_1", &hAcqServer);

    // Gets camera handle
    status = CorAcqDeviceGetHandle(hAcqServer, 0, &hAcqDevice); // 0 = First instance

    // Optionally loads a configuration file to program the camera
    // Otherwise, the camera will work with its default settings
    status = CorAcqDeviceLoadFeatures(hAcqDevice, "Genie_M640_Example.ccf");

    // Creates a buffer compatible with camera
    status = CorAcqDeviceGetFeatureValueByName(hAcqDevice, "Width", &width,
        sizeof(width));
    status = CorAcqDeviceGetFeatureValueByName(hAcqDevice, "Height", &height,
        sizeof(height));
    status = CorAcqDeviceGetFeatureValueByName(hAcqDevice, "SaperaBufferFormat",
        &format, sizeof(format));
    status = CorBufferNew(hSystemServer, width, height, format,
        CORBUFFER_VAL_TYPE_SCATTER_GATHER, &hBuffer);

    // Creates a transfer handle to link camera to buffer
    status = CorXferNew(hAcqServer, hAcqDevice, hBuffer, NULL, &hXfer);

    // Registers a callback function on "End-Of-Frame" events
    status = CorXferRegisterCallback(hXfer, CORXFER_VAL_EVENT_TYPE_END_OF_FRAME,
        XferCallback, (void *)&hView);

    // Activates the connection between camera and buffer
    status = CorXferConnect(hXfer);
```

```

// Gets display handle
status = CorDisplayGetHandle(hSystemServer, 0, &hDisplay);

// Creates a view handle and assign it to a HWND
status = CorViewNew(hSystemServer, hDisplay, hBuffer,
    CORVIEW_VAL_MODE_AUTO_DETECT, &hView);
status = CorViewSetPrm(hView, CORVIEW_PRM_HWND, -1); // -1: create new window

// Starts a continuous transfer (live grab)
status = CorXferStart(hXfer, CORXFER_CONTINUOUS);

printf("Press any key to stop grab\n");
getch(); // wait until a key has been hit

// Stops the transfer and waits (timeout = 5 sec)
status = CorXferStop(hXfer);
status = CorXferWait(hXfer, 5000);

// Breaks the connection between acquisition and buffer
status = CorXferDisconnect(hXfer);

printf("Press any key to terminate\n");
getch();

// Releases handles when finished (in the reverse order)
CorViewFree(hView);
CorDisplayRelease(hDisplay);
CorXferFree(hXfer);
CorBufferFree(hBuffer);
CorAcqDeviceRelease(hAcqDevice);
CorManReleaseServer(hAcqServer);

// Close Sapera API
status = CorManClose();

return 0;
}

```

---

## Modifying the Camera Features

The following describes how to modify camera features individually or by group.

### Accessing Feature Information and Values

The following example shows how features of the camera can be accessed. Information such as type, range and access mode can be retrieved for each supported feature. The AcqDevice module also allows modifying the feature values by directly writing to the camera. In some circumstances a set of feature values are tightly coupled together and must therefore be written to the camera all at once. The next section shows how to proceed in such a case.

```

//
// Callback Function
//
CORSTATUS CCONV CameraCallback(void *context, COREVENTINFO hEventInfo)
{
    CORSTATUS status;
    UINT32 eventCount;
    UINT32 eventIndex;
    char eventName[64];
    CORACQDEVICE hAcqDevice = (CORACQDEVICE) context;

    // Retrieve count, index and name of the received event
    status = CorEventInfoGetPrm(hEventInfo, COREVENTINFO_PRM_EVENT_COUNT, &eventCount);
    status = CorEventInfoGetPrm(hEventInfo, COREVENTINFO_PRM_EVENT_INDEX, &eventIndex);
    status = CorAcqDeviceGetEventNameByIndex(hAcqDevice, eventIndex, eventName,
        sizeof(eventName));

    // Check for "Feature Value Changed" event
    if (strcmp(eventName, "Feature Value Changed") == 0)
    {
        // Retrieve index and name of the feature that has changed
        int featureIndex;
        char featureName[64];
        status = CorEventInfoGetPrm(hEventInfo, COREVENTINFO_PRM_FEATURE_INDEX,
            &featureIndex);
        status = CorAcqDeviceGetFeatureNameByIndex(hAcqDevice, featureIndex,
            featureName, sizeof(featureName));
    }

    return CORSTATUS_OK;
}

//
// Main Program
//
main()
{
    CORSTATUS status;
    CORSERVER hSystemServer, hAcqServer;
    CORACQDEVICE hAcqDevice;
    UINT32 featureCount, featureIndex;
    CORFEATURE hFeature;
    UINT32 value, min, max, inc;
    UINT32 enumCount, enumIndex, enumValue;
    char enumString[64];
    UINT32 lutIndex, lutNEntries, lutFormat;
    CORLUT hLut;
    UINT32 numEvents, eventIndex;
    char eventName[64];

    // Initialize Sapera API
    status = CorManOpen();

    // Get handle to the system server
    hSystemServer = CorManGetLocalServer();

    // Get handle to the camera server
    status = CorManGetServerByName("Genie_M640_1", &hAcqServer);

    // Get handle to the camera resource
    status = CorAcqDeviceGetHandle(hAcqServer, 0, &hAcqDevice);

    // Get the number of features provided by the camera
    status = CorAcqDeviceGetFeatureCount(hAcqDevice, &featureCount);

    // Create an empty feature object (to receive information)
    status = CorFeatureNew(hAcqServer, &hFeature);

    //
    // Example 1 : Browse through the feature list
    //
    for (featureIndex = 0; featureIndex < featureCount; featureIndex++)
    {
        char featureName[CORPRM_GETSIZE(CORFEATURE_PRM_NAME)];
        UINT32 featureType;

        // Get information from current feature

```

```

// Get feature object
status = CorAcqDeviceGetFeatureInfoByIndex(hAcqDevice, featureIndex, hFeature);

// Extract name and type from object
status = CorFeatureGetPrm(hFeature, CORFEATURE_PRM_NAME, featureName);
status = CorFeatureGetPrm(hFeature, CORFEATURE_PRM_TYPE, &featureType);

// Get/set value from/to current feature
switch (featureType)
{
    // Feature is a 64-bit integer
    case CORFEATURE_VAL_TYPE_INT64:
    {
        UINT64 value;
        status = CorAcqDeviceGetFeatureValueByIndex(hAcqDevice, featureIndex,
            &value, sizeof(value));
        value += 10;
        status = CorAcqDeviceSetFeatureValueByIndex(hAcqDevice, featureIndex,
            &value, sizeof(value));
    }
    break;
    // Feature is a boolean
    case CORFEATURE_VAL_TYPE_BOOL:
    {
        BOOL value;
        status = CorAcqDeviceGetFeatureValueByIndex(hAcqDevice, featureIndex,
            &value, sizeof(value));
        value = !value;
        status = CorAcqDeviceSetFeatureValueByIndex(hAcqDevice, featureIndex,
            &value, sizeof(value));
    }
    break;
    // Other feature types
    // ...
}

//
// Example 2 : Access specific feature (integer example)
//
// Get feature object
status = CorAcqDeviceGetFeatureInfoByName(hAcqDevice, "Gain", hFeature);

// Extract minimum, maximum and increment values
status = CorFeatureGetMin(hFeature, &min, sizeof(min));
status = CorFeatureGetMax(hFeature, &max, sizeof(max));
status = CorFeatureGetInc(hFeature, &inc, sizeof(inc));

// Read, modify and write value
status = CorAcqDeviceGetFeatureValueByName(hAcqDevice, "Gain", &value,
    sizeof(value));
value += 10;
status = CorAcqDeviceSetFeatureValueByName(hAcqDevice, "Gain", &value,
    sizeof(value));

//
// Example 3 : Access specific feature (enumeration example)
//
// Get feature object
status = CorAcqDeviceGetFeatureInfoByName(hAcqDevice, "ExposureMode", hFeature);

// Get number of items in enumeration
status = CorFeatureGetEnumCount(hFeature, &enumCount);

for (enumIndex = 0; enumIndex < enumCount; enumIndex++)
{
    // Get item string and value
    status = CorFeatureGetEnumString(hFeature, enumIndex, enumString,
        sizeof(enumString));
    status = CorFeatureGetEnumValue(hFeature, enumIndex, &enumValue);
}

// Read a value and get its associated string
status = CorAcqDeviceGetFeatureValueByName(hAcqDevice, "ExposureMode", &enumValue,
    sizeof(enumValue));
status = CorFeatureGetEnumStringFromValue(hFeature, enumValue, enumString,
    sizeof(enumString));

```

```

// Write a value corresponding to known string
status = CorFeatureGetEnumValueFromString(hFeature, "Manual", &enumValue);
status = CorAcqDeviceSetFeatureValueByName(hAcqDevice, "ExposureMode", &enumValue,
    sizeof(enumValue));

//
// Example 4 : Access specific feature (LUT example)
//
// Select a LUT and retrieve its size and format
status = CorAcqDeviceGetFeatureValueByName(hAcqDevice, "LUTNumberEntries",
    &lutNEntries, sizeof(lutNEntries));
status = CorAcqDeviceGetFeatureValueByName(hAcqDevice, "LUTFormat", &lutFormat,
    sizeof(lutFormat));

// Create and generate a compatible software LUT
status = CorLutNew(hSystemServer, lutNEntries, lutFormat, &hLut);
status = CorLutReverse(hLut);

// Write LUT values to camera
status = CorAcqDeviceSetFeatureDataByName(hAcqDevice, "LUTData", hLut);

//
// Example 5 : Callback management
//
// Browse event list
status = CorAcqDeviceGetEventCount(hAcqDevice, &numEvents);
for (eventIndex = 0; eventIndex < numEvents; eventIndex++)
{
    status = CorAcqDeviceGetEventNameByIndex(hAcqDevice, eventIndex, eventName,
        sizeof(eventName));
}

// Register event by name
status = CorAcqDeviceRegisterCallbackByName(hAcqDevice, "Feature Value Changed",
    CameraCallback, hAcqDevice);

// Modified a feature (Will trigger callback function)
value = 150;
status = CorAcqDeviceSetFeatureValueByName(hAcqDevice, "Gain", &value,
    sizeof(value));

// Unregister event by name
status = CorAcqDeviceUnregisterCallbackByName(hAcqDevice, "Feature Value Changed");

// Release handles
status = CorLutFree(hLut);
status = CorFeatureFree(hFeature);
status = CorAcqDeviceRelease(hAcqDevice);
status = CorManReleaseServer(hAcqServer);
status = CorManReleaseServer(hSystemServer);

// Close Spera API
status = CorManClose();
}

```

## Writing Feature Values by Group

When a series of features are tightly coupled it becomes almost impossible to modify those features without following a specific order. One example is the region-of-interest (ROI) where the four values (top, left, width and height) depend on each other. To circumvent this problem the AcqDevice module allows you to temporarily set the feature values in an “internal cache” and then downloads the values to the camera all at once. The following code illustrates the ROI example.

```
. . .

CORSTATUS status;
UINT32 value;

// Set manual mode to update features
status = CorAcqDeviceSetPrm(hAcqDevice, CORACQDEVICE_PRM_UPDATE_FEATURE_MODE,
    CORACQDEVICE_VAL_UPDATE_FEATURE_MODE_MANUAL);

// Set buffer top position value (in the internal cache only)
value = 50;
status = CorAcqDeviceSetFeatureValueByName(hAcqDevice, "OffsetY", &value,
    sizeof(value));

// Set buffer left position value (in the internal cache only)
value = 50;
status = CorAcqDeviceSetFeatureValueByName(hAcqDevice, "OffsetX", &value,
    sizeof(value));

// Set buffer width value (in the internal cache only)
value = 300;
status = CorAcqDeviceSetFeatureValueByName(hAcqDevice, "Width", &value,
    sizeof(value));

// Set buffer height value (in the internal cache only)
value = 300;
status = CorAcqDeviceSetFeatureValueByName(hAcqDevice, "Height", &value,
    sizeof(value));

// Write features value to the device (by reading values from the internal cache)
status = CorAcqDeviceUpdateFeaturesToDevice(hAcqDevice);

// Set back the automatic mode
status = CorAcqDeviceSetPrm(hAcqDevice, CORACQDEVICE_PRM_UPDATE_FEATURE_MODE,
    CORACQDEVICE_VAL_UPDATE_FEATURE_MODE_AUTO);
```

# Displaying Images

---

## Required Modules

The following three Sopera modules are required to initiate a display process:

- **Display:** Static resource based on an onboard display section.
- **Buffer:** Dynamic resource containing data to display. Several type options may be chosen when allocating the buffer to be compatible with the different display modes (see the "Working with Buffers" section for more information about these options).
- **View:** Dynamic resource used to link the display to the buffer and to synchronize the display operations.

---

## Display Example

The example below illustrates how to display an image contained within a system buffer to the computer VGA card. The buffer is transferred to the Windows desktop using the DIB mode (automatically detected by the View module). When using this mode, a Windows Device-Independent Bitmap (DIB) is first created before being sent to VGA memory. For more information on the View modes, see Modifying the View Parameters.

```
CORSTATUS status;        // Error code
CORSERVER hSystem;       // System server handle
CORDISPLAY hDisplay;     // Display handle
CORBUFFER hBuffer;       // Buffer handle
CORVIEW hView;           // View handle

// Initialize Sopera API
status = CorManOpen();

// Get system server handle
hSystem = CorManGetLocalServer();

// Get display handle
status = CorDisplayGetHandle(hSystem, 0, &hDisplay);

// Create a 640x480/8-bit monochrome buffer in system memory
status = CorBufferNew(hSystem, 640, 480, CORBUFFER_VAL_FORMAT_UINT8, CORBUFFER_VAL_TYPE_VIRTUAL, &hBuffer);

// Create a view handle
status = CorViewNew(hSystem, hDisplay, hBuffer, CORVIEW_VAL_MODE_AUTO_DETECT, &hView);

// Set HWND parameter to NULL to display image on the desktop
status = CorViewSetPrm(hView, CORVIEW_PRM_HWND, NULL);

// Display image in the desktop
status = CorViewShow(hView);

// Release handles when finished
status = CorViewFree(hView);           // Should be freed first
status = CorBufferFree(hBuffer);
status = CorDisplayRelease(hDisplay);

// Close Sopera API
status = CorManClose();
```



---

## Modifying the View Parameters

The following describes view modes, source and destination windows, and zooming.

### View Modes

Three viewing modes are available. Specifying `CORVIEW_VAL_MODE_AUTO_DETECT` when creating the View module will choose the appropriate mode, taking into account the given buffer.

- **DIB mode:** Used to display buffers of any pixel format. A View module can be created in DIB mode if the associated buffer is contiguous, scatter-gather, or virtual. DIB mode uses a device-independent bitmap to represent and transfer buffer data to the Display module.
- **BLT mode:** Used if the display device supports DirectDraw (Windows XP 32-bit only) and if the buffer is an offscreen buffer. If the display adapter supports it, BLT mode will perform a fast data transfer from the buffer to the display memory. This mode is usually faster than the DIB mode, if the buffer has been allocated in video memory and if the transfer occurs within the display adapter, thus freeing the CPU or PCI bus of potential bottlenecks. Create offscreen buffers in video memory using the same pixel format as the display adapter's current pixel format (for instance, RGB565 for a 65536 color configuration). For offscreen buffers in system memory, the `CORDISPLAY_PRM_PIXEL_TYPE_OFFSCREEN` parameter supplies a list of pixel formats that DirectDraw can copy directly to the display memory. If the buffer's pixel format is not in this list, a software conversion will be performed.
- **Keyer mode:** Used if the display device supports DirectDraw (Windows XP 32-bit only) and if the buffer is an overlay buffer. The display adapter's hardware can perform a color keying operation between the overlay buffer and the display memory using the keyer color defined by the `CORVIEW_PRM_KEYER_COLOR` parameters. The color keying mode is determined by the View module's `CORVIEW_PRM_OVERLAY_MODE` parameter.

### Source and Destination Windows and Zooming

The following are the View module's two reference windows:

- A source window that defines an area in the buffer to display.
- A destination window that defines a region on the display surface or in the target window's client area (if `CORVIEW_PRM_HWND` is not 0) where the source window region is displayed.

Upon the creation of a new View module, the source window is by default the same size as the whole buffer viewed and is positioned at its origin. The destination window matches the dimensions of the source window and is positioned at the origin of the display surface or the target window's client area. The dimensions and position of these windows can be modified using the `CORVIEW_PRM_ROI_SRC_xxx` and `CORVIEW_PRM_ROI_DST_xxx` parameters, if the `CORVIEW_CAP_ROI_SRC` and `CORVIEW_CAP_ROI_DST` capabilities are not 0 (for instructions on setting these parameters, see *Displaying in a Windows Application*). If these two windows have the same dimensions, no zooming is performed (the pixels are displayed as they are read in the buffer). If the destination window is a different size from the source window, the buffer elements are zoomed up or down (as appropriate) as they are displayed. The character of the zooming operation depends on the value of the `CORVIEW_CAP_ZOOM_HORZ_METHOD` and `CORVIEW_CAP_ZOOM_VERT_METHOD` capabilities. Zooming can be accomplished through pixel dropping or replication, interpolation, or by powers of 2. X and Y zoom methods are independent from each other.



Zooming may influence the View module's display speed (realtime refresh may not be possible).

---

## Displaying in a Windows Application

The View module contains three callback functions, CorViewOnPaint, CorViewOnMove, and CorViewOnSize. They can be called in your Windows application's respective message handlers for WM\_PAINT, WM\_MOVE and WM\_SIZE. Below is an example of a Windows application using the Visual C++'s MFC library. This is a dialog-based application whose dialog window is used to display the buffer content. The window's handle is passed as a parameter in the OnInitDialog handler to ensure that it is not null. The destination window is adjusted each time the dialog is resized. The source window corresponds to the buffer rectangle by default. The View module will scale the buffer contents into the dialog window because it is not adjusted.

```
CORSTATUS status;          // Error code
CORSERVER hSystem; // System server handle
CORDISPLAY hDisplay;      // Display handle
CORBUFFER hBuffer; // Buffer handle
CORVIEW hView;           // View handle

CCorViewDlg::CCorViewDlg()
{
    // Initialize Sapera API
    status = CorManOpen();

    // Other initialization
    ...

    // Get system server handle
    hSystem = CorManGetLocalServer();

    // Get display handle
    status = CorDisplayGetHandle(hSystem, 0, &hDisplay);

    // Create a 640x480/8-bit monochrome buffer in system memory
    status = CorBufferNew(hSystem, 640, 480, CORBUFFER_VAL_FORMAT_UINT8, CORBUFFER_VAL_TYPE_VIRTUAL,
        &hBuffer);

    // Create a view handle
    status = CorViewNew(hSystem, hDisplay, hBuffer, CORVIEW_VAL_MODE_AUTO_DETECT, &hView);
}

CCorViewDlg::~CCorViewDlg()
{
    CORSTATUS status;          // Error code

    // Release handles when finished
    status = CorViewFree(hView); // Should be freed first
    status = CorBufferFree(hBuffer);
    status = CorDisplayRelease(hDisplay);

    // Close Sapera API
    status = CorManClose();
}

BOOL CCorViewDlg::OnInitDialog()
{
    // Call default handler
    CDialog::OnInitDialog();

    // Other initialization
    ...

    // Set HWND parameter to window's handle
    status = CorViewSetPrm(hView, CORVIEW_PRM_HWND, (UINT32)GetSafeHwnd());

    return TRUE;
}

void CCorViewDlg::OnPaint()
{
    if (IsIconic())
    {
        ...
    }
    else
    {

```

```

// Optionally call the default handler to paint a background
CDialog::OnPaint();

// Update view area
CorViewOnPaint(hView);
}

void CCorViewDlg::OnSize(UINT nType, int cx, int cy)
{
// Call default handler
CDialog::OnSize(nType, cx, cy);

// Fit destination window to window's client area
CRect cli;
GetClientRect(cli);
status = CorViewSetPrm(hView, CORVIEW_PRM_ROI_DST_LEFT, cli.left);
status = CorViewSetPrm(hView, CORVIEW_PRM_ROI_DST_TOP, cli.top);
status = CorViewSetPrm(hView, CORVIEW_PRM_ROI_DST_WIDTH, cli.Width());
status = CorViewSetPrm(hView, CORVIEW_PRM_ROI_DST_HEIGHT, cli.Height());

// Update displayed area
CorViewOnSize(hView);
}

void CCorViewDlg::OnMove(int x, int y)
{
// Call default handler
CDialog::OnMove(x, y);

// Update displayed area
CorViewOnMove(hView);
}

```

# Working with Buffers

## Root and Child Buffers

A buffer is created in one of two ways: either as a root buffer (with no parent) or as a child buffer (with a parent). The parent of the child may also be a child itself, which allows you to build a buffer hierarchy with no restriction on the number of levels. A buffer can have more than one child buffer.

A child buffer shares the same memory space as its parent, and it defines an adjustable rectangular area within the root buffer. A child may be used by a processing function in order to process a region of interest. The example below shows how to create a root buffer with two child buffers.



**Note:** Child buffers must be freed before the root. If not, the root will return an error and will not be freed.

```
CORSTATUS status;                // Status code
CORSERVER hServer;               // Server handle
CORBUFFER hBuffer;               // Root buffer handle
CORBUFFER hChildLeft, hChildRight; // Child buffer handles

// Initialize Sapera API
status = CorManOpen();

// Get server handle
hServer = CorManGetLocalServer();

// Create a 640x480/8-bit monochrome buffer
status = CorBufferNew(hServer, 640, 480, CORBUFFER_VAL_FORMAT_UINT8, CORBUFFER_VAL_TYPE_SCATTER_GATHER,
&hBuffer);

// Create a child in the upper-left corner
status = CorBufferNewChild(hBuffer, 0, 0, 320, 240, &hChildLeft);

// Create a child in the upper-right corner
status = CorBufferNewChild(hBuffer, 320, 0, 320, 240, &hChildRight);

// Use buffers
...

// Free child buffers
status = CorBufferFree(hChildLeft);
status = CorBufferFree(hChildRight);

// Free root buffer
status = CorBufferFree(hBuffer);

// Close Sapera API
status = CorManClose();
```

Child buffer coordinates are accessed through four buffer parameters (*XMIN*, *YMIN*, *WIDTH*, and *HEIGHT*) that allow you to modify the position and size of the rectangle. The following example demonstrates several manipulations of the child buffers from the previous example.

```
// Swap buffers (left/right)
status = CorBufferSetPrm(hChildLeft, CORBUFFER_PRM_XMIN, 320);
status = CorBufferSetPrm(hChildRight, CORBUFFER_PRM_XMIN, 0);

// Set buffer as high as root
status = CorBufferSetPrm(hChildLeft, CORBUFFER_PRM_HEIGHT, 480);
status = CorBufferSetPrm(hChildRight, CORBUFFER_PRM_HEIGHT, 480);
```

## Buffer Types

Various types of buffers can be created. The type of buffer created illustrates how it will be allocated and how it can be used with other modules, such as the Transfer or View modules.

### Contiguous Memory Buffers

The buffer is allocated in contiguous memory. This means that the buffer is contained in a single, contiguous block of physical memory. The allocation mode allows the Transfer module to access the buffer through an efficient low-level process, for example, during an acquisition task. It is required to specify `CORBUFFER_VAL_TYPE_CONTIGUOUS` to allocate a buffer in contiguous memory when creating the buffer. Buffer size is limited by the amount of contiguous memory available which in turn is limited to one third of the total physical memory, up to 120MB. Use a scatter-gather buffer type to allocate large size buffers.

### Scatter-Gather Memory Buffers

A buffer may be allocated in paged pool memory. This means that the buffer is composed of many 4K byte memory blocks (pages) that are locked in physical memory by the Buffer module. This particular allocation mode allows the Transfer module to access the buffer through an efficient low-level process, for example, during an acquisition task. It is required to specify `CORBUFFER_VAL_TYPE_SCATTER_GATHER` to allocate a scatter-gather buffer when creating a new buffer. Note that a scatter-gather buffer can be very large since it uses paged pool memory.

### Unmapped Buffers

When the total amount of required buffer memory is close to or exceeds the amount of available virtual memory (2 GBytes under 32-bit Windows), then it is not possible to allocate and map the required memory.

When using the `CORBUFFER_VAL_TYPE_UNMAPPED` type, buffers are allocated in system memory. Pages are allocated but not mapped into the process virtual address space. Before trying to retrieve buffer virtual addresses, their memory has to be mapped into the process virtual address space by calling either the `CorBufferMap` or the `CorBufferMapEx` function. This buffer type can be logically ORed with `CORBUFFER_VAL_TYPE_SCATTER_GATHER` to create a source buffer or destination buffer for a transfer resource.

### Virtual Buffers

Similar to a scatter-gather buffer except that pages of memory are not locked. This type of buffer permits the allocation of very large buffers; however, these buffers cannot be used as a source/destination for the transfer resource. It is required to specify `CORBUFFER_VAL_TYPE_VIRTUAL` to allocate a virtual buffer when creating the new buffer. This type of buffer may be used, for example, to store an image resulting from a processing operation. If you supply a contiguous scatter-gather or virtual buffer to `CorViewNew`, the View resource created will ensure that any pixel format can be displayed, sometimes at the expense of higher CPU utilization.

### Offscreen and Overlay Buffers

These buffer types use `DirectDraw` (Windows XP 32-bit only) (which must be installed on the computer) to exploit the hardware acceleration provided by the display adapter. Note that these buffers are subject to some restrictions. Before creating this buffer type, verify that the `CORDISPLAY_PRM_PIXEL_TYPE_OFFSCREEN` or `CORDISPLAY_PRM_PIXEL_TYPE_OVERLAY` parameters list

the pixel formats that can be displayed efficiently without software conversion. The parameters depend on the display adapter and its current display mode (256 colors, 16, 24, or 32 bits). Note that a buffer created using any of those types can be used in low-level transfer processes, such as an acquisition task.

If the display device supports DirectDraw and `CORBUFFER_VAL_TYPE_OFFSCREEN` is specified when a buffer is created, the buffer will be allocated in system memory. The View module created using a buffer of this type tries to use the display adapter's hardware to copy the buffer's contents from system memory to video display memory. A system memory offscreen buffer can be created using any pixel format; however, calling *CorViewShow* with its corresponding view will take longer to execute if its pixel format is not listed in the `CORDISPLAY_PRM_PIXEL_TYPE_OFFSCREEN` parameter.

## Off-Screen Buffers in Video Memory

The buffer is allocated in offscreen video memory if `CORBUFFER_VAL_TYPE_OFFSCREEN` and `CORBUFFER_VAL_TYPE_VIDEO` is specified when creating the buffer (the two values should be ORed). The View module created using a buffer of this type uses the display adapter's hardware to perform a fast copy from video memory to video display memory. Typically, a buffer of this type is used when a graphical element is reused for several consecutive frames without modification. In this case, it is more efficient to keep this element in video memory and use the hardware to copy it to the appropriate position in each frame.



**Note:** If the display is in 256 color mode and 8-bit offscreen buffers are used, care should be taken to make certain that the buffers do not contain pixels with values within the 0-9 and 246-255 ranges. These values are reserved for Windows system colors and will not be displayed correctly.

## Overlay Buffers

The buffer is allocated in video memory. Once a View module is created using this buffer and *CorViewShow* is initially called, the display adapter's overlay hardware will keep updating the display with the buffer's contents without additional *CorViewShow* calls. Note that the pixel format of an overlay buffer must be listed in the `CORDISPLAY_PRM_PIXEL_TYPE_OVERLAY` parameter. Typically, overlay buffers will support more pixel formats (like YUV) than offscreen buffers. Color keying is supported by overlays as well. The behaviour of the overlay regarding key colors is determined by the `CORVIEW_PRM_OVERLAY_MODE` parameter of the View module resource associated with the buffer.

## Dummy Buffers

No memory is allocated for a dummy buffer in order that it does not contain any data elements. However, all of its size and format parameters are still valid. This means that any Sapera functionality from other modules that need access to buffer data elements will not work. The only exception is the Transfer module, which may use dummy buffers as placeholders when no data is to be physically transferred.

---

# Reading and Writing a Buffer

The following describes accessing simple buffer data as well as accessing buffer data using pointers.

## Simple Buffer Data Access

The simplest way to read or write data to a buffer is by accessing it element by element. The `CorBufferReadElement` and `CorBufferWriteElement` functions are used to read and write a single elements to a buffer, respectively. The following examples demonstrate how to access data in an 8-bit monochrome buffer.

```
CORSTATUS status;      // Status code
CORSERVER hServer;     // Server handle
CORBUFFER hBuffer;     // Buffer handle
UINT8 value;           // Unsigned character to store 8-bit value

// Initialize Sopera API
status = CorManOpen();

// Get server handle
...

// Create a 640x480/8-bit monochrome buffer
status = CorBufferNew(hServer, 640, 480, CORBUFFER_VAL_FORMAT_UINT8, CORBUFFER_VAL_TYPE_VIRTUAL, &hBuffer);

// Write a constant value at a specific position
value = 0x80;
status = CorBufferWriteElement(hBuffer, 100, 200, &value, sizeof( value));

// Read back the value
status = CorBufferReadElement(hBuffer, 100, 200, &value, sizeof( value));

// Free buffer
status = CorBufferFree(hBuffer);

// Close Sopera API
status = CorManClose();
```

Accessing buffer data in this way is quite straightforward but, unfortunately, it considerably slows down access time. Alternately, you can access data by reading/writing an array of elements with only one function call through the Buffer module's `CorBufferRead` and `CorBufferWrite` functions. Below is a sample code illustrating the usage of these functions.

```
CORSTATUS status;      // Status code
CORSERVER hServer;     // Server handle
CORBUFFER hBuffer;     // Buffer handle
UINT8 *array;          // Character array to store 8-bit values
UINT32 size;           // Size of the array in bytes

// Initialize Sopera API
status = CorManOpen();

// Get server handle
...

// Create a 640x480/8-bit monochrome buffer
status = CorBufferNew(hServer, 640, 480, CORBUFFER_VAL_FORMAT_UINT8, CORBUFFER_VAL_TYPE_VIRTUAL, &hBuffer);

// Create an array the same size as the buffer
size = 640 * 480 * sizeof( UINT8);
array = (BYTE *) malloc(size);

// Fill array with values
...

// Write array to buffer
status = CorBufferWrite(hBuffer, 0, array, size);

// Read back array from buffer
status = CorBufferRead(hBuffer, 0, array, size);

// Free array and buffer
free(array);
status = CorBufferFree(hBuffer);

// Close Sopera API
status = CorManClose();
```



## Buffer Data Access Using Pointers

Another way to access data stored in a buffer is to get a pointer to the buffer's memory by retrieving the value of its CORBUFFER\_PRM\_ADDRESS parameter. If the buffer has been allocated into video memory (that is, an offscreen-video buffer or an overlay buffer), it must be locked before its address can be obtained. A buffer is locked by setting its CORBUFFER\_PRM\_LOCKED to a non-zero value.

```
CORSTATUS status;          // Status code
CORSERVER hServer;         // Server handle
CORBUFFER hBuffer;         // Buffer handle
UINT16 *dataPtr;           // pointer to buffer memory
UINT8 *basePtr;            // pointer to buffer memory
UINT32 pitch;              // width of buffer created
UINT32 i,j;

// Initialize Sapera API
status = CorManOpen();

// Get server handle
...

// Create a 640x480/16-bit RGB 565 buffer in video memory
// Display should also be 16 bits

status = CorBufferNew(hServer, 640, 480, CORBUFFER_VAL_FORMAT_RGB565, CORBUFFER_VAL_TYPE_OFFSCREEN |
CORBUFFER_VAL_TYPE_VIDEO, &hBuffer);

// Get the pitch of the surface
status = CorBufferGetPrm(hBuffer, CORBUFFER_PRM_PITCH, &pitch);

// Lock buffer since it is in video memory
status = CorBufferSetPrm(hBuffer, CORBUFFER_PRM_LOCKED, TRUE);

// Get address of the buffer's memory
status = CorBufferGetPrm(hBuffer, CORBUFFER_PRM_ADDRESS, &basePtr);

for(i=0;i<480;i++)
{
    dataPtr = (UINT16*)(basePtr + i*pitch);
    for(j=0;j<640;j++)
    {
        // Process the line pointed to by dataPtr
        ...
    }
}

// Unlock buffer
status = CorBufferSetPrm(hBuffer, CORBUFFER_PRM_LOCKED, FALSE);

// note: at this point, dataPtr should not be used anymore

// Free buffer
status = CorBufferFree(hBuffer);

// Close Sapera API
status = CorManClose();
```

Additional buffer functions allow you to read and write specific data structures such as lines, rectangles, and dots.

# Sapera Frame Grabber Acquisition

## Acquisition Parameters & Capabilities

This section describes the functions of the Acquisition, Camera, and VIC Modules. The parameters and capabilities are described in the Sapera LT Acquisition Parameters Reference Manual.

## Acquisition Functions

Function	Description
CorAcqFreeFlatfield	Deallocate a flatfield resource from an acquisition device.
CorAcqGetCamIOControl	Gets value of a custom camera I/O control.
CorAcqGetCap	Gets acquisition capability value from an acquisition device.
CorAcqGetCount	Gets the number of acquisition devices on a server.
CorAcqGetFlatfield	Get the gain and offset values for a flatfield resource.
CorAcqGetHandle	Gets a handle to an acquisition device.
CorAcqGetImageFilter	Gets the image filter kernel.
CorAcqGetLut	Gets input LUT values from an acquisition device.
CorAcqGetPrm	Gets acquisition parameter value from an acquisition device.
CorAcqGetPrms	Gets camera-dependent and VIC-dependent parameters from an acquisition device.
CorAcqGetSerialPortName	Retrives the serial port name used by an acquisition device.
CorAcqNewFlatfield	Create a flatfield resource for an acquisition device.
CorAcqRegisterCallback	Register callback function for an acquisition resource (32-bit version).
CorAcqRegisterCallbackEx	Register callback function for an acquisition resource (expanded 64-bit version).
CorAcqRelease	Releases handle to an acquisition device.
CorAcqReset	Resets an acquisition device.
CorAcqResetModule	Resets the resources associated with the server's acquisition device(s).
CorAcqSetCamIOControl	Sets value of a custom camera I/O control.
CorAcqSetFlatfield	Set the gain and offset values for a flatfield resource.
CorAcqSetImageFilter	Set the image filter kernel values.
CorAcqSetLut	Sets input LUT values for an acquisition device
CorAcqSetPrm	Sets a simple acquisition parameter of an acquisition device
CorAcqSetPrmEx	Sets a complex acquisition parameter of an acquisition device
CorAcqSetPrms	Sets camera-dependent and VIC-dependent parameters of an acquisition device
CorAcqSoftwareTrigger	Simulate a trigger to the acquisition device.
CorAcqUnlock	Unlocks acquisition parameters of an acquisition device
CorAcqUnregisterCallback	Unregister callback function for an acquisition resource
CorAcqUnregisterCallbackEx	Unregister callback function for an acquisition resource (expanded version)

---

## CorAcqFreeFlatfield

Deallocate a flatfield resource from an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqFreeFlatfield</b> (CORACQ <i>hAcq</i> , UINT32 <i>flatfieldNumber</i> );	
<b>Description</b>	Deallocate a flatfield resource for an acquisition device that was allocated with CorAcqNewFlatfield.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>flatfieldNumber</i>	The resource's flatfield number
<b>Output</b>	<i>None</i>	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_OUT_OF_RANGE	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_NO_MEMORY	
	CORSTATUS_NOT_AVAILABLE	
<b>See Also</b>	CorAcqNewFlatfield	

---

## CorAcqGetCamIOControl

Get value of a custom camera I/O control

<b>Prototype</b>	CORSTATUS <b>CorAcqGetCamIOControl</b> (CORACQ <i>hAcq</i> , PCSTR <i>label</i> , UINT32 * <i>value</i> );	
<b>Description</b>	Gets the current value of a custom camera I/O control.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>label</i>	String specifying the label of the custom camera I/O control to get the value from.
<b>Output</b>	<i>value</i>	Current value of the custom camera I/O
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_INVALID	
	CORSTATUS_ARG_NULL (if <i>label</i> or <i>value</i> is NULL)	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_NOT_IMPLEMENTED	
<b>Note</b>	See Data Structures in the <i>Sapera LT Acquisition Parameters Reference Manual</i> , for retrieving correct values with specific macros.	

---

## CorAcqGetCap

Get acquisition capability value from an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqGetCap</b> (CORACQ <i>hAcq</i> , UINT32 <i>cap</i> , void * <i>value</i> );	
<b>Description</b>	Gets acquisition capability value from an acquisition device.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>cap</i>	Acquisition device capability requested
<b>Output</b>	<i>value</i>	Value of the capability
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_ARG_NULL (if <i>value</i> is NULL)	
	CORSTATUS_CAP_INVALID	

---

## CorAcqGetCount

Get the number of acquisition devices on a server

<b>Prototype</b>	CORSTATUS <b>CorAcqGetCount</b> (CORSERVER <i>hServer</i> , UINT32 * <i>count</i> );
<b>Description</b>	Gets the number of acquisition devices available on a server.
<b>Input</b>	<i>hServer</i> Server handle
<b>Output</b>	<i>count</i> Number of acquisition devices. The value of <i>count</i> is 0 when no acquisition device is available.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_NOT_IMPLEMENTED (when there is no Acquisition devices supported by the specified server) CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>count</i> is NULL)

---

## CorAcqGetFlatfield

Get the gain and offset values for a flatfield resource

<b>Prototype</b>	CORSTATUS <b>CorAcqGetFlatfield</b> (CORACQ <i>hAcq</i> , UINT32 <i>flatfieldNumber</i> , CORBUFFER <i>hBufferGain</i> , CORBUFFER <i>hBufferOffset</i> );
<b>Description</b>	Reads the gain and offset values for each pixel from the allocated flatfield resource.
<b>Input</b>	<i>hAcq</i> Acquisition resource handle <i>flatfieldNumber</i> Flatfield Number
<b>Output</b>	<i>hBufferGain</i> Buffer resource handle. The buffer contains the flatfield gain values for each pixel in the flatfield resource. <i>hBufferOffset</i> Buffer resource handle. The buffer contains the flatfield offset values for each pixel in the flatfield resource.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY CORSTATUS_NOT_AVAILABLE CORSTATUS_ARG_INCOMPATIBLE
<b>See Also</b>	CorAcqNewFlatfield, CorAcqFreeFlatfield and CorAcqSetFlatfield

---

## CorAcqGetHandle

Get a handle to an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqGetHandle</b> (CORSERVER <i>hServer</i> , UINT32 <i>index</i> , CORACQ * <i>hAcq</i> );
<b>Description</b>	Gets a handle to an acquisition device.
<b>Input</b>	<i>hServer</i> Server handle <i>index</i> Specifies the acquisition device to select. Valid values are in the range [0... <i>count</i> -1], where <i>count</i> is the value returned by CorAcqGetCount.
<b>Output</b>	<i>hAcq</i> Acquisition resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_ACCESSIBLE CORSTATUS_RESOURCE_IN_USE
<b>See Also</b>	CorAcqGetCount, CorAcqRelease

---

## CorAcqGetImageFilter

Get the image filter kernel values

<b>Prototype</b>	CORSTATUS <b>CorAcqGetImageFilter</b> (CORACQ hAcq, UINT32 imageFilterNumber, CORBUFFER hBufferKernel);	
<b>Description</b>	Reads the kernel values to the image filter.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle.
	<i>imageFilterNumber</i>	Image filter to read.
	<i>hBufferKernel</i>	Buffer resource handle. The buffer contains the kernel values.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_OUT_OF_RANGE	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_NO_MEMORY	
	CORSTATUS_NOT_AVAILABLE	
	CORSTATUS_ARG_INCOMPATIBLE	
<b>See Also</b>	CorAcqSetImageFilter	
<b>Note</b>	hBufferKernel is a 2D buffer of INT32.	

---

## CorAcqGetLut

Get input LUT values from an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqGetLut</b> (CORACQ <i>hAcq</i> , CORLUT <i>hLut</i> , UINT32 <i>lutNumber</i> );	
<b>Description</b>	Gets input LUT values from an acquisition device.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>lutNumber</i>	LUT number to get values from
<b>Output</b>	<i>hLut</i>	LUT resource handle
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_OUT_OF_RANGE	
	CORSTATUS_INCOMPATIBLE_LUT	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_NO_MEMORY	
<b>Note</b>	CORSTATUS_NOT_AVAILABLE	
	The LUT number value range is [0...CORACQ_PRM_LUT_MAX-1].	
<b>See Also</b>	CorAcqSetLut	

---

## CorAcqGetPrm

Get acquisition parameter value from an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqGetPrm</b> (CORACQ <i>hAcq</i> , UINT32 <i>prm</i> , void * <i>value</i> );	
<b>Description</b>	Gets acquisition parameter (simple and complex) value from an acquisition device. Make certain that <i>value</i> points to a data structure that matches the data type of the specified acquisition parameter.	
	See Data Structures in the <i>Sapera LT Acquisition Parameters Reference Manual</i> , for retrieving correct values with specific macros.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>prm</i>	Acquisition parameter requested
<b>Output</b>	<i>value</i>	Current value of the requested parameter
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_ARG_NULL (if <i>value</i> is NULL)	
	CORSTATUS_PRM_INVALID	
<b>See Also</b>	CorAcqSetPrm and CorAcqSetPrmEx	

---

## CorAcqGetPrms

Get camera-dependent and VIC-dependent parameter values from an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqGetPrms</b> (CORACQ <i>hAcq</i> , CORVIC <i>hVic</i> , CORCAM <i>hCam</i> , UINT32 <i>toLock</i> );	
<b>Description</b>	Gets camera-dependent and VIC-dependent parameter values from an acquisition device. The VIC and camera resource handles can be any valid handle obtained through CorVicNew and CorCamNew respectively.  If the acquisition parameters are locked ( <i>toLock</i> = TRUE), then the acquisition parameters cannot be modified by CorAcqSetPrms and CorAcqSetPrmEx. The only way to modify the parameters is to use CorAcqSetPrms with the same VIC and CAM handles that were used when locking the parameters. Refere to the CorAcqSetPrms for a more detailed explanation about the locking mechanism.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>toLock</i>	Lock acquisition parameters (TRUE or FALSE)
<b>Output</b>	<i>hVic</i>	VIC resource handle
	<i>hCam</i>	Camera resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_PARAMETERS_LOCKED	
<b>See Also</b>	CorAcqSetPrms, CorAcqSetPrm, CorAcqSetPrmEx, CorVicNew and CorCamNew	

---

## CorAcqGetSerialPortName

Retrives the serial port name used by an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqGetSerialPortName</b> (CORACQ <i>hAcq</i> , UINT32 <i>portNameLengthMax</i> , char* <i>szSerialPortName</i> );	
<b>Description</b>	Copies the name of the serial port used with the acquisition device.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>portNameLengthMax</i>	Maximum number of characters to copy
<b>Output</b>	<i>szSerialPortName</i>	Name of the serial port
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_IMPLEMENTED	

---

## CorAcqNewFlatfield

Allocate a flatfield resource for an acquisition resource

<b>Prototype</b>	CORSTATUS <b>CorAcqNewFlatfield</b> (CORACQ <i>hAcq</i> , UINT32 * <i>pFlatfieldNumber</i> );	
<b>Description</b>	Allocate a flatfield resource for an acquisition resource	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
<b>Output</b>	<i>pFlatfieldNumber</i>	Pointer to a flatfield number
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY CORSTATUS_NOT_AVAILABLE	
<b>See Also</b>	CorAcqFreeFlatfield, CorAcqSetFlatfield and CorAcqGetFlatfield	

---

## CorAcqRegisterCallback

Register callback function for an acquisition resource

**Prototype**      `CORSTATUS CorAcqRegisterCallback(CORACQ hAcq, UINT32 eventType, PCORCALLBACK callbackFct, void *context);`

**Description**      Registers callback function for the specified acquisition resource.

**Input**

<i>hAcq</i>	Acquisition resource handle
<i>eventType</i>	Type of event to register. See CORACQ_PRM_EVENT_TYPE in the <i>Sapera LT Acquisition Parameters Reference Manual</i> .
<i>callbackFct</i>	Callback function to register. The callback function is defined as follows: <code>CORSTATUS CCONV callback(void *context, UINT32 eventType, UINT32 eventCount);</code> When called, <i>context</i> will have the value specified at the callback function registration; <i>eventType</i> will contain the event(s) that triggered the call to the callback function; <i>eventCount</i> should increment by one at each call, with a starting value of 1. In case the acquisition resource cannot keep up because there are too many events to be signaled, <i>eventCount</i> will take non- consecutive values, indicating that events have been lost. See the Data Types section for the PCORCALLBACK definition.
<i>context</i>	Context pointer passed to the callback function when called

**Output**      None

**Return Value**      CORSTATUS\_OK  
CORSTATUS\_ARG\_NULL  
CORSTATUS\_INVALID\_HANDLE  
CORSTATUS\_NOT\_AVAILABLE  
CORSTATUS\_RESOURCE\_IN\_USE

**Note**      The values may be ORed if more than one event is desired. Moreover, when used, CORACQ\_VAL\_EVENT\_TYPE\_END\_OF\_LINE must be ORed with an *unsigned* integer representing the line (max 65535) on which the callback function has to be called while CORACQ\_VAL\_EVENT\_TYPE\_END\_OF\_NLINES must be ORed with an *unsigned* integer representing the number of lines (max 65535) after which the callback function has to be called.

Also note that the line number for which the callback function is called is not returned through its eventType argument; the corresponding bits are always set to 0.

**See Also**      CorAcqUnregisterCallback



## Register callback function for an acquisition resource

<b>Description</b>	Registers callback function for the specified acquisition resource.
--------------------	---------------------------------------------------------------------

Output	None
--------	------

**Note** The values may be ORed if more than one event is desired. Moreover, when used, `CORACQ_VAL_EVENT_TYPE_END_OF_LINE` must be ORed with an *unsigned* integer representing the line (max 65535) on which the callback function has to be called while `CORACQ_VAL_EVENT_TYPE_END_OF_NLINES` must be ORed with an *unsigned* integer representing the number of lines (max 65535) after which the callback function has to be called.

Also note that the line number for which the callback function is called is not returned through its `eventType` argument; the corresponding bits are always set to 0.

This function allows timestamp events to be registered and will permit extra events that the 32-bit `CorAcqRegisterCallback` does not support. However, device drivers continue to support both functions.

**See Also** [CorAcqUnregisterCallbackEx](#)

## Release handle to an acquisition device

<b>Description</b>	Releases handle to an acquisition device.
--------------------	-------------------------------------------

Output	None
--------	------

**See Also** [CorAcqGetHandle](#)

---

## CorAcqReset

Reset an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqReset</b> (CORACQ <i>hAcq</i> );
<b>Description</b>	Reset and restore the default acquisition parameter values of the specified acquisition device.
<b>Input</b>	<i>hAcq</i> Acquisition resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_PARAMETERS_LOCKED CORSTATUS_SOFTWARE_ERROR
<b>See Also</b>	CorAcqResetModule

---

## CorAcqResetModule

Reset the resources associated with the server's acquisition device(s)

<b>Prototype</b>	CORSTATUS <b>CorAcqResetModule</b> (CORSERVER <i>hServer</i> );
<b>Description</b>	This releases all the resources (handle, memory) currently allocated. Before using this function, make certain that no other application is currently using any acquisition device resource. Proceed with caution when using this function.
<b>Input</b>	<i>hServer</i> Server handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorAcqReset

---

## CorAcqSetCamIOControl

Set value of a custom I/O control

<b>Prototype</b>	CORSTATUS <b>CorAcqSetCamIoControl</b> (CORACQ hAcq, PCSTR label, UINT32 value)
<b>Description</b>	Sets the state of a custom I/O control that was previously defined by the Camera parameter CORACQ_PRM_CAM_IO_CONTROL. Refer to the Custom Camera Control I/O Description section in the <i>Sapera LT Acquisition Parameters Reference Manual</i> , for a discussion about custom I/O control.
<b>Input</b>	<i>hAcq</i> Acquisition resource handle <i>label</i> String specifying the label of the custom camera I/O control <i>value</i> Value to write to the custom camera I/O control
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID CORSTATUS_ARG_NULL (if <i>label</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_IMPLEMENTED CORSTATUS_PARAMETERS_LOCKED
<b>Note</b>	See the Data Structures section in the <i>Sapera LT Acquisition Parameters Reference Manual</i> , for building correct values with specific macros.

---

## CorAcqSetFlatfield

Set the gain and offset values for a flatfield resource

<b>Prototype</b>	CORSTATUS <b>CorAcqSetFlatfield</b> (CORACQ hAcq, UINT32 flatfieldNumber, CORBUFFER hBufferGain, CORBUFFER hBufferOffset);
<b>Description</b>	Writes the gain and offset values for each pixel to the allocated flatfield resource.
<b>Input</b>	<i>hAcq</i> Acquisition resource handle <i>flatfieldNumber</i> Flatfield Number <i>hBufferGain</i> Buffer resource handle. The buffer contains the flatfield gain values for each pixel in the flatfield resource. <i>hBufferOffset</i> Buffer resource handle. The buffer contains the flatfield offset values for each pixel in the flatfield resource.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY CORSTATUS_NOT_AVAILABLE CORSTATUS_ARG_INCOMPATIBLE
<b>See Also</b>	CorAcqNewFlatfield, CorAcqFreeFlatfield and CorAcqGetFlatfield

---

## CorAcqSetImageFilter

Set the image filter kernel values

<b>Prototype</b>	CORSTATUS <b>CorAcqSetImageFilter</b> (CORACQ hAcq, UINT32 imageFilterNumber, CORBUFFER hBufferKernel);	
<b>Description</b>	Writes the kernel values to the image filter.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>imageFilterNumber</i>	Image filter to write
	<i>hBufferKernel</i>	Buffer resource handle. The buffer contains the kernel values.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_OUT_OF_RANGE	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_NO_MEMORY	
	CORSTATUS_NOT_AVAILABLE	
	CORSTATUS_ARG_INCOMPATIBLE	
<b>See Also</b>	CorAcqGetImageFilter	
<b>Note</b>	hBufferKernel is a 2D buffer of INT32.	

---

## CorAcqSetLut

Set input LUT values for an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqSetLut</b> (CORACQ hAcq, CORLUT hLut, UINT32 lutNumber);	
<b>Description</b>	Sets input LUT values for an acquisition device.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>hLut</i>	LUT resource handle created with CorLutNew or CorLutNewFromFile.
	<i>lutNumber</i>	LUT number to write the values to. The LUT number value range is [0...CORACQ_PRM_LUT_MAX-1].
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_OUT_OF_RANGE	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_INCOMPATIBLE_LUT	
	CORSTATUS_NO_MEMORY	
	CORSTATUS_NOT_AVAILABLE	
<b>See Also</b>	CorAcqGetLut	

---

## CorAcqSetPrm

Set a simple acquisition parameter of an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqSetPrm</b> (CORACQ <i>hAcq</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );						
<b>Description</b>	<p>Sets a simple acquisition device's parameter. A simple parameter is one that fits inside an UINT32. If the parameter is complex, use CorAcqSetPrmEx.</p> <p>Acquisition parameters are normally initialized all at once by CorAcqSetPrms. One may want to modify certain parameters at a later time, such as those related to camera swithing, brightness and contrast settings. In this case, CorAcqSetPrm (or CorAcqSetPrmEx) should be used for faster execution.</p>						
<b>Input</b>	<table><tr><td><i>hAcq</i></td><td>Acquisition resource handle</td></tr><tr><td><i>prm</i></td><td>Acquisition parameter to set</td></tr><tr><td><i>value</i></td><td>New value of the parameter</td></tr></table>	<i>hAcq</i>	Acquisition resource handle	<i>prm</i>	Acquisition parameter to set	<i>value</i>	New value of the parameter
<i>hAcq</i>	Acquisition resource handle						
<i>prm</i>	Acquisition parameter to set						
<i>value</i>	New value of the parameter						
<b>Output</b>	None						
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY CORSTATUS_PARAMETERS_LOCKED CORSTATUS_PRM_INVALID CORSTATUS_PRM_INVALID_VALUE CORSTATUS_PRM_MUTUALLY_EXCLUSIVE CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_PRM_READ_ONLY						
<b>Note</b>	See the section Data Structures in the <i>Sapera LT Acquisition Parameters Reference Manual</i> , for building correct values with specific macros.						
<b>See Also</b>	CorAcqGetPrm, CorAcqSetPrmEx and CorAcqSetPrms						

---

## CorAcqSetPrmEx

Set a complex acquisition parameter of an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqSetPrmEx</b> (CORACQ <i>hAcq</i> , UINT32 <i>prm</i> , void * <i>value</i> );						
<b>Description</b>	<p>Sets a complex acquisition device's parameter. A complex parameter is greater in size than an UINT32. If the parameter size is UINT32, use either CorAcqSetPrm or CorAcqSetPrmEx.</p> <p>Acquisition parameters are normally initialized all at once by CorAcqSetPrms. One may want to modified certain parameters at a later time, such as those related to camera swithing, brightness and contrast settings. In this case, CorAcqSetPrmEx (or CorAcqSetPrm) should be used for faster execution.</p>						
<b>Input</b>	<table><tr><td><i>hAcq</i></td><td>Acquisition resource handle</td></tr><tr><td><i>prm</i></td><td>Acquisition parameter to set</td></tr><tr><td><i>value</i></td><td>New value of the parameter</td></tr></table>	<i>hAcq</i>	Acquisition resource handle	<i>prm</i>	Acquisition parameter to set	<i>value</i>	New value of the parameter
<i>hAcq</i>	Acquisition resource handle						
<i>prm</i>	Acquisition parameter to set						
<i>value</i>	New value of the parameter						
<b>Output</b>	None						
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY CORSTATUS_PARAMETERS_LOCKED CORSTATUS_PRM_INVALID CORSTATUS_PRM_INVALID_VALUE CORSTATUS_PRM_MUTUALLY_EXCLUSIVE CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_PRM_READ_ONLY						
<b>See Also</b>	CorAcqGetPrm and CorAcqSetPrm						

---

## CorAcqSetPrms

Set camera-dependent and VIC-dependent parameter values of an acquisition device

**Prototype**      `CORSTATUS CorAcqSetPrms(CORACQ hAcq, CORVIC hVic, CORCAM hCam, UINT32 toUnlock);`

**Description**      Initializes an acquisition device with the specified camera-dependent and VIC-dependent parameter values.

The Sapera Development environment provides a Windows application called CameraExpert that allows the user to create/modify CAM and VIC files. Using CorVicLoad and CorCamLoad, the VIC and CAM resource handles can then be obtained from the CAM and VIC files respectively

If the acquisition parameters are locked (by a previous call to CorAcqGetPrms), then the same VIC and camera module handles that were used when locking the parameters initially must be used to set the parameters. Locking the parameters may allow faster hardware initialization depending on the actual device driver/hardware implementation because only the parameters that have changed since being locked will be reinitialized.

Also, in the specific case where the parameters are locked, the *toUnlock* flag is used to determined the state of the parameters upon returning from this function:

toUnlock = TRUE: unlock parameters

toUnlock = FALSE: keep parameters locked

Parameters can also be unlocked without any modifications by using CorAcqUnlock.

**Input**              *hAcq*              Acquisition resource handle  
                      *hVic*              VIC resource handle  
                      *hCam*              Camera resource handle  
                      *toUnlock*      Unlock acquisition parameters (TRUE or FALSE)

**Output**              None

**Return Value**      CORSTATUS\_OK  
                          CORSTATUS\_INVALID\_HANDLE  
                          CORSTATUS\_PARAMETERS\_LOCKED  
                          CORSTATUS\_PRM\_INVALID\_VALUE  
                          CORSTATUS\_PRM\_MUTUALLY\_EXCLUSIVE  
                          CORSTATUS\_PRM\_NOT\_AVAILABLE  
                          CORSTATUS\_ARG\_OUT\_OF\_RANGE

**See Also**            CorAcqGetPrms, CorAcqUnlock, CorVicNew and CorCamNew

---

## CorAcqSoftwareTrigger

Simulate a trigger to the acquisition device

**Prototype**      `CORSTATUS CorAcqSoftwareTrigger(CORACQ hAcq, UINT32 triggerType);`

**Description**      Calling this function will simulate a hardware trigger to the acquisition device.

**Input**              *hAcq*              Acquisition resource handle  
                      *UINT32*      Type of trigger: CORACQ\_CAP\_SOFTWARE\_TRIGGER.

**Output**              None

**Return Value**      CORSTATUS\_OK  
                          CORSTATUS\_PRM\_NOT\_AVAILABLE  
                          CORSTATUS\_INVALID\_HANDLE

---

## CorAcqUnlock

Unlock acquisition parameters of an acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqUnlock</b> (CORACQ <i>hAcq</i> , CORVIC <i>hVic</i> , CORCAM <i>hCam</i> );	
<b>Description</b>	Unlock the acquisition parameters previously locked by a call to CorAcqGetPrms.	
<b>Input</b>	<i>hAcq</i>	Acquisition device resource handle
	<i>hVic</i>	VIC resource handle
	<i>hCam</i>	Camera resource handle
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_PARAMETERS_LOCKED	
<b>Note</b>	The VIC and camera resource handles must be the same VIC and camera module handles that were used when locking the parameters with CorAcqGetPrms.	
<b>See Also</b>	CorAcqGetPrms and CorAcqSetPrms	

---

## CorAcqUnregisterCallback

Unregister callback function for an acquisition resource

<b>Prototype</b>	CORSTATUS <b>CorAcqUnregisterCallback</b> (CORACQ <i>hAcq</i> , PCORCALLBACK <i>callbackFct</i> );	
<b>Description</b>	Unregisters the specified acquisition resource callback function.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>callbackFct</i>	Callback function to unregister. See Data Types section for the PCORCALLBACK definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorAcqRegisterCallback	

---

## CorAcqUnregisterCallbackEx

Unregister callback function for an acquisition resource

<b>Prototype</b>	CORSTATUS <b>CorAcqUnregisterCallback</b> (CORACQ <i>hAcq</i> , PCOREVENTINFOCALLBACK <i>callback</i> );	
<b>Description</b>	Unregisters the specified acquisition resource callback function.	
<b>Input</b>	<i>hAcq</i>	Acquisition resource handle
	<i>callbackFct</i>	Callback function to unregister. See Data Types section for the PCOREVENTINFOCALLBACK definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorAcqRegisterCallbackEx	

---

# Camera Module Functions

The Camera Module manages all parameters that define a camera, such as camera type, video timings, and sync info. These parameters are usually fixed for a given camera. Parameters may be saved to or retrieved from a file and used to configure an Acquisition Module.

This section describes the functions of the Camera Module. The parameters and capabilities are described in the *Sapera LT Acquisition Parameters Reference Manual*.

Function	Description
CorCamFree	<i>Releases handle to a camera resource</i>
CorCamGetPrm	<i>Gets camera parameter value from a camera resource</i>
CorCamLoad	<i>Loads camera parameters from a file into a camera resource</i>
CorCamNew	<i>Creates a new camera resource</i>
CorCamSave	<i>Saves to a file the camera parameters of a camera resource</i>
CorCamSetPrm	<i>Sets a simple camera parameter of a camera resource</i>
CorCamSetPrmEx	<i>Sets a complex camera parameter of a camera resource</i>

---

## CorCamFree

Release handle to a camera resource

**Prototype**      CORSTATUS **CorCamFree**(CORCAM *hCam*);

**Description**    Releases handle to a camera resource.

**Input**            *hCam*      Camera resource handle

**Output**           None

**Return Value**   CORSTATUS\_OK  
CORSTATUS\_INVALID\_HANDLE

**See Also**        CorCamNew

---

## CorCamGetPrm

Get camera parameter value from a camera resource

**Prototype**      CORSTATUS **CorCamGetPrm**(CORCAM *hCam*, UINT32 *prm*, void \**value*);

**Description**    Gets a camera parameter value from a camera resource.

**Input**            *hCam*      Camera resource handle  
*prm*            Camera parameter requested

**Output**           *value*      Current value of the parameter

**Return Value**   CORSTATUS\_OK  
CORSTATUS\_ARG\_NULL (if *value* is NULL)  
CORSTATUS\_INVALID\_HANDLE  
CORSTATUS\_PRM\_INVALID

**See Also**        CorCamSetPrm and CorCamSetPrmEx



---

## CorCamLoad

Load camera parameters from a file into a camera resource

<b>Prototype</b>	CORSTATUS <b>CorCamLoad</b> (CORCAM <i>hCam</i> , const char * <i>filename</i> );
<b>Description</b>	Fills the camera-dependent acquisition parameters from a file. The function does not initialize the actual hardware. The function CorAcqGetPrms must be called to perform the hardware initialization.
<b>Input</b>	<i>filename</i> String specifying the path and filename
<b>Output</b>	<i>hCam</i> Camera resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>filename</i> is NULL) CORSTATUS_FILE_OPEN_ERROR CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_IMPLEMENTED
<b>See Also</b>	CorCamSave and CorCamNew

---

## CorCamNew

Create a new camera resource

<b>Prototype</b>	CORSTATUS <b>CorCamNew</b> (CORSERVER <i>hServer</i> , CORCAM * <i>hCam</i> );
<b>Description</b>	Allocates the data structure (dynamic resource) to store the camera parameters and returns the handle to it.  The data structure is allocated on the local server; that is, where the application is running (typically the Host computer). Camera parameters may be loaded from the "Camera file" using the CorCamLoad function. The <i>hCamc</i> handle is used by the CorAcqGetPrms function to initialize the acquisition device with the camera parameters.
<b>Input</b>	<i>hServer</i> Server handle
<b>Output</b>	<i>hCam</i> Camera resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>hCam</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY
<b>See Also</b>	CorCamFree, CorCamLoad and CorAcqGetPrms

---

## CorCamSave

Save the camera parameters of a camera resource

<b>Prototype</b>	CORSTATUS <b>CorCamSave</b> (CORCAM <i>hCam</i> , const char * <i>filename</i> );
<b>Description</b>	Saves to a file the camera-dependent acquisition parameters of a camera resource.
<b>Input</b>	<i>hCam</i> Camera resource handle <i>filename</i> String specifying the path and filename.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>filename</i> is NULL) CORSTATUS_FILE_WRITE_ERROR CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_IMPLEMENTED
<b>See Also</b>	CorCamLoad

---

## CorCamSetPrm

Set a simple camera parameter of a camera resource

<b>Prototype</b>	CORSTATUS <b>CorCamSetPrm</b> (CORCAM <i>hCam</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );	
<b>Description</b>	Sets a simple camera resource parameter. A simple parameter is one that can fit inside an UINT32. If the parameter is complex, use the function CorCamSetPrmEx.  The CorAcqSetPrms function must then be called to initialize the acquisition hardware with the CAM resource parameters. Alternatively, simple CAM parameters can be applied individually to the acquisition hardware using CorAcqSetPrm.	
<b>Input</b>	<i>hCam</i>	Camera resource handle
	<i>prm</i>	Camera parameter to modify
	<i>value</i>	New value of the parameter
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID	
<b>See Also</b>	CorCamGetPrm, CorCamSetPrmEx and CorAcqSetPrms	

---

## CorCamSetPrmEx

Set a complex camera parameter of a camera resource

<b>Prototype</b>	CORSTATUS <b>CorCamSetPrmEx</b> (CORCAM <i>hCam</i> , UINT32 <i>prm</i> , void * <i>value</i> );	
<b>Description</b>	Sets a complex camera resource parameter. A complex parameter is of size greater than an UINT32. If the parameter size is UINT32, use either CorCamSetPrm or CorCamSetPrmEx.  The CorAcqSetPrms function must then be called to initialize the acquisition hardware with the CAM resource parameters. Alternatively, complex CAM parameters may be applied individually to the acquisition hardware using CorAcqSetPrmEx.	
<b>Input</b>	<i>hCam</i>	Camera resource handle
	<i>prm</i>	Camera parameter to modify
	<i>value</i>	New value of the parameter
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID	
<b>See Also</b>	CorCamGetPrm, CorCamSetPrm and CorAcqSetPrms	

---

## VIC Module Functions

The VIC (Video Input Conditioning) Module manages all parameters that are camera-independent, such as brightness and contrast. Parameters may be saved to or retrieved from a file and used to configure the acquisition hardware through Acquisition Module functions.

This section describes the functions of the VIC Module. The parameters and capabilities are described in the *Sapera LT Acquisition Parameters Reference Manual*.

Function	Description
CorVicFree	Releases handle to a VIC resource
CorVicGetPrm	Gets VIC parameters value from a VIC resource
CorVicLoad	Loads VIC parameters from a file into a VIC resource
CorVicNew	Allocates the data structure to store the VIC parameters
CorVicSave	Saves to a file the VIC parameters of a VIC resource
CorVicSetPrm	Sets a simple VIC parameter of a VIC resource
CorVicSetPrmEx	Sets a complex VIC parameter of a VIC resource

---

### CorVicFree

Release handle to a VIC resource

<b>Prototype</b>	CORSTATUS <b>CorVicFree</b> (CORVIC <i>hVic</i> );
<b>Description</b>	Releases the handle to a VIC resource.
<b>Input</b>	<i>hVic</i> VIC resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorVicNew

---

### CorVicGetPrm

Get VIC parameter value from a VIC resource

<b>Prototype</b>	CORSTATUS <b>CorVicGetPrm</b> (CORVIC <i>hVic</i> , UINT32 <i>prm</i> , void * <i>value</i> );
<b>Description</b>	Gets a VIC parameter value from a VIC resource.
<b>Input</b>	<i>hVic</i> VIC resource handle <i>prm</i> VIC parameter requested
<b>Output</b>	<i>value</i> Current value of the parameter
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID
<b>See Also</b>	CorVicSetPrm and CorVicSetPrmEx

---

## CorVicLoad

Load VIC parameters from a file into a VIC resource

<b>Prototype</b>	CORSTATUS <b>CorVicLoad</b> (CORVIC <i>hVic</i> , const char * <i>filename</i> );
<b>Description</b>	Loads VIC parameters from a file into a VIC resource.
<b>Input</b>	<i>filename</i> String specifying the path and filename
<b>Output</b>	<i>hVic</i> VIC resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>filename</i> is NULL) CORSTATUS_FILE_OPEN_ERROR CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_IMPLEMENTED
<b>See Also</b>	CorVicSave

---

## CorVicNew

Create a new VIC resource handle

<b>Prototype</b>	CORSTATUS <b>CorVicNew</b> (CORSERVER <i>hServer</i> , CORVIC * <i>hVic</i> );
<b>Description</b>	Allocates the data structure (dynamic resource) to store the VIC parameters and returns the handle to it.  The data structure is allocated on the local server, that is, where the application is running (typically the Host computer). The VIC parameters may be loaded from the "VIC file" using the CorVicLoad function. The <i>hVic</i> handle is used by the CorAcqGetPrms function to initialize the acquisition device with the VIC parameters.
<b>Input</b>	<i>hServer</i> Handle to the Server where the VIC resource (data structure) will be allocated.
<b>Output</b>	<i>hVic</i> New VIC resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>hVic</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY
<b>See Also</b>	CorVicFree and CorVicLoad

---

## CorVicSave

Save to a file the VIC parameters of a VIC resource

<b>Prototype</b>	CORSTATUS <b>CorVicSave</b> (CORVIC <i>hVic</i> , const char * <i>filename</i> );
<b>Description</b>	Saves to a file the VIC resource parameters.
<b>Input</b>	<i>hVic</i> VIC resource handle <i>filename</i> String specifying the path and filename
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>filename</i> is NULL) CORSTATUS_FILE_WRITE_ERROR CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_IMPLEMENTED
<b>See Also</b>	CorVicLoad

---

## CorVicSetPrm

Set a simple VIC parameter of a VIC resource

<b>Prototype</b>	CORSTATUS <b>CorVicSetPrm</b> (CORVIC <i>hVic</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );		
<b>Description</b>	Sets a simple VIC resource parameter. A simple parameter is one that fits inside an UINT32. If the parameter is complex, use CorVicSetPrmEx.  The CorAcqSetPrms function must then be called to initialize the acquisition hardware with the VIC resource parameters. Alternatively, simple VIC parameters may be applied individually to the acquisition hardware using CorAcqSetPrm.		
<b>Input</b>	<i>hVic</i>	VIC resource handle	
	<i>prm</i>	VIC parameter to modify	
	<i>value</i>	New value of the parameter	
<b>Output</b>	None		
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID		
<b>See Also</b>	CorVicGetPrm, CorVicSetPrmEx, CorCamSetPrm and CorAcqSetPrms		

---

## CorVicSetPrmEx

Set a complex VIC parameter of a VIC resource

<b>Prototype</b>	CORSTATUS <b>CorVicSetPrmEx</b> (CORVIC <i>hVic</i> , UINT32 <i>prm</i> , void * <i>value</i> );		
<b>Description</b>	Sets a complex VIC resource parameter. A complex parameter has a size greater than an UINT32. If the parameter size is UINT32, use either CorVicSetPrm or CorVicSetPrmEx.  The CorAcqSetPrms function must then be called to initialize the acquisition hardware with the VIC resource parameters. Alternatively, complex VIC parameters may be applied individually to the acquisition hardware using CorAcqSetPrmEx.		
<b>Input</b>	<i>hVic</i>	VIC resource handle	
	<i>prm</i>	VIC parameter to modify	
	<i>value</i>	New value of the parameter	
<b>Output</b>	None		
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID		
<b>See Also</b>	CorVicGetPrm, CorVicSetPrm, CorCamSetPrmEx and CorAcqSetPrms		

# Sapera Camera Acquisition

## AcqDevice Module

The *AcqDevice* module functions provide read/write features from/to devices such as a GigE-Vision camera. The module also contains functions for sending commands and registering events to devices.



**Note:** Frame-grabber devices are not supported by this module. The *Acq* module must be used in such cases.

## AcqDevice Parameters

ID	Parameters	Attribute
0x00	CORACQDEVICE_PRM_LABEL	Read-only
0x01	CORACQDEVICE_PRM_UPDATE_FEATURE_MODE	Read/write
0x02	CORACQDEVICE_PRM_CONFIG_NAME	Read/write
0x03	CORACQDEVICE_PRM_MODE_NAME	Read/write

### CORACQDEVICE\_PRM\_LABEL

**Description** Acquisition device ID: Zero-terminated array of characters with a fixed size of 128 bytes.

**Type** CHAR[128]

**Note** This parameter is read-only.

### CORACQDEVICE\_PRM\_CONFIG\_NAME

**Description** Defines the configuration name to use when saving the device features using `CorAcqDeviceSaveFeatures`. It is then possible to uniquely identify different configuration files when the company name, camera model name, and mode name are the same. For example, "High Contrast"

When loading a configuration file using `CorAcqDeviceLoadFeatures`, this parameter is automatically updated.

**Type** CHAR[64]

**See also** CORACQDEVICE\_PRM\_MODE\_NAME

### CORACQDEVICE\_PRM\_MODE\_NAME

**Description** Defines the mode name to use when saving the device features using `CorAcqDeviceSaveFeatures`. It is then possible to uniquely identify different modes when the company name and camera model name are the same. For example, "Single-Channel, Free-Running"

When loading a configuration file using `CorAcqDeviceLoadFeatures`, this parameter is automatically updated.

**Type** CHAR[64]

**See also** CORACQDEVICE\_PRM\_CONFIG\_NAME

---

## CORACQDEVICE\_PRM\_UPDATE\_FEATURE\_MODE

<b>Description</b>	Defines the mode by which features are written to the device. In the automatic mode (CORACQDEVICE_VAL_UPDATE_FEATURE_MODE_AUTO) every time a feature is set using the <i>CorAcqDeviceSetFeatureValue...</i> or <i>CorAcqDeviceSetFeatureData...</i> functions the feature value is immediately written to the device. In the manual mode (CORACQDEVICE_VAL_UPDATE_FEATURE_MODE_MANUAL) each feature is temporarily cached until the <i>CorAcqDeviceUpdateFeaturesToDevice</i> is called to write all features to the device at once.
<b>Type</b>	UINT32
<b>Values</b>	CORACQDEVICE_VAL_UPDATE_FEATURE_MODE_AUTO (0x00) Each feature is written to the device individually without being cached. CORACQDEVICE_VAL_UPDATE_FEATURE_MODE_MANUAL (0x01) Each feature is temporarily cached until <i>CorAcqDeviceUpdateFeaturesToDevice</i> is called.
<b>Note</b>	The default mode is automatic. However when setting a series of parameters that are related to each other (for instance a region-of-interest composed of four values) the manual mode is useful to avoid invalid temporary device states.

## AcqDevice Functions

Function	Description
<b>General Functions</b>	
CorAcqDeviceResetModule	Resets the resources associated with the server's acquisition devices
CorAcqDeviceGetCount	Gets the number of acquisition devices on a server
CorAcqDeviceGetHandle	Gets a handle to an acquisition device with read/write access
CorAcqDeviceGetHandleReadOnly	Gets a handle to an acquisition device with read-only access
CorAcqDeviceRelease	Releases a handle to an acquisition device
CorAcqDeviceReset	Resets an acquisition device
<b>Module Capability and Parameter Access Functions</b>	
CorAcqDeviceGetCap	Gets a capability value from an acquisition device
CorAcqDeviceGetPrm	Gets a parameter value from an acquisition device
CorAcqDeviceSetPrm	Sets a simple parameter value to an acquisition device
CorAcqDeviceSetPrmEx	Sets a complex parameter value to an acquisition device
<b>Feature Access Functions</b>	
CorAcqDeviceGetFeatureCount	Returns the number of features supported by the acquisition device
CorAcqDeviceGetFeatureNameByIndex	Returns the name of a feature associated with a specified index
CorAcqDeviceGetFeatureIndexByName	Returns the index of a feature associated with a specified name
CorAcqDeviceIsFeatureAvailable	Returns whether or not a feature is supported by the acquisition device
CorAcqDeviceGetFeatureInfoByName	Returns information on a feature associated with a specified name
CorAcqDeviceGetFeatureInfoByIndex	Returns information on a feature associated with a specified index
CorAcqDeviceGetFeatureValueByName	Returns the value of a simple feature associated with a specified name
CorAcqDeviceGetFeatureValueByIndex	Returns the value of a simple feature associated with a specified index
CorAcqDeviceGetFeatureDataByName	Returns the value of a complex feature associated with a specified name
CorAcqDeviceGetFeatureDataByIndex	Returns the value of a complex feature associated with a specified index
CorAcqDeviceSetFeatureValueByName	Sets the value of a simple feature associated with a specified name
CorAcqDeviceSetFeatureValueByIndex	Sets the value of a simple feature associated with a specified index
CorAcqDeviceSetFeatureDataByName	Sets the value of an complex feature associated with a specified name
CorAcqDeviceSetFeatureDataByIndex	Sets the value of a complex feature associated with a specified index
CorAcqDeviceUpdateFeaturesToDevice	Sets all the features to the acquisition device at once
CorAcqDeviceUpdateFeaturesFromDevice	Gets all the features from the acquisition device at once
CorAcqDeviceLoadFeatures	Loads all the features from a configuration file
CorAcqDeviceSaveFeatures	Saves all (or a subset of) features to a configuration file.
CorAcqDeviceGetCategoryCount	Gets the number of unique feature category names
CorAcqDeviceGetCategoryPath	Gets the full path name of a unique feature category



## Event Management Functions

CorAcqDeviceGetEventCount	Returns the number of events supported by the acquisition device
CorAcqDeviceGetEventNameByIndex	Returns the name of an event associated with a specified index
CorAcqDeviceGetEventIndexByName	Returns the index of an event associated with a specified name
CorAcqDeviceIsEventAvailable	Returns whether or not an event is supported by the acquisition device
CorAcqDeviceRegisterCallbackByName	Registers a callback function for the event associated with a specified name
CorAcqDeviceRegisterCallbackByIndex	Registers a callback function for the event associated with a specified index
CorAcqDeviceUnregisterCallbackByName	Unregisters a callback function on the event associated with a specified name
CorAcqDeviceUnregisterCallbackByIndex	Unregisters a callback function on the event associated with a specified index
CorAcqDeviceIsCallbackRegisteredByName	Returns whether or not a callback function was registered on the event associated with a specified name
CorAcqDeviceIsCallbackRegisteredByIndex	Returns whether or not a callback function was registered on the event associated with a specified index

## File Access Functions

CorAcqDeviceIsFileAccessAvailable	Returns whether or not file access is supported by the acquisition device
CorAcqDeviceGetFileCount	Returns the number of files supported by the acquisition device
CorAcqDeviceGetFileNameByIndex	Returns the name of a file associated with a specified index
CorAcqDeviceGetFileIndexByName	Returns the index of a file associated with a specified name
CorAcqDeviceGetFilePropertyByIndex	Gets a property of a file associated with a specified index on the acquisition device
CorAcqDeviceGetFilePropertyByName	Gets a property of a file associated with a specified name on the acquisition device
CorAcqDeviceReadFileByIndex	Reads a file associated with a specified index from an acquisition device to a system host
CorAcqDeviceReadFileByName	Writes a file associated with a specified name from an acquisition device to a system host
CorAcqDeviceWriteFileByIndex	Writes a file associated with a specified index from a system host to an acquisition device
CorAcqDeviceReadFileByName	Writes a file associated with a specified name from a system host to an acquisition device
CorAcqDeviceDeleteFileByIndex	Deletes a file associated with a specified index from the acquisition device
CorAcqDeviceDeleteFileByName	Deletes a file associated with a specified name from the acquisition device

## General Functions

The general functions are used to enumerate the acquisition devices in a system and enable/disable access to those devices.

---

### CorAcqDeviceGetCount

Gets the number of server acquisition devices.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetCount</b> (CORSERVER <i>server</i> , PUINT32 <i>count</i> );
<b>Description</b>	Gets the number of acquisition devices available on a server.
<b>Input</b>	<i>server</i> Server handle
<b>Output</b>	<i>count</i> Number of acquisition devices. The value of <i>count</i> is 0 when no acquisition device is available.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_NOT_IMPLEMENTED (when there is no Acquisition device supported by the specified server) CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>count</i> is NULL)

---

### CorAcqDeviceGetHandle

Gets a handle to an acquisition device with read/write access.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetHandle</b> (CORSERVER <i>server</i> , UINT32 <i>index</i> , PCORACQDEVICE <i>acqDevice</i> );
<b>Description</b>	Gets a handle to an acquisition device with read/write access. If the handle is already used by another application, use CorAcqDeviceGetHandleReadOnly to obtain read-only access to the device.
<b>Input</b>	<i>server</i> Handle to a server that contains an <i>AcqDevice</i> resource <i>index</i> Specifies the acquisition device to select. Valid values are in the range [0... <i>count</i> -1], where <i>count</i> is the value returned by CorAcqDeviceGetCount.
<b>Output</b>	<i>acqDevice</i> Acquisition resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_ACCESSIBLE CORSTATUS_RESOURCE_IN_USE
<b>See Also</b>	CorAcqDeviceGetCount, CorAcqDeviceRelease, CorAcqDeviceGetHandleReadOnly

---

## CorAcqDeviceGetHandleReadOnly

Gets a handle to an acquisition device with read-only access.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetHandleReadOnly</b> (CORSERVER <i>server</i> , UINT32 <i>index</i> , PCORACQDEVICE <i>acqDevice</i> );	
<b>Description</b>	Gets a handle to an acquisition device with read-only access. If the handle is already used by another application use this function to obtain read-only access to the device. To know what functions of the <i>AcqDevice</i> module are accessible with this type of handle, refer to the function documentation.	
<b>Input</b>	<i>server</i>	Server handle
	<i>index</i>	Specifies the acquisition device to select. Valid values are in the range [0... <i>count</i> -1], where <i>count</i> is the value returned by CorAcqDeviceGetCount.
<b>Output</b>	<i>acqDevice</i>	Acquisition resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_ACCESSIBLE	
<b>See Also</b>	CorAcqDeviceGetCount, CorAcqDeviceRelease, CorAcqDeviceGetHandle	

---

## CorAcqDeviceRelease

Releases a handle to an acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceRelease</b> (CORACQDEVICE <i>acqDevice</i> );	
<b>Description</b>	Releases a handle to an acquisition device.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorAcqDeviceGetHandle, CorAcqDeviceGetHandleReadOnly	

---

## CorAcqDeviceReset

Resets an acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceReset</b> (CORACQDEVICE <i>acqDevice</i> );	
<b>Description</b>	Reset and restore the default acquisition parameter values of the specified acquisition device.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_SOFTWARE_ERROR	
<b>Note</b>	This function is not valid for read-only handles.	
<b>See Also</b>	CorAcqDeviceResetModule	

---

## CorAcqDeviceResetModule

Resets the resources associated with the server's acquisition devices.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceResetModule</b> (CORSERVER <i>server</i> );
<b>Description</b>	Releases all resources (handle, memory) currently allocated. Before using this function, make certain that no other application is currently using any acquisition device resource. Proceed with caution when using this function.
<b>Input</b>	<i>hServer</i> <i>Server handle</i>
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>Note</b>	This function is not valid for read-only handles.
<b>See Also</b>	CorAcqDeviceReset

## Module Capability and Parameter Access Functions

The module capability and parameter access functions provide read/write capabilities and parameters for acquisition devices.



**Note:** *Capabilities* and *parameters* control the behavior of an *AcqDevice* module. They are different from *features* which describe the attributes of the hardware device itself.

---

### CorAcqDeviceGetCap

Gets a capability value from an acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetCap</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>cap</i> , void * <i>value</i> );	
<b>Description</b>	Gets a capability value from an acquisition device. A capability defines the availability of the associated parameter.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>cap</i>	Acquisition capability requested
<b>Output</b>	<i>value</i>	Value of the requested capability
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>value</i> is NULL) CORSTATUS_CAP_INVALID	
<b>See Also</b>	CorAcqDeviceGetPrm	

---

### CorAcqDeviceGetPrm

Gets a parameter value from an acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetPrm</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>prm</i> , void * <i>value</i> );	
<b>Description</b>	Gets a parameter (simple and complex) value from an acquisition device. Make certain that the data storage pointed to by <i>value</i> matches the data type of the specified parameter. See the description of each parameter for the required data storage type.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>prm</i>	Acquisition parameter requested
<b>Output</b>	<i>value</i>	Current value of the requested parameter
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>value</i> is NULL) CORSTATUS_PRM_INVALID	
<b>See Also</b>	CorAcqDeviceSetPrm and CorAcqDeviceSetPrmEx	

---

## CorAcqDeviceSetPrm

Sets a simple parameter value to an acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceSetPrm</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );	
<b>Description</b>	Sets a simple acquisition device parameter. A simple parameter is one that fits inside an UINT32. For complex parameters use CorAcqDeviceSetPrmEx. See the description of each parameter for the required data storage type.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>prm</i>	Acquisition parameter to set
	<i>value</i>	New value of the parameter
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY CORSTATUS_PRM_INVALID CORSTATUS_PRM_INVALID_VALUE CORSTATUS_PRM_MUTUALLY_EXCLUSIVE CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_PRM_READ_ONLY	
<b>Note</b>	This function is not valid for read-only handles.	
<b>See Also</b>	CorAcqDeviceGetPrm, CorAcqDeviceSetPrmEx	

---

## CorAcqDeviceSetPrmEx

Sets a complex parameter value to an acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceSetPrmEx</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>prm</i> , const void * <i>value</i> );	
<b>Description</b>	Sets a complex acquisition device's parameter. A complex parameter is greater in size than an UINT32. If the parameter size is UINT32, use either CorAcqDeviceSetPrm or CorAcqDeviceSetPrmEx. See the description of each parameter for the required data storage type.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>prm</i>	Acquisition parameter to set
	<i>value</i>	New value of the parameter
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY CORSTATUS_PRM_INVALID CORSTATUS_PRM_INVALID_VALUE CORSTATUS_PRM_MUTUALLY_EXCLUSIVE CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_PRM_READ_ONLY	
<b>Note</b>	This function is not valid for read-only handles.	
<b>See Also</b>	CorAcqDeviceGetPrm and CorAcqDeviceSetPrm	

## Feature Access Functions

The feature access functions are used to enumerate the list of features supported by the device, get information associated with each of those features and read/write the feature values from/to the device.

---

### CorAcqDeviceGetCategoryCount

Gets the number of unique feature category names.

**Prototype**      `CORSTATUS CorAcqDeviceGetCategoryCount(CORACQDEVICE acqDevice, PUINT32 count);`

**Description**      Gets the number of unique feature category names. This is equivalent to getting the information for all available features (CorAcqDeviceGetFeatureCount followed by CorAcqDeviceGetFeatureInfoByIndex), retrieving the value of CORFEATURE\_PRM\_CATEGORY for each, and then counting the unique category names.

After calling this function, you can call CorAcqDeviceGetCategoryPath to retrieve full path names for individual features, using a category index which can be any value in the range [0...*count*-1].

**Input**              *acqDevice*      Acquisition resource handle

**Output**            *count*            Number of feature categories

**Return Value**    CORSTATUS\_OK if successful.  
For information on handling other CORSTATUS return values see the "Error Management" section.

**See Also**          CorAcqDeviceGetCategoryPath

---

### CorAcqDeviceGetCategoryPath

Gets the full path name of a unique feature category.

**Prototype**      `CORSTATUS CorAcqDeviceGetCategoryPath (CORACQDEVICE acqDevice, UINT32 categoryIndex, PSTR path, UINT32 pathSize);`

**Description**      Returns the full path name of a feature category at a specified index, following a call to the CorAcqDeviceGetCategoryCount function to get the total number of categories. The returned path name is formatted according to the following rules:

All path names begin with "\Root" or "\SaperaRoot"

Top level categories are returned as "\Root\CategoryName"

Second level categories are returned as "\Root\CategoryName\SubCategoryName"

and so on...

This allows parsing of category path names so that these can be shown using a hierarchical view in a GUI based application.

**Input**              *acqDevice*      Acquisition resource handle

*categoryIndex*    Index of the category. All indices in the range [0 ... value returned by CorAcqDeviceGetCategoryCount – 1] are valid.

*pathSize*          Size (in bytes) of the buffer pointed to by *path*

**Output**            *path*            Full path name of the category associated with the specified index

**Return Value**    CORSTATUS\_OK if successful.  
For information on handling other CORSTATUS return values see the "Error Management" section.

**See Also**          CorAcqDeviceGetCategoryCount

---

## CorAcqDeviceGetFeatureCount

Returns the number of features supported by the acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFeatureCount</b> (CORACQDEVICE <i>acqDevice</i> , PUINT32 <i>count</i> );
<b>Description</b>	Returns the number of features supported by the acquisition device. Devices do not necessarily support the same feature set. For instance you can use this function to retrieve the number of features and then get information about those features using <code>CorAcqDeviceGetFeatureInfo</code> , using a feature index which can be any value in the range [0... <i>count</i> -1].
<b>Input</b>	<i>acqDevice</i> Acquisition resource handle
<b>Output</b>	<i>count</i> Number of features
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.

---

## CorAcqDeviceGetFeatureDataByIndex

Returns the value of a complex feature associated with a specified index.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFeatureDataByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , CORHANDLE <i>dataDest</i> );
<b>Description</b>	<p>Returns the value of a <i>complex type</i> feature associated with a specified index. A complex type feature is a feature that is contained in a handle. See CORFEATURE_PRM_TYPE for a list of simple and complex types. For simple type features you must use the <code>CorAcqDeviceGetFeatureValueByIndex</code> instead.</p> <p>The <i>dataDest</i> handle must be allocated by the user prior to calling this function. For example if the feature is contained in a <i>CorBuffer</i> module, you must allocate the buffer using <code>CorBufferNew</code>. Attributes of the buffer such as <i>width</i>, <i>height</i> and <i>format</i> must be obtained through others features provided by your acquisition device. Upon calling this function the buffer's data from the device will be copied to your buffer object.</p>
<b>Input</b>	<i>acqDevice</i> Acquisition resource handle <i>index</i> Index of the feature. All indices in the range [0 ... value returned by <code>CorAcqDeviceGetFeatureCount</code> – 1] are valid.
<b>Output</b>	<i>dataDest</i> Resource handle to store feature data
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>See Also</b>	<code>CorAcqDeviceGetFeatureCount</code> , <code>CorAcqDeviceGetFeatureValueByIndex</code> , <code>CorAcqDeviceGetFeatureDataByName</code>



---

## CorAcqDeviceGetFeatureDataByName

Returns the value of a complex feature associated with a specified name.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFeatureDataByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , CORHANDLE <i>dataDest</i> );	
<b>Description</b>	<p>Returns the value of a <i>complex type</i> feature associated with a specified name. A complex type feature is a feature that is contained in a handle. See CORFEATURE_PRM_TYPE for a list of simple and complex types. For simple type features you must use the <i>CorAcqDeviceGetFeatureValueByName</i> instead.</p> <p>The <i>dataDest</i> handle must be allocated by the user prior to calling this function. For example if the feature is contained in a <i>CorBuffer</i> module, you must allocate the buffer using <i>CorBufferNew</i>. Attributes of the buffer such as <i>width</i>, <i>height</i> and <i>format</i> must be obtained through others features provided by your acquisition device. Upon calling this function the buffer's data from the device will be copied to your buffer object.</p>	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>name</i>	Feature name. See device User's Manual for the list of supported features.
<b>Output</b>	<i>dataDest</i>	Resource handle to store feature data
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceSetFeatureValueByName, CorAcqDeviceSetFeatureDataByIndex	

---

## CorAcqDeviceGetFeatureIndexByName

Returns the index of a feature associated with a specified name.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFeatureIndexByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , PUINT32 <i>index</i> );	
<b>Description</b>	<p>Returns the index of a feature associated with a specified name. This function is useful in building a list of indexes associated with the feature names you commonly use. Then those features are accessed by index to increase performance.</p>	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>name</i>	Feature name. See device User's Manual for the list of supported features.
<b>Output</b>	<i>index</i>	Index of the feature associated with the specified name
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceGetFeatureNameByIndex	

---

## CorAcqDeviceGetFeatureInfoByIndex

Returns information on a feature associated with a specified index.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFeatureInfoByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , CORFEATURE <i>feature</i> );	
<b>Description</b>	Returns information on a feature associated with a specified index. All information about the feature is stored in a <i>CorFeature</i> object. The <i>CorFeature</i> object contains the attributes of the feature such as name, type, range, and so forth. See the <i>CorFeature</i> module for more details.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>index</i>	Index of the feature. All indices in the range [0 ... value returned by CorAcqDeviceGetFeatureCount – 1] are valid.
<b>Output</b>	<i>feature</i>	Feature resource handle to store feature information
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceGetFeatureCount, CorAcqDeviceGetFeatureInfoByName, Feature Module	

---

## CorAcqDeviceGetFeatureInfoByName

Returns information on a feature associated with a specified name.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFeatureInfoByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , CORFEATURE <i>feature</i> );	
<b>Description</b>	Returns information on a feature associated with a specified name. All the information about the feature is stored in a <i>CorFeature</i> object. The <i>CorFeature</i> object contains the attributes of the feature such as name, type, range, and so forth. See the <i>CorFeature</i> module for more details.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>name</i>	Feature name. See device User's Manual for the list of supported features.
<b>Output</b>	<i>feature</i>	Feature resource handle to store feature information
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceGetFeatureInfoByIndex, Feature Module	

---

## CorAcqDeviceGetFeatureNameByIndex

Returns the name of a feature associated with a specified index

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFeatureNameByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , PSTR <i>name</i> , UINT32 <i>nameSize</i> );	
<b>Description</b>	Returns the name of a feature associated with a specified index. For instance you can use this function to display the name of all features supported by the device.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>index</i>	Index of the feature. All indices in the range [0 ... value returned by CorAcqDeviceGetFeatureCount – 1] are valid.
	<i>nameSize</i>	Size (in bytes) of the buffer pointed to by <i>name</i>
<b>Output</b>	<i>name</i>	Name of the feature associated with the specified index
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceGetFeatureIndexByName	

---

## CorAcqDeviceGetFeatureValueByIndex

Returns the value of a simple feature associated with a specified index.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFeatureValueByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , void * <i>value</i> , UINT32 <i>valueSize</i> );	
<b>Description</b>	<p>Returns the value of a <i>simple type</i> feature associated with a specified index. A simple type feature is a feature that is NOT contained in a handle. See CORFEATURE_PRM_TYPE for a list of simple and complex types. For complex type features you must use the <i>CorAcqDeviceGetFeatureDataByIndex</i> instead.</p> <p>To determine the size of the buffer pointed to by <i>value</i> you must obtain the type of the feature using <i>CorAcqDeviceGetFeatureInfoByIndex</i>. Each feature type has its predetermined size.</p>	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>index</i>	Index of the feature. All indices in the range [0 ... value returned by <i>CorAcqDeviceGetFeatureCount</i> – 1] are valid.
	<i>valueSize</i>	Size of the buffer pointed to by <i>value</i> (in bytes)
<b>Output</b>	<i>value</i>	Address of a buffer to store the feature value
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>Note</b>	Except for unitless features, each feature has its specific native unit, for example millisecond, KHz, tenth of degree, and so forth. This information is obtained through the CORFEATURE_PRM_SI_UNIT and CORFEATURE_PRM_SI_TO_NATIVE_EXP10 parameters.	
<b>See Also</b>	<i>CorAcqDeviceGetFeatureCount</i> , <i>CorAcqDeviceGetFeatureDataByIndex</i> , <i>CorAcqDeviceGetFeatureValueByName</i>	

---

## CorAcqDeviceGetFeatureValueByName

Returns the value of a simple feature associated with a specified name.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFeatureValueByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , void * <i>value</i> , UINT32 <i>valueSize</i> );	
<b>Description</b>	<p>Returns the value of a <i>simple type</i> feature associated with a specified name. A simple type feature is a feature that is NOT contained in a handle. See CORFEATURE_PRM_TYPE for a list of simple and complex types. For complex type features you must use the <i>CorAcqDeviceGetFeatureDataByName</i> instead.</p> <p>To determine the size of the buffer pointed to by <i>value</i> you must obtain the type of the feature using <i>CorAcqDeviceGetFeatureInfoByName</i>. Each feature type has its predetermined size.</p>	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>name</i>	Feature name. See device User's Manual for the list of supported features.
	<i>valueSize</i>	Size of the buffer pointed to by <i>value</i> (in bytes)
<b>Output</b>	<i>value</i>	Address of a buffer to store the feature value
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>Note</b>	Except for unitless features, each feature has its specific native unit, for example millisecond, KHz, tenth of degree, and so forth. This information is obtained through the CORFEATURE_PRM_SI_UNIT and CORFEATURE_PRM_SI_TO_NATIVE_EXP10 parameters.	
<b>See Also</b>	<i>CorAcqDeviceGetFeatureDataByName</i> , <i>CorAcqDeviceGetFeatureValueByIndex</i>	

---

## CorAcqDeviceIsFeatureAvailable

Returns whether or not a feature is supported by the acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceIsFeatureAvailable</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , PUINT32 <i>isAvailable</i> );
<b>Description</b>	Returns whether or not a feature is supported by the acquisition device. This function is useful when an application supports several acquisition devices each having a different feature set.
<b>Input</b>	<i>acqDevice</i> Acquisition resource handle <i>name</i> Feature name. See device User's Manual for the list of supported features.
<b>Output</b>	<i>isAvailable</i> True (1) if the feature is supported by the device. False (0) otherwise
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.

---

## CorAcqDeviceLoadFeatures

Loads all device features from a configuration file.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceLoadFeatures</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR filename);
<b>Description</b>	Loads all the features from a configuration file. This function reads the features from a <i>Sapera LT's CCF File</i> and writes them to the device. The CCF file is generated by the <i>Sapera LT CamExpert Program</i> .  For devices that support hardware persistence storage (see your Acquisition Device User's Manual) loading a CCF file is not mandatory. For other devices you must load a CCF file to ensure the device is in a usable state.
<b>Input</b>	<i>acqDevice</i> Acquisition resource handle <i>filename</i> Name of the configuration file to load features from
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>Note</b>	This function is not valid for read-only handles.
<b>See Also</b>	CorAcqDeviceSaveFeatures

---

## CorAcqDeviceSaveFeatures

Saves all or a subset of features to a configuration file.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceSaveFeatures</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>filename</i> );	
<b>Description</b>	<p>Saves all or a subset of the device features to a configuration file. This function reads the features from the device and writes them to a <i>Sapera LT's CCF File</i>.</p> <p>Not all features are saved. For example read-only features are not saved by default. To know what features are saved by default refer to CORFEATURE_PRM_SAVED_TO_CONFIG_FILE parameter. This parameter also allows you to control whether each individual feature is saved or not.</p> <p>This function is useful for devices that do not support hardware persistence storage (see the Acquisition Device User's Manual) in order to retrieve the feature values after a shut down of the device.</p>	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>filename</i>	Name of the configuration file to save features to
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceLoadFeatures	

---

## CorAcqDeviceSetFeatureDataByIndex

Sets the value of a complex feature associated with a specified index.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceSetFeatureDataByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , CORHANDLE <i>dataSrc</i> );	
<b>Description</b>	<p>Sets the value of a <i>complex type</i> feature associated with a specified index. A complex type feature is a feature that is contained in a handle. See CORFEATURE_PRM_TYPE for a list of simple and complex types. For simple type features you must use <i>CorAcqDeviceSetFeatureValueByIndex</i> instead.</p> <p>The <i>dataSrc</i> handle must be a valid handle containing the feature data to be set.</p>	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>index</i>	Index of the feature. All indices in the range [0 ... value returned by CorAcqDeviceGetFeatureCount – 1] are valid.
	<i>dataSrc</i>	Resource handle that contains feature data
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>Note</b>	This function is not valid for read-only handles.	
<b>See Also</b>	CorAcqDeviceGetFeatureCount, CorAcqDeviceSetFeatureValueByIndex, CorAcqDeviceSetFeatureDataByName	

---

## CorAcqDeviceSetFeatureDataByName

Sets the value of a complex feature associated with a specified name.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceSetFeatureDataByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , CORHANDLE <i>dataSrc</i> );	
<b>Description</b>	Sets the value of a <i>complex type</i> feature associated with a specified name. A complex type feature is a feature that is contained in a handle. See CORFEATURE_PRM_TYPE for a list of simple and complex types. For simple type features you must use <i>CorAcqDeviceSetFeatureValueByName</i> instead.  The <i>dataSrc</i> handle must be a valid handle containing the feature data to be set.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>name</i>	Feature name. See device User's Manual for the list of supported features.
	<i>dataSrc</i>	Resource handle that contains feature data
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>Note</b>	This function is not valid for read-only handles.	
<b>See Also</b>	CorAcqDeviceSetFeatureValueByName CorAcqDeviceSetFeatureDataByIndex	

---

## CorAcqDeviceSetFeatureValueByIndex

Sets the value of a simple feature associated with a specified index.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceSetFeatureValueByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , const void * <i>value</i> , UINT32 <i>valueSize</i> );	
<b>Description</b>	Sets the value of a <i>simple type</i> feature associated with a specified index. A simple type feature is a feature that is NOT contained in a handle. See CORFEATURE_PRM_TYPE for a list of simple and complex types. For complex type features you must use <i>CorAcqDeviceSetFeatureDataByIndex</i> instead.  To determine the size of the buffer pointed to by <i>value</i> you must obtain the feature type using <i>CorAcqDeviceGetFeatureInfoByIndex</i> . Each feature type has its predetermined size.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>index</i>	Index of the feature. All indices in the range [0 ... value returned by CorAcqDeviceGetFeatureCount – 1] are valid.
	<i>value</i>	Address of a buffer that contains the feature value
	<i>valueSize</i>	Size of the buffer pointed to by <i>value</i> (in bytes)
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>Notes</b>	This function is not valid for read-only handles.  Except for unitless features, each feature has its specific native unit, for example millisecond, KHz, tenth of degree, and so forth. This information is obtained through the CORFEATURE_PRM_SI_UNIT and CORFEATURE_PRM_SI_TO_NATIVE_EXP10 parameters.	
<b>See Also</b>	CorAcqDeviceGetFeatureCount CorAcqDeviceSetFeatureValueByName CorAcqDeviceSetFeatureDataByIndex	

---

## CorAcqDeviceSetFeatureValueByName

Sets the value of a simple feature associated with a specified name.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceSetFeatureValueByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , const void * <i>value</i> , UINT32 <i>valueSize</i> );								
<b>Description</b>	<p>Sets the value of a <i>simple type</i> feature associated with a specified name. A simple type feature is a feature that is NOT contained in a handle. See CORFEATURE_PRM_TYPE for a list of simple and complex types. For complex type features you must use <i>CorAcqDeviceSetFeatureDataByName</i> instead.</p> <p>To determine the size of the buffer pointed to by <i>value</i> you must obtain the feature type using <i>CorAcqDeviceGetFeatureInfoByName</i>. Each feature type has its predetermined size.</p>								
<b>Input</b>	<table><tr><td><i>acqDevice</i></td><td>Acquisition resource handle</td></tr><tr><td><i>name</i></td><td>Feature name. See device User's Manual for the list of supported features.</td></tr><tr><td><i>value</i></td><td>Address of a buffer that contains the feature value</td></tr><tr><td><i>valueSize</i></td><td>Size of the buffer pointed to by <i>value</i> (in bytes)</td></tr></table>	<i>acqDevice</i>	Acquisition resource handle	<i>name</i>	Feature name. See device User's Manual for the list of supported features.	<i>value</i>	Address of a buffer that contains the feature value	<i>valueSize</i>	Size of the buffer pointed to by <i>value</i> (in bytes)
<i>acqDevice</i>	Acquisition resource handle								
<i>name</i>	Feature name. See device User's Manual for the list of supported features.								
<i>value</i>	Address of a buffer that contains the feature value								
<i>valueSize</i>	Size of the buffer pointed to by <i>value</i> (in bytes)								
<b>Output</b>	None								
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.								
<b>Note</b>	<p>This function is not valid for read-only handles.</p> <p>Except for unitless features, each feature has its specific native unit, for example millisecond, KHz, tenth of degree, and so forth. This information is obtained through the CORFEATURE_PRM_SI_UNIT and CORFEATURE_PRM_SI_TO_NATIVE_EXP10 parameters.</p>								
<b>See Also</b>	CorAcqDeviceSetFeatureValueByIndex, CorAcqDeviceSetFeatureDataByName								

---

## CorAcqDeviceUpdateFeaturesFromDevice

Gets all the features from the acquisition device at once.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceUpdateFeaturesFromDevice</b> (CORACQDEVICE <i>acqDevice</i> );		
<b>Description</b>			
<b>Input</b>	<table><tr><td><i>acqDevice</i></td><td>Acquisition resource handle</td></tr></table>	<i>acqDevice</i>	Acquisition resource handle
<i>acqDevice</i>	Acquisition resource handle		
<b>Output</b>	None		
<b>Return Value</b>	Gets all the features from the acquisition device at once. This function must be used when the <i>feature update mode</i> is set to manual (See CORACQDEVICE_PRM_FEATURE_UPDATE_MODE). In this mode writing individual features is done to an internal cache. Calling this function resets the internal cache to the values currently present in the device. This is useful when a certain number of features have been set to the internal cache but you want to undo those settings.		
<b>Note</b>	This function is not valid for read-only handles.		
<b>See Also</b>	CorAcqDeviceUpdateFeaturesToDevice, CORACQDEVICE_PRM_UPDATE_FEATURE_MODE		

---

## CorAcqDeviceUpdateFeaturesToDevice

Sets all the features to the acquisition device at once.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceUpdateFeaturesToDevice</b> (CORACQDEVICE <i>acqDevice</i> );
<b>Description</b>	Sets all the features to the acquisition device at once. This function must be used when the <i>feature update mode</i> is set to manual (See CORACQDEVICE_PRM_FEATURE_UPDATE_MODE). In this mode writing individual features is done to an internal cache. After all the required features have been set, call this function to write them all to the device.
<b>Input</b>	<i>acqDevice</i> Acquisition resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>Note</b>	This function is not valid for read-only handles.
<b>See Also</b>	CorAcqDeviceUpdateFeaturesFromDevice, CORACQDEVICE_PRM_UPDATE_FEATURE_MODE



## Event Management Functions

The event management functions are used to enumerate the list of events supported by the device and register user callback functions on those events.

---

### CorAcqDeviceGetEventCount

Returns the number of events supported by the acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetEventCount</b> (CORACQDEVICE <i>acqDevice</i> , PUINT32 <i>count</i> );	
<b>Description</b>	Returns the number of events supported by the acquisition device. Devices do not necessarily support the same event set. For instance you can use this function to retrieve the number of events and then get the name of those event using CorAcqDeviceGetEventNameByIndex, using an event index which can be any value in the range [0... <i>count</i> -1].	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
<b>Output</b>	<i>count</i>	Number of events
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	

---

### CorAcqDeviceGetEventIndexByName

Returns the index of an event associated with a specified name.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetEventIndexByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , PUINT32 <i>index</i> );	
<b>Description</b>	Returns the index of an event associated with a specified name.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>name</i>	Event name. See device User's Manual for the list of supported events.
<b>Output</b>	<i>index</i>	Index of the event associated with the specified name
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceGetEventIndexByName	

---

### CorAcqDeviceGetEventNameByIndex

Returns the name of an event associated with a specified index.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetEventNameByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , PSTR <i>name</i> , UINT32 <i>nameSize</i> );	
<b>Description</b>	Returns the name of an event associated with a specified index. The typical usage is converting an event index (retrieved from your callback information) to the corresponding name. You can then sort the events by name in order to call the appropriate event handling code.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>index</i>	Index of the event. All indices in the range [0 ... value returned by CorAcqDeviceGetEventCount – 1] are valid.
	<i>nameSize</i>	Size (in bytes) of the buffer pointed to by <i>name</i>
<b>Output</b>	<i>name</i>	Name of the event associated with the specified index
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceGetEventIndexByName and CorAcqDeviceGetEventCount	

---

## CorAcqDeviceIsEventAvailable

Returns whether or not an event is supported by the acquisition device.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceIsEventAvailable</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , PUINT32 <i>isAvailable</i> );	
<b>Description</b>	Returns whether or not an event is supported by the acquisition device. This function is useful when an application supports several acquisition devices each having a different event set.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>name</i>	Event name. See device User's Manual for the list of supported events.
<b>Output</b>	<i>isAvailable</i>	TRUE if the event is supported by the device. FALSE otherwise
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	

---

## CorAcqDeviceIsCallbackRegisteredByIndex

Returns whether or not a callback function was registered on the event associated with a specified index.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceIsCallbackRegisteredByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , PUINT32 <i>isRegistered</i> );	
<b>Description</b>	Returns whether or not a callback function was registered on the event associated with a specified index. For example use this function in a loop to determine if the callback function associated with the current index has to be unregistered.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>index</i>	Index of the event. All indices in the range [0 ... value returned by CorAcqDeviceGetEventCount – 1] are valid.
<b>Output</b>	<i>isRegistered</i>	TRUE if a callback function was registered on this event. FALSE otherwise
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceIsCallbackRegisteredByName and CorAcqDeviceGetEventCount	

---

## CorAcqDeviceIsCallbackRegisteredByName

Returns whether or not a callback function was registered on the event associated with a specified name.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceIsCallbackRegisteredByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> , PUINT32 <i>isRegistered</i> );	
<b>Description</b>	Returns whether or not a callback function was registered on the event associated with a specified name.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>name</i>	Event name. See device User's Manual for the list of supported events.
<b>Output</b>	<i>isRegistered</i>	TRUE if a callback function was registered on this event. FALSE otherwise
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorAcqDeviceIsCallbackRegisteredByIndex	

---

## CorAcqDeviceRegisterCallbackByIndex

Registers a callback function on the event associated with a specified index.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceRegisterCallbackByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , PCOREVENTINFOCALLBACK <i>callback</i> , void * <i>context</i> );	
<b>Description</b>	Registers an event by associating a callback function to the specified index. When the event occurs in the acquisition device the specified callback function is called. The callback function provides information on the corresponding event (in the <i>COREVENTINFO</i> handle). Refer to the <i>EventInfo</i> module for more detail on the available information. The context pointer is also returned by the callback function allowing you to exchange user information between the callback and your application context.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>index</i>	Index of the event. All indices in the range [0 ... value returned by CorAcqDeviceGetEventCount – 1] are valid.
	<i>callback</i>	Address of a user callback function of the following form:  <pre>CORSTATUS CCONV MyCallback(void *context, COREVENTINFO hEventInfo) { }</pre>
	<i>context</i>	Pointer to a user storage (that is, variable, structure, buffer, etc). Can be NULL.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>Note</b>	This function is not valid for read-only handles.	
<b>See Also</b>	CorAcqDeviceRegisterCallbackByName, EventInfo Module, and CorAcqDeviceGetEventCount	

---

## CorAcqDeviceRegisterCallbackByName

Registers a callback function on the event associated with a specified name.

**Prototype**      `CORSTATUS CorAcqDeviceRegisterCallbackByName(CORACQDEVICE acqDevice, PCSTR name, PCOREVENTINFOCALLBACK callback, void *context);`

**Description**      Registers an event by associating a callback function to the specified name. When the event occurs in the acquisition device the specified callback function is called. The callback function provides information on the corresponding event (in the *COREVENTINFO* handle). Refer to the *EventInfo* module for more detail on the available information. The context pointer is also returned by the callback function allowing you to exchange user information between the callback and your application context.

**Input**              *acqDevice*      Acquisition resource handle  
                      *name*              Event name. See device User's Manual for the list of supported events.  
                      *callback*        Address of a user callback function of the following form:

```

CORSTATUS CCONV MyCallback(void *context, COREVENTINFO hEventInfo)
{
}

```

*context*        Pointer to a user storage (that is, variable, structure, buffer, etc). Can be NULL.

**Output**              None

**Return Value**      `CORSTATUS_OK` if successful.  
For information on handling other `CORSTATUS` return values see the "Error Management" section.

**Note**                This function is not valid for read-only handles.

**See Also**           `CorAcqDeviceRegisterCallbackByIndex`, `EventInfo` Module

### Example

```

CORSTATUS CCONV MyCallback(void *context, COREVENTINFO hEventInfo)
{
    // Retrieve "AcqDevice" handle through context pointer
    // Context could be anything else
    CORACQDEVICE hAcqDevice = (CORACQDEVICE) context;

    // Access information using CorEventInfo...functions
    // ...
}

main()
{
    // ...
    CorAcqDeviceRegisterCallbackByName(hAcqDevice,
    "FeatureValueChanged", MyCallback, hAcqDevice);
    // ...
    CorAcqDeviceUnregisterCallbackByName(hAcqDevice,
    "FeatureValueChanged");
    // ...
}

```

---

## CorAcqDeviceUnregisterCallbackByIndex

Unregisters a callback function on the event associated with a specified index.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceUnregisterCallbackByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> );
<b>Description</b>	Unregisters a callback function on the event associated with a specified index. Use this function in a loop to unregister all the callback functions previously registered.
<b>Input</b>	<i>acqDevice</i> Acquisition resource handle <i>index</i> Index of the event. All indices in the range [0 ... value returned by CorAcqDeviceGetEventCount – 1] are valid.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>Note</b>	This function is not valid for read-only handles.
<b>See Also</b>	CorAcqDeviceIsCallbackRegisteredByIndex, CorAcqDeviceIsCallbackRegisteredByName, CorAcqDeviceUnregisterCallbackByName, and CorAcqDeviceGetEventCount
<b>Example</b>	

```
// Unregisters all the callback functions
//
UINT32 eventCount, eventIndex;
CorAcqDeviceGetEventCount(hAcqDevice, &eventCount);
for (eventIndex = 0; eventIndex < eventCount; eventIndex++)
{
    BOOL isRegistered;
    CorAcqDeviceIsCallbackRegistered(hAcqDevice, eventIndex,
    &isRegistered);
    if (isRegistered)
    {
        CorAcqDeviceUnregisterCallbackByIndex(hAcqDevice,
        eventIndex);
    }
}
```

---

## CorAcqDeviceUnregisterCallbackByName

Unregisters a callback function on the event associated with a specified name.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceUnregisterCallbackByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>name</i> );
<b>Description</b>	Unregisters a callback function on the event associated with a specified name. Use this function to unregister a callback function for which you know the name.
<b>Input</b>	<i>acqDevice</i> Acquisition resource handle <i>name</i> Event name. See device User's Manual for the list of supported events.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>Note</b>	This function is not valid for read-only handles.
<b>See Also</b>	CorAcqDeviceUnregisterCallbackByIndex
<b>Note</b>	This function is not valid for read-only handles.
<b>See Also</b>	CorAcqDeviceIsCallbackRegisteredByIndex, CorAcqDeviceIsCallbackRegisteredByName, CorAcqDeviceUnregisterCallbackByIndex

## File Access Functions

The file access functions are used to access the files supported by the device, and read/write files from/to the device.

---

### CorAcqDeviceDeleteFileByIndex

Deletes the specified file associated with an index on the acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceDeleteFileByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>deviceFileIndex</i> );	
<b>Description</b>	Deletes the specified file associated with an index on the acquisition device.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>deviceFileIndex</i>	Index of the file
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>deviceFileIndex</i> is NULL)	

---

### CorAcqDeviceDeleteFileByName

Deletes the specified file associated with a name on the acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceDeleteFileByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>deviceFileName</i> );	
<b>Description</b>	Deletes the specified file associated with a name on the acquisition device.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>deviceFileName</i>	Name of the file
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>deviceFileName</i> is NULL)	

---

### CorAcqDeviceGetFileCount

Gets the index of the file specified by the *fileName* parameter.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFileCount</b> (CORACQDEVICE <i>acqDevice</i> , PUINT32 <i>count</i> );	
<b>Description</b>	Gets the index of the file specified by the <i>fileName</i> parameter.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
<b>Output</b>	<i>count</i>	Returns the number of files that the acquisition device holds. See the acquisition device User's Manual for the list of supported files.e.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>count</i> is NULL)	

---

## CorAcqDeviceGetFileIndexByName

Gets the index of the file specified by the *fileName* parameter

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFileIndexByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>fileName</i> , PUINT32 <i>index</i> );	
<b>Description</b>	Gets the index of the file specified by the <i>fileName</i> parameter.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>fileName</i>	Name of the file
<b>Output</b>	<i>index</i>	Index of the file
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_ARG_NULL (if <i>fileName</i> is NULL)	

---

## CorAcqDeviceGetFileNameByIndex

Gets the name of the file specified by the *index* parameter.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceGetFileNameByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>index</i> , PSTR <i>fileName</i> , UINT32 <i>nameSize</i> );	
<b>Description</b>	Gets the name of the file specified by the <i>index</i> parameter.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>index</i>	Index of the file
<b>Output</b>	<i>fileName</i>	Name of the file
	<i>nameSize</i>	Specifies the maximum length of the character string that <i>fileName</i> can contain.
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_ARG_NULL (if <i>index</i> is NULL)	

## CorAcqDeviceGetFilePropertyByIndex

Gets the value for the specified property type for the file associated with a specified index.

<b>Prototype</b>	<code>CORSTATUS CorAcqDeviceGetPropertyByIndex(CORACQDEVICE <i>acqDevice</i>, UINT32 <i>fileIndex</i>, UINT32 <i>propertyType</i>, PUINT64 <i>pPropertyValue</i>);</code>
------------------	---------------------------------------------------------------------------------------------------------------------------------------------------------------------------

<b>Description</b>	Gets the value for the specified property type for the file associated with a specified index.
--------------------	------------------------------------------------------------------------------------------------

<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
--------------	------------------	-----------------------------

<i>fileIndex</i>	Index of the file
------------------	-------------------

*propertyType* Specifies the required property. Currently supported values are:

CORACQDEVICE_FILE_PROPERTY_ACCESS_MODE	Access mode for the device file. Possible return values are:
----------------------------------------	--------------------------------------------------------------

CORACQDEVICE_FILE_PROPERTY_FILE_SIZE	Device file size, in bytes
--------------------------------------	----------------------------

**Output** *pPropertyValue* Returns the property value.

Possible values for the access mode are:

CORACQDEVICE\_VAL\_FILE\_ACCESS\_MODE\_NONE  
CORACQDEVICE\_VAL\_FILE\_ACCESS\_MODE\_READ\_ONLY  
CORACQDEVICE\_VAL\_FILE\_ACCESS\_MODE\_WRITE\_ONLY  
CORACQDEVICE\_VAL\_FILE\_ACCESS\_MODE\_READ\_WRITE

**Return Value**    CORSTATUS\_OK  
                       CORSTATUS\_INVALID\_HANDLE  
                       CORSTATUS\_ARG\_NULL (if *fileIndex* is NULL)

## CorAcqDeviceGetFilePropertyByName

Gets the value for the specified property type for the file associated with a specified name.

**Prototype**     CORSTATUS **CorAcqDeviceGetPropertyByName**(CORACQDEVICE *acqDevice*, PCSTR *fileName*, UINT32 *propertyType*, PUINT64 *pPropertyValue*);

<b>Description</b>	Gets the value for the specified property type for the file associated with a specified name.
--------------------	-----------------------------------------------------------------------------------------------

<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
--------------	------------------	-----------------------------

<i>fileName</i>	Name of the file
-----------------	------------------

*propertyType* Specifies the required property. Currently supported values are:

CORACQDEVICE_FILE_PROPERTY_ACCESS_MODE	Access mode for the device file.
----------------------------------------	----------------------------------

CORACQDEVICE_FILE_PROPERTY_FILE_SIZE	Device file size, in bytes
--------------------------------------	----------------------------

**Output** *pPropertyValue* Returns the property value.

Possible values for the access mode are:

CORACQDEVICE\_VAL\_FILE\_ACCESS\_MODE\_NONE  
CORACQDEVICE\_VAL\_FILE\_ACCESS\_MODE\_READ\_ONLY  
CORACQDEVICE\_VAL\_FILE\_ACCESS\_MODE\_WRITE\_ONLY  
CORACQDEVICE\_VAL\_FILE\_ACCESS\_MODE\_READ\_WRITE

<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>filename</i> is NULL)
---------------------	---------------------------------------------------------------------------------------------



---

## CorAcqDeviceIsFileAccessAvailable

Returns if file access is supported by the acquisition device

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceIsFileAccessAvailable</b> (CORACQDEVICE <i>acqDevice</i> , PUINT32 <i>isAvailable</i> );	
<b>Description</b>	Returns if file access is supported by the acquisition device.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
<b>Output</b>	<i>isAvailable</i>	True (1) if file access is supported by the device. False (0) otherwise
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	

---

## CorAcqDeviceReadFileByIndex

Reads the specified file associated with an index from the device and saves it in the specified location on the host computer.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceReadFileByIndex</b> (CORACQDEVICE <i>acqDevice</i> , UINT32 <i>deviceFileIndex</i> , PCSTR <i>localFileName</i> );	
<b>Description</b>	Reads the specified file associated with an index from the device and saves it in the specified location on the host computer.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>deviceFileIndex</i>	Index of the file
	<i>localFileName</i>	Full directory path and filename on the host computer to save the file..
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>deviceFileIndex</i> is NULL)	

---

## CorAcqDeviceReadFileByName

Reads the specified file associated with a name from the device and saves it in the specified location on the host computer.

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceReadFileByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>deviceFileName</i> , PCSTR <i>localFileName</i> );	
<b>Description</b>	Reads the specified file associated with a name from the device and saves it in the specified location on the host computer.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>deviceFileName</i>	Name of the file
	<i>localFileName</i>	Full directory path and filename on the host computer to save the file.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>fileIndex</i> is NULL)	

---

## CorAcqDeviceWriteFileByIndex

Writes to the specified file associated with an index on the device

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceWriteFileByIndex</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>localFileName</i> , UINT32 <i>deviceFileIndex</i> );	
<b>Description</b>	Writes to the specified file associated with an index on the device.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>localFileName</i>	Full directory path and filename on the host computer of the file to write to the device
	<i>deviceFileIndex</i>	Index of the file on the device to overwrite
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>deviceFileIndex</i> is NULL)	

---

## CorAcqDeviceWriteFileByName

Writes to the specified file associated with a name on the device

<b>Prototype</b>	CORSTATUS <b>CorAcqDeviceWriteFileByName</b> (CORACQDEVICE <i>acqDevice</i> , PCSTR <i>localFileName</i> , PCSTR <i>deviceFileName</i> );	
<b>Description</b>	Writes to the specified file associated with an index on the device.	
<b>Input</b>	<i>acqDevice</i>	Acquisition resource handle
	<i>localFileName</i>	Full directory path and filename on the host computer of the file to write to the device
	<i>deviceFileName</i>	Name of the file on the device to overwrite
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_NULL (if <i>deviceFileName</i> is NULL)	

---

## Feature Module

The *Feature* module is used to retrieve the feature information from the *AcqDevice* module. Each feature supported by the *AcqDevice* module provides a set of capabilities such as name, type, access mode, and so forth, that can be obtained through the feature module. The feature module is used by *CorAcqDeviceGetFeatureInfo...* functions.

### Feature Parameters

ID	Parameters	Type	Access
0x00	CORFEATURE_PRM_NAME	String (64 characters)	R only
0x01	CORFEATURE_PRM_TYPE	Enumeration	R only
0x02	CORFEATURE_PRM_STANDARD	Boolean	R only
0x03	CORFEATURE_PRM_ACCESS_MODE	Enumeration	R only
0x04	CORFEATURE_PRM_POLLING_TIME	32-bit Integer	R only
0x05	CORFEATURE_PRM_TOOL_TIP	String (256 characters)	R only
0x06	CORFEATURE_PRM_DISPLAY_NAME	String (64 characters)	R only
0x07	CORFEATURE_PRM_REPRESENTATION	Enumeration	R only
0x08	CORFEATURE_PRM_SIGN	Enumeration	R only
0x09	CORFEATURE_PRM_SI_UNIT	String (32 characters)	R only
0x0A	CORFEATURE_PRM_CATEGORY	String (64 characters)	R only
0x0B	CORFEATURE_PRM_WRITE_MODE	32-bit Integer	R only
0x0C	CORFEATURE_PRM_SAVED_TO_CONFIG_FILE	Boolean	RW
0x0D	CORFEATURE_PRM_SI_TO_NATIVE_EXP10	32-bit Integer	R only
0x0E	CORFEATURE_PRM_VISIBILITY	Enumeration	R only
0x0F	CORFEATURE_PRM_SELECTOR	Boolean	R only
0x10	CORFEATURE_PRM_ARRAY_LENGTH	32-bit Integer	R only
0x11	CORFEATURE_PRM_DESCRIPTION	String (512 characters)	R only
0x14	CORFEATURE_PRM_INCREMENT_TYPE	Enumeration	R only
0x15	CORFEATURE_PRM_VALID_VALUE_COUNT	32-bit Integer	R only
0x18	CORFEATURE_PRM_FLOAT_PRECISION	64-bit Integer	R only
0x19	CORFEATURE_PRM_FLOAT_NOTATION	Enumeration	R only

---

## CORFEATURE\_PRM\_ACCESS\_MODE

<b>Description</b>	Determines the type of access for a feature. See the value descriptions below.
<b>Type</b>	UINT32
<b>Values</b>	<b>CORFEATURE_VAL_ACCESS_MODE_UNDEFINED</b> Undefined access mode <b>CORFEATURE_VAL_ACCESS_MODE_RW</b> The feature can be read and written. Most of the features are of this type. <b>CORFEATURE_VAL_ACCESS_MODE_RO</b> The feature can only be read. Certain type of features such as "Sensor Temperature" and "Sensor Resolution" cannot be written. <b>CORFEATURE_VAL_ACCESS_MODE_WO</b> The feature can only be written. Some features represent commands (or actions) such as "starting a calibration algorithm" for example. This kind of feature cannot be read back. <b>CORFEATURE_VAL_ACCESS_MODE_NP</b> The feature is not present. The feature is visible in the interface but is not implemented for this device. <b>CORFEATURE_VAL_ACCESS_MODE_NE</b> The feature is present but not enabled. Often used when a feature depends on another feature's value.

---

## CORFEATURE\_PRM\_ARRAY\_LENGTH

<b>Description</b>	Represents the number of bytes required to store the value of a feature of array type, that is, when the CORFEATURE_PRM_TYPE is CORFEATURE_VAL_TYPE_ARRAY. You can then create a buffer with a height of one line, and a width corresponding to this number of bytes, and then use the buffer handle when calling the <i>CorAcqDeviceGetFeatureData...</i> / <i>CorAcqDeviceSetFeatureData...</i> functions.
<b>Type</b>	UINT32
<b>Values</b>	Positive integer

---

## CORFEATURE\_PRM\_CATEGORY

<b>Description</b>	Represents the category of features the current feature belongs to. All the features are divided into categories to simplify the presentation of features coming from a large feature set.
<b>Type</b>	String (64 characters)
<b>Values</b>	String representing the name of the category
<b>Note</b>	The categories are useful to present a categorized list of features in a graphical user interface.

---

## CORFEATURE\_PRM\_DESCRIPTION

<b>Description</b>	Text representing the full description of the feature.
<b>Type</b>	String (1024 characters)
<b>Values</b>	String representing the description
<b>Note</b>	This parameter can be used to display detailed textual information in a graphical user interface.

---

## CORFEATURE\_PRM\_DISPLAY\_NAME

<b>Description</b>	Represents the name of the feature in a more descriptive way than CORFEATURE_PRM_NAME. This name can be used for listing features in a graphical user interface.
<b>Type</b>	String (64 characters)
<b>Values</b>	String representing the display name of the feature
<b>Note</b>	This name must not be used as an index to the <i>AcqDevice</i> module functions. Use CORFEATURE_PRM_NAME instead.

---

## CORFEATURE\_PRM\_FLOAT\_NOTATION

<b>Description</b>	Gets the type of notation to use to display a float type feature.
<b>Type</b>	Enumeration
<b>Values</b>	Possible values are: <b>CORFEATURE_VAL_FLOAT_NOTATION_UNDEFINED</b> Undefined <b>CORFEATURE_VAL_FLOAT_NOTATION_FIXED</b> Display variable using fixed notation. For example, 123.4 <b>CORFEATURE_VAL_FLOAT_NOTATION_SCIENTIFIC</b> Display variable using scientific notation. For example, 1.234e-2.

---

## CORFEATURE\_PRM\_FLOAT\_PRECISION

<b>Description</b>	Gets the number of decimal places to display for a float type feature.
<b>Type</b>	UINT64
<b>Values</b>	Possible values are: <b>CORFEATURE_VAL_FLOAT_NOTATION_UNDEFINED</b> Undefined <b>CORFEATURE_VAL_FLOAT_NOTATION_FIXED</b> Display variable using fixed notation. For example, 123.4 <b>CORFEATURE_VAL_FLOAT_NOTATION_SCIENTIFIC</b> Display variable using scientific notation. For example, 1.234e-2.

---

## CORFEATURE\_PRM\_INCREMENT\_TYPE

<b>Description</b>	Determines the type of increment for an integer or floating-point feature. See the value descriptions below.
<b>Type</b>	UINT32
<b>Values</b>	Positive integer

---

## CORFEATURE\_PRM\_NAME

<b>Description</b>	Represents the name of the feature. The name of a feature can be used as an index to the feature set in the <i>AcqDevice</i> module.
<b>Type</b>	String (64 characters)
<b>Values</b>	String representing the name of the feature
<b>Note</b>	This string should not be used for display in a graphical user interface. Instead the CORFEATURE_PRM_DISPLAY_NAME provides a more descriptive name.

---

## CORFEATURE\_PRM\_POLLING\_TIME

<b>Description</b>	Interval of time between two consecutive feature updates. Some read-only features such as “Sensor Temperature” for instance must be read from the device at a certain frequency in order to refresh to feature module. You can modify this value to either increase or decrease the refresh rate.
<b>Type</b>	UINT32
<b>Values</b>	Positive integer

---

## CORFEATURE\_PRM\_REPRESENTATION

<b>Description</b>	Determines the mathematical representation of a integer or float feature. See possible options below.
<b>Type</b>	UINT32
<b>Values</b>	<b>CORFEATURE_VAL_REPRESENTATION_UNDEFINED</b> Undefined representation <b>CORFEATURE_VAL_REPRESENTATION_LINEAR</b> The feature follows a linear scale <b>CORFEATURE_VAL_REPRESENTATION_LOGARITHMIC</b> The feature follows a logarithmic scale <b>CORFEATURE_VAL_REPRESENTATION_BOOLEAN</b> The feature is a boolean (can have two values: zero or non-zero)

---

## CORFEATURE\_PRM\_SAVED\_TO\_CONFIG\_FILE

<b>Description</b>	Specifies whether or not a feature is saved to the configuration file when calling <i>CorAcqDeviceSaveFeatures</i> . All the features are assigned a default behavior. For example the read-only features are not saved while the read-write features are. You can however change the default behavior using this parameter. For example a read-only feature such as “Sensor Temperature” is not saved by default. You set this parameter to TRUE to force the feature to be written to the configuration file.
<b>Type</b>	Boolean
<b>Values</b>	TRUE for allowing the feature to be saved, FALSE otherwise.
<b>Note</b>	If you force read-only features to be saved those features will not be restored when loading back the CCF file. The reason is that the features are not writable to the device.

---

## CORFEATURE\_PRM\_SELECTOR

<b>Description</b>	Determines if the value of the current feature directly affects the values of other features, using a one to many parent-child relationship. For example, if the current feature represents a look-up table index, then the affected features could represent values associated with one specific look-up table.  In this case, the current feature is called the selector.  Use the following functions to find out which features are selected: <i>CorFeatureGetSelectedCount</i> , <i>CorFeatureGetSelectedIndex</i> , and <i>CorFeatureGetSelectedName</i> .
<b>Type</b>	Boolean
<b>Values</b>	TRUE if the feature is a selector, FALSE otherwise.

---

## CORFEATURE\_PRM\_SIGN

<b>Description</b>	Determines the sign of the integer or float feature. This information is useful when reading and writing feature values. By knowing the sign of the feature value you can “type cast” it to the corresponding C/C++ type.
<b>Type</b>	UINT32
<b>Values</b>	<b>CORFEATURE_VAL_SIGN_UNDEFINED</b> Sign is undefined <b>CORFEATURE_VAL_SIGN_SIGNED</b> The feature is a signed integer or float <b>CORFEATURE_VAL_SIGN_UNSIGNED</b> The feature is an unsigned integer or float

---

## CORFEATURE\_PRM\_SI\_TO\_NATIVE\_EXP10

<b>Description</b>	Used to convert the value of a feature from SI unit (international system) to native unit (the unit used to read/write the feature through the API). The following equation describes the relation between the two unit systems: $V_{NATIVE} = V_{SI} * 10^E$ Where $V$ is the value of a feature and $E$ is the current parameter.
<b>Type</b>	32-bit integer
<b>Values</b>	The value is the exponent of a base 10. It can be negative or positive.
<b>Example 1</b>	You want to set the camera integration time to a known value in seconds. The “IntegrationDuration” feature is represented in microseconds. Therefore the current parameter value is 6. For instance if the desired integration time is 0.5 second you can compute the value to pass to <i>CorAcqDeviceSetFeatureValue...</i> as follows: $V_{NATIVE} = 0.5 * 10^6 = 500000$
<b>Example 2</b>	You want to monitor the temperature of the camera sensor. The “SensorTemperature” feature is reported in tenths of celcius degree. Therefore the current parameter value is 1. For instance if the feature value returned by <i>CorAcqDeviceGetFeatureValue...</i> is 205 then you can compute the temperature in celcius as follows: $V_{SI} = \frac{V_{NATIVE}}{10^E} = \frac{205}{10^1} = 20.5$ Use the <i>CORFEATURE_SI_UNIT</i> parameter to retrieve the SI unit corresponding to the feature to monitor.

---

## CORFEATURE\_PRM\_SI\_UNIT

<b>Description</b>	Describes the physical unit representing the feature in the international system (SI). Examples of units are Volts, Pixels, Celsius Degrees, and so forth. This information is useful to present in a graphical user interface.  Most of the time the unit used by the feature (the native unit) is NOT the SI unit directly but a multiple of it, for example the exposure time may be represented in microseconds instead of seconds. To convert the feature value to the SI unit you must use the <i>CORFEATURE_PRM_SI_TO_NATIVE_EXP10</i> conversion factor.
<b>Type</b>	String (32 characters)
<b>Values</b>	String representing the unit of the feature in the international system (SI)
<b>Note</b>	Many features are unitless and therefore don't provide this information. In such a case an empty string is returned.

---

## CORFEATURE\_PRM\_STANDARD

<b>Description</b>	Determines if a feature is standard or custom. Most of the features are standard. However sometimes custom features might be provided as part of a special version of an acquisition device driver.
<b>Type</b>	Boolean
<b>Values</b>	TRUE if the feature is standard, FALSE otherwise.

---

## CORFEATURE\_PRM\_TOOL\_TIP

<b>Description</b>	Small text representing the explanation of the feature.
<b>Type</b>	String (256 characters)
<b>Values</b>	String representing the tool tip
<b>Note</b>	This parameter can be used to implement tool tips in a graphical user interface.

---

## CORFEATURE\_PRM\_TYPE

<b>Description</b>																							
<b>Type</b>	UINT32																						
<b>Values</b>	<table><tr><td><b>CORFEATURE_VAL_TYPE_UNDEFINED</b> Undefined type</td><td>Simple</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_INT32</b> 32-bit Integer</td><td>Simple</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_INT64</b> 64-bit Integer</td><td>Simple</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_FLOAT</b> 32-bit Floating-Point</td><td>Simple</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_DOUBLE</b> 64-bit Floating-Point</td><td>Simple</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_BOOL</b> Boolean</td><td>Simple</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_ENUM</b> Enumeration</td><td>Simple</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_STRING</b> ASCII character string</td><td>Simple</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_BUFFER</b> Buffer handle</td><td>Complex</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_LUT</b> LUT handle</td><td>Complex</td></tr><tr><td><b>CORFEATURE_VAL_TYPE_ARRAY</b> Buffer handle</td><td></td></tr></table>	<b>CORFEATURE_VAL_TYPE_UNDEFINED</b> Undefined type	Simple	<b>CORFEATURE_VAL_TYPE_INT32</b> 32-bit Integer	Simple	<b>CORFEATURE_VAL_TYPE_INT64</b> 64-bit Integer	Simple	<b>CORFEATURE_VAL_TYPE_FLOAT</b> 32-bit Floating-Point	Simple	<b>CORFEATURE_VAL_TYPE_DOUBLE</b> 64-bit Floating-Point	Simple	<b>CORFEATURE_VAL_TYPE_BOOL</b> Boolean	Simple	<b>CORFEATURE_VAL_TYPE_ENUM</b> Enumeration	Simple	<b>CORFEATURE_VAL_TYPE_STRING</b> ASCII character string	Simple	<b>CORFEATURE_VAL_TYPE_BUFFER</b> Buffer handle	Complex	<b>CORFEATURE_VAL_TYPE_LUT</b> LUT handle	Complex	<b>CORFEATURE_VAL_TYPE_ARRAY</b> Buffer handle	
<b>CORFEATURE_VAL_TYPE_UNDEFINED</b> Undefined type	Simple																						
<b>CORFEATURE_VAL_TYPE_INT32</b> 32-bit Integer	Simple																						
<b>CORFEATURE_VAL_TYPE_INT64</b> 64-bit Integer	Simple																						
<b>CORFEATURE_VAL_TYPE_FLOAT</b> 32-bit Floating-Point	Simple																						
<b>CORFEATURE_VAL_TYPE_DOUBLE</b> 64-bit Floating-Point	Simple																						
<b>CORFEATURE_VAL_TYPE_BOOL</b> Boolean	Simple																						
<b>CORFEATURE_VAL_TYPE_ENUM</b> Enumeration	Simple																						
<b>CORFEATURE_VAL_TYPE_STRING</b> ASCII character string	Simple																						
<b>CORFEATURE_VAL_TYPE_BUFFER</b> Buffer handle	Complex																						
<b>CORFEATURE_VAL_TYPE_LUT</b> LUT handle	Complex																						
<b>CORFEATURE_VAL_TYPE_ARRAY</b> Buffer handle																							
<b>Note</b>	<p>If the type is <i>simple</i> the feature must be read/written using the <i>CorAcqDeviceGetFeatureValue.../ CorAcqDeviceSetFeatureValue...</i> functions. If the type is <i>complex</i> the feature must be read/written using the <i>CorAcqDeviceGetFeatureData.../ CorAcqDeviceSetFeatureData...</i> functions.</p> <p>If the feature is of array type, then the handle should refer to a buffer with a height of one line, and a width corresponding to the number of bytes given by the value of the CORFEATURE_PRM_ARRAY_LENGTH parameter.</p>																						



---

## CORFEATURE\_PRM\_VALID\_VALUE\_COUNT

<b>Description</b>	Number of valid values for an integer or floating-point feature which defines them as a list, that is, the CORFEATURE_PRM_INCREMENT_TYPE parameter is CORFEATURE_VAL_INCREMENT_TYPE_LIST. In this case, use the CorFeatureGetValidValue function to enumerate these values.
<b>Type</b>	UINT32
<b>Values</b>	Positive integer

---

## CORFEATURE\_PRM\_VISIBILITY

<b>Description</b>	Determines the level of visibility assigned to a feature. This parameter is useful to classify the features in a graphical user interface in terms of user expertise.
<b>Type</b>	UINT32
<b>Values</b>	<b>CORFEATURE_VAL_VISIBILITY_UNDEFINED</b> Undefined visibility level <b>CORFEATURE_VAL_VISIBILITY_BEGINNER</b> Specifies that the feature should be made visible to any user. <b>CORFEATURE_VAL VISIBILITY EXPERT</b> Specifies that the feature should be made visible to users with a certain level of expertise. <b>CORFEATURE_VAL VISIBILITY GURU</b> Specifies that the feature should be made visible to users with a high level of expertise. <b>CORFEATURE_VAL VISIBILITY INVISIBLE</b> Specifies that the feature should not be made visible to any user. This level of visibility is normally used on obsolete or internal features.

---

## CORFEATURE\_PRM\_WRITE\_MODE

<b>Description</b>	Determines whether or not a feature can be modified when the transfer module is connected and/or acquiring. Some features like the buffer dimensions for example cannot be changed while data is being transferred to the buffer.
<b>Type</b>	UINT32
<b>Values</b>	<b>CORFEATURE_VAL_WRITE_MODE_UNDEFINED</b> Undefined write mode <b>CORFEATURE_VAL_WRITE_MODE_ALWAYS</b> The feature can always be written. <b>CORFEATURE_VAL WRITE_MODE_NOT_ACQUIRING</b> The feature can only be written when the transfer module is not acquiring. If the transfer is currently acquiring you must stop the acquisition using <i>CorXferStop</i> / <i>CorXferWait</i> before modifying the feature value. <b>CORFEATURE_VAL WRITE_MODE_NOT_CONNECTED</b> The feature can only be written when the transfer module is not connected. If the transfer is currently connected you must disconnect it using <i>CorXferDisconnect</i> before modifying the feature value.
<b>Note</b>	Use this information to prevent an application from changing certain features when the transfer module is connected and/or acquiring.

## Feature Functions

Function	Description
<b>Creation/Destruction</b>	
CorFeatureNew	Creates an empty feature object
CorFeatureFree	Destroys a feature object
<b>General Parameters</b>	
CorFeatureGetPrm	Gets a parameter value from a feature object
CorFeatureSetPrm	Sets a simple parameter value to a feature object
CorFeatureSetPrmEx	Sets a complex parameter value to a feature object
<b>Integer/Float-specific Parameters</b>	
CorFeatureGetMin	Returns the minimum acceptable value for a feature
CorFeatureGetMax	Returns the maximum acceptable value for a feature
CorFeatureGetInc	Returns the minimum acceptable increment for a feature
CorFeatureGetValidValue	Returns one of a predefined set of valid values for a feature
<b>Enumeration-specific Parameters</b>	
CorFeatureGetEnumCount	Returns the number of items in an enumeration
CorFeatureGetEnumString	Returns the enumeration string corresponding to a specified index
CorFeatureGetEnumValue	Returns the enumeration value corresponding to a specified index
CorFeatureIsEnumEnabled	Returns whether or not the enumeration item corresponding to a specified index is enabled
CorFeatureGetEnumStringFromValue	Returns the enumeration string corresponding to a specified enumeration value
CorFeatureGetEnumValueFromString	Returns the enumeration value corresponding to a specified enumeration string
<b>Selector-specific Parameters</b>	
CorFeatureGetSelectedCount	Returns the number of features associated with a selector
CorFeatureGetSelectedIndex	Returns the index of a feature associated with a selector
CorFeatureGetSelectedName	Returns the name of a feature associated with a selector
CorFeatureGetSelectingCount	Returns the number of selectors associated with a feature
CorFeatureGetSelectingIndex	Returns the index of a selector associated with a feature
CorFeatureGetSelectingName	Returns the name of a selector associated with a feature

## Creation/Destruction

---

### CorFeatureFree

Destroys a feature object.

<b>Prototype</b>	CORSTATUS <b>CorFeatureFree</b> (CORFEATURE <i>feature</i> );
<b>Description</b>	Destroys a feature object previously created using <i>CorFeatureNew</i> .
<b>Input</b>	<i>feature</i> Feature handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>See Also</b>	CorFeatureNew

---

### CorFeatureNew

Creates an empty feature object.

<b>Prototype</b>	CORSTATUS <b>CorFeatureNew</b> (CORSERVER <i>server</i> , PCORFEATURE <i>feature</i> );
<b>Description</b>	Creates an empty feature object. Upon creation the feature object is reset with null values. To fill-in a feature object call the <i>CorAcqDeviceGetFeatureInfo...</i> functions.
<b>Input</b>	<i>server</i> Handle to a server where to create the feature object. Must be the same as that of the <i>CorAcqDevice</i> object.
<b>Output</b>	<i>feature</i> Feature handle
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>See Also</b>	CorFeatureFree, CorAcqDeviceGetFeatureInfoByIndex, CorAcqDeviceGetFeatureInfoByName

## General Parameters

The general parameters are those that apply to all feature types (they are not specific to any particular type). For example the *name* of a feature is a general parameter.

---

### CorFeatureGetPrm

Gets a parameter value from a feature object.

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetPrm</b> (CORFEATURE <i>feature</i> , UINT32 <i>prm</i> , void * <i>value</i> );
<b>Description</b>	Gets a parameter (simple and complex) value from a feature object. Make certain that the data storage pointed to by <i>value</i> matches the data type of the specified parameter. See the description of each parameter to know what kind of data storage it requires.
<b>Input</b>	<i>feature</i> Feature handle <i>prm</i> Feature parameter requested
<b>Output</b>	<i>value</i> Current value of the requested parameter
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>See Also</b>	CorFeatureSetPrm, CorFeatureSetPrmEx, Feature Parameters

---

## CorFeatureSetPrm

Sets a simple parameter value to a feature object.

**Prototype**      `CORSTATUS CorFeatureSetPrm(CORFEATURE feature, UINT32 prm, UINT32 value);`

**Description**      Sets a simple feature parameter. A simple parameter is one that fits inside an UINT32. If the parameter is complex, use CorFeatureSetPrmEx. See the description of each parameter to know what kind of data storage it requires.

**Input**            *feature*      Feature handle  
                  *prm*        Feature parameter to set  
                  *value*      New value of the parameter

**Output**            None

**Return Value**    CORSTATUS\_OK if successful.  
For information on handling other CORSTATUS return values see the "Error Management" section.

**See Also**        CorFeatureGetPrm, CorFeatureSetPrmEx, Feature Parameters

---

## CorFeatureSetPrmEx

Sets a complex parameter value to a feature object.

**Prototype**      `CORSTATUS CorFeatureSetPrmEx(CORFEATURE feature, UINT32 prm, const void *value);`

**Description**      Sets a complex feature parameter. A complex parameter is greater in size than an UINT32. If the parameter size is UINT32, use either CorFeatureSetPrm or CorFeatureSetPrmEx. See the description of each parameter to know what kind of data storage it requires.

**Input**            *feature*      Feature handle  
                  *prm*        Feature parameter to set  
                  *value*      New value of the parameter

**Output**            None

**Return Value**    CORSTATUS\_OK if successful.  
For information on handling other CORSTATUS return values see the "Error Management" section.

**See Also**        CorFeatureGetPrm, CorFeatureSetPrm, Feature Parameters

## Integer/Float-specific Parameters

The following parameters are specific to integer and float feature types.

---

### CorFeatureGetInc

Returns the minimum acceptable increment for a feature.

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetInc</b> (CORFEATURE <i>feature</i> , void * <i>incVal</i> , UINT32 <i>valSize</i> );
<b>Description</b>	Returns the minimum acceptable increment for an integer or a float feature. Some features cannot vary by increments of 1. Their value must be a multiple of a certain increment. For example the buffer cropping dimensions might require to be a multiple of 4 in order to optimize the data transfer.
<b>Input</b>	<i>feature</i> Feature handle <i>valSize</i> Size of the <i>incVal</i> buffer
<b>Output</b>	<i>incVal</i> Address of the buffer to store the increment value
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>See Also</b>	CorFeatureGetMin, CorFeatureGetMax

---

### CorFeatureGetMax

Returns the maximum acceptable value for a feature.

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetMax</b> (CORFEATURE <i>feature</i> , void * <i>maxVal</i> , UINT32 <i>valSize</i> );
<b>Description</b>	Returns the maximum acceptable value for a feature. For integer and float types <i>maxVal</i> must point to a variable of the same type as the feature. For a string type the maximum length of the string (excluding the trailing null character) is returned and <i>maxVal</i> must point to a UINT32 variable.
<b>Input</b>	<i>feature</i> Feature handle <i>valSize</i> Size of the <i>maxVal</i> buffer
<b>Output</b>	<i>maxVal</i> Address of the buffer to store the maximum value
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>See Also</b>	CorFeatureGetMin, CorFeatureGetInc

---

### CorFeatureGetMin

Returns the minimum acceptable value for a feature.

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetMin</b> (CORFEATURE <i>feature</i> , void * <i>minVal</i> , UINT32 <i>valSize</i> );
<b>Description</b>	Returns the minimum acceptable value for a feature. For integer and float types <i>minVal</i> must point to a variable of the same type as the feature. For a string type the minimum length of the string (excluding the trailing null character) is returned and <i>minVal</i> must point to a UINT32 variable.
<b>Input</b>	<i>feature</i> Feature handle <i>valSize</i> Size of the <i>minVal</i> buffer
<b>Output</b>	<i>minVal</i> Address of the buffer to store the minimum value
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>See Also</b>	CorFeatureGetMax, CorFeatureGetIncc

---

## CorFeatureGetValidValue

Returns one of a predefined set of valid values for a feature.

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetValidValue</b> (CORFEATURE <i>feature</i> , UINT32 <i>valueIndex</i> , void * <i>val</i> , UINT32 <i>valSize</i> );	
<b>Description</b>	Returns one of a predefined set of valid values for an integer or floating-point feature which defines them as a list, that is, the CORFEATURE_PRM_INCREMENT_TYPE parameter is CORFEATURE_VAL_INCREMENT_TYPE_LIST.  The <i>valueIndex</i> argument can be any value from 0 to the value of the CORFEATURE_PRM_VALID_VALUE_COUNT parameter, minus 1. The <i>val</i> argument must point to a variable of the same type as the feature.	
<b>Input</b>	<i>feature</i>	Feature handle
	<i>valueIndex</i>	Index of the valid value
	<i>valSize</i>	Size of the <i>val</i> buffer
<b>Output</b>	<i>val</i>	Address of the buffer to store the valid value
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CORFEATURE_PRM_INCREMENT_TYPE, CORFEATURE_PRM_VALID_VALUE_COUNT	

## Enumeration-specific Parameters

The following parameters are specific to the enumeration feature type.

---

## CorFeatureGetEnumCount

Returns the number of items in an enumeration.

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetEnumCount</b> (CORFEATURE <i>feature</i> , PUINT32 <i>count</i> );	
<b>Description</b>	Returns the number of items in an enumeration. Use this function along with <i>CorFeatureGetEnumString</i> and <i>CorFeatureGetEnumValue</i> to enumerate all the items contained within an enumeration feature.	
<b>Input</b>	<i>feature</i>	Feature handle
<b>Output</b>	<i>count</i>	Number of items in the enumeration
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorFeatureGetEnumString, CorFeatureGetEnumValue	

---

## CorFeatureGetEnumString

Returns the enumeration string corresponding to a specified index.

**Prototype**      `CORSTATUS CorFeatureGetEnumString(CORFEATURE feature, UINT32 index, PSTR enumString, UINT32 stringSize);`

**Description**      Returns the enumeration string corresponding to a specified index. Use this function along with *CorFeatureGetEnumCount* and *CorFeatureGetEnumValue* to enumerate all the items contained within an enumeration feature.

**Input**            *feature*      Feature handle  
*index*          Index of the enumeration item. Ranges from 0 to *CorFeatureGetEnumCount* - 1  
*stringSize*      Size of the *enumString* buffer (in bytes)

**Output**           *enumString*   String associated with the item specified by *index*

**Return Value**    CORSTATUS\_OK if successful.  
For information on handling other CORSTATUS return values see the "Error Management" section.

**See Also**        *CorFeatureGetEnumCount*

---

## CorFeatureGetEnumStringFromValue

Returns the enumeration string corresponding to a specified enumeration value.

**Prototype**      `CORSTATUS CorFeatureGetEnumStringFromValue(CORFEATURE feature, UINT32 value, PSTR enumString, UINT32 stringSize);`

**Description**      Returns the enumeration string corresponding to a specified enumeration value. For example you may use this function to retrieve the string corresponding to an enumeration value returned by the *CorAcqDeviceGetFeatureValue...* functions.

**Input**            *feature*      Feature handle  
*value*          Value to look for in the enumeration items  
*stringSize*      Size of the *enumString* buffer (in bytes)

**Output**           *enumString*   String associated with the specified value

**Return Value**    CORSTATUS\_OK if successful.  
For information on handling other CORSTATUS return values see the "Error Management" section.

**See Also**        *CorFeatureGetEnumValueFromString*

---

## CorFeatureGetEnumValue

Returns the enumeration value corresponding to a specified index.

**Prototype**      `CORSTATUS CorFeatureGetEnumValue(CORFEATURE feature, UINT32 index, PUINT32 value);`

**Description**      Returns the enumeration value corresponding to a specified index. Use this function along with *CorFeatureGetEnumCount* and *CorFeatureGetEnumString* to enumerate all the items contained within an enumeration feature.

**Input**            *feature*      Feature handle  
*index*          Index of the enumeration item. Ranges from 0 to *CorFeatureGetEnumCount* - 1  
*value*          Value associated with the item specified by *index*

**Return Value**    CORSTATUS\_OK if successful.  
For information on handling other CORSTATUS return values see the "Error Management" section.

**See Also**        *CorFeatureGetEnumCount*

---

## CorFeatureGetEnumValueFromString

Returns the enumeration value corresponding to a specified enumeration string.

**Prototype**      `CORSTATUS CorFeatureGetEnumValueFromString(CORFEATURE feature, PCSTR enumString, PUINT32 value);`

**Description**      Returns the enumeration value corresponding to a specified enumeration string. For example you may use this function to retrieve the value corresponding to a known enumeration string and then set this value to the device using the *CorAcqDeviceSetFeatureValue...* functions.

**Input**              *feature*              Feature handle  
*enumString*      String to look for in the enumeration items

**Output**            *value*              Value associated with the specified string

**Return Value**    `CORSTATUS_OK` if successful.  
For information on handling other `CORSTATUS` return values see the "Error Management" section.

**See Also**          `CorFeatureGetEnumStringFromValue`

---

## CorFeatureIsEnumEnabled

Returns whether or not the enumeration item corresponding to a specified index is enabled.

**Prototype**      `CORSTATUS CorFeatureIsEnumEnabled(CORFEATURE feature, UINT32 index, PUINT32 enabled);`

**Description**      Returns whether or not the enumeration item corresponding to a specified index is enabled. Each item in an enumeration is present for all the application duration. However an enumeration item may be dynamically enabled/disabled according to the value of another feature. Use this function to determine the enable state of an item at a given time.

**Input**              *feature*              Feature handle  
*index*              Index of the enumeration item. Ranges from 0 to *CorFeatureGetEnumCount* - 1

**Output**            *enabled*            TRUE if the item is enabled, FALSE otherwise.

**Return Value**    `CORSTATUS_OK` if successful.  
For information on handling other `CORSTATUS` return values see the "Error Management" section.



## Selector-specific Parameters

The following functions are specific to selectors

---

### CorFeatureGetSelectedCount

Returns the number of features associated with a selector.

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetSelectedCount</b> (CORFEATURE <i>feature</i> , PUINT32 <i>count</i> );
<b>Description</b>	Returns the number of features associated with a selector (value of CORFEATURE_PRM_SELECTOR is TRUE). These selected features can be considered as children of the current CORFEATURE object.
<b>Input</b>	<i>feature</i> Feature handle
<b>Output</b>	<i>count</i> Number of features associated with the selector, 0 if the current feature is not a selector.
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>See Also</b>	CorFeatureGetSelectedIndex, CorFeatureGetSelectedName

---

### CorFeatureGetSelectedIndex

Returns the index of a feature associated with a selector.

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetSelectedIndex</b> (CORFEATURE <i>feature</i> , UINT32 <i>selectedIndex</i> , PUINT32 <i>featureIndex</i> );
<b>Description</b>	Returns the acquisition device index of a feature associated with a selector (value of CORFEATURE_PRM_SELECTOR is TRUE). This feature can be considered a child of the current CORFEATURE object.  The number of features associated with the selector is returned by CorFeatureGetSelectedCount.  The returned index can be used by CorAcqDeviceGetFeatureInfoByIndex to access the specified CORFEATURE object. The number of features supported by the acquisition device is returned by the CorAcqDeviceGetFeatureCount.
<b>Input</b>	<i>feature</i> Feature handle <i>selectedIndex</i> Index of the selected feature, relative to the selector, from 0 to the value returned by CorFeatureGetSelectedCount, minus 1.
<b>Output</b>	<i>featureIndex</i> Index of the selected feature, relative to the acquisition device, from 0 to the value returned by CorAcqDeviceGetFeatureCount, minus 1.
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.
<b>See Also</b>	CorFeatureGetSelectedCount

---

## CorFeatureGetSelectedName

Returns the name of a feature associated with a selector.

**Prototype**      `CORSTATUS CorFeatureGetSelectedName(CORFEATURE feature, UINT32 selectedIndex, PSTR featureName, UINT32 nameSize);`

**Description**      Returns the acquisition device name of a feature associated with a selector (value of CORFEATURE\_PRM\_SELECTOR is TRUE). This feature can be considered a child of the current CORFEATURE object.

The number of features associated with the selector is returned by CorFeatureGetSelectedCount.

The feature name can be used by CorAcqDeviceGetFeatureInfoByName to access the specified CORFEATURE object. The number of features supported by the acquisition device is returned by CorAcqDeviceGetFeatureCount.

**Input**              *feature*              Feature handle

*selectedIndex*      Index of the selected feature, relative to the selector, from 0 to the value returned by CorFeatureGetSelectedCount, minus 1.

**Output**              *featureName*      Acquisition device feature name.

*nameSize*      Size (in bytes) of the buffer pointed to by *featureName*.

**Return Value**      CORSTATUS\_OK if successful.

For information on handling other CORSTATUS return values see the "Error Management" section.

**See Also**              CorFeatureGetSelectedCount

---

## CorFeatureGetSelectingCount

Returns the number of selectors associated with a feature.

**Prototype**      `CORSTATUS CorFeatureGetSelectingCount(CORFEATURE feature, PUINT32 count);`

**Description**      Returns the number of selectors (value of CORFEATURE\_PRM\_SELECTOR is TRUE) associated with a feature. These selectors can be considered as parents of the current CORFEATURE object.

**Input**              *feature*      Feature handle

**Output**              *count*      Number of selectors associated with the current feature, 0 if there are no associated selectors.

**Return Value**      CORSTATUS\_OK if successful.

For information on handling other CORSTATUS return values see the "Error Management" section.

**See Also**              CorFeatureGetSelectingIndex, CorFeatureGetSelectingName

---

## CorFeatureGetSelectingIndex

Returns the index of a selector associated with a feature.

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetSelectingIndex</b> (CORFEATURE <i>feature</i> , UINT32 <i>selectingIndex</i> , PUINT32 <i>featureIndex</i> );	
<b>Description</b>	<p>Returns the acquisition device index of a selector (value of CORFEATURE_PRM_SELECTOR is TRUE) associated with a feature. This feature can be considered a parent of the current CORFEATURE object.</p> <p>The number of selectors associated with a feature is returned by CorFeatureGetSelectingCount.</p> <p>The returned index can be used by CorAcqDeviceGetFeatureInfoByIndex to access the specified CORFEATURE object. The number of features supported by the acquisition device is returned by the CorAcqDeviceGetFeatureCount.</p>	
<b>Input</b>	<i>feature</i>	Feature handle
	<i>selectingIndex</i>	Index of the selector, relative to the current feature, from 0 to the value returned by CorFeatureGetSelectingCount, minus 1.
<b>Output</b>	<i>featureIndex</i>	Index of the selector, relative to the acquisition device, from 0 to the value returned by CorAcqDeviceGetFeatureCount, minus 1.
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorFeatureGetSelectingCount	

---

## CorFeatureGetSelectingName

Returns the name of a selector associated with a feature

<b>Prototype</b>	CORSTATUS <b>CorFeatureGetSelectingName</b> (CORFEATURE <i>feature</i> , UINT32 <i>selectingIndex</i> , PSTR <i>featureName</i> , UINT32 <i>nameSize</i> );	
<b>Description</b>	<p>Returns the acquisition device name of a selector (value of CORFEATURE_PRM_SELECTOR is TRUE) associated with a feature. This feature can be considered a parent of the current CORFEATURE object.</p> <p>The number of selectors associated with a feature is returned by CorFeatureGetSelectingCount.</p> <p>The returned name can be used by CorAcqDeviceGetFeatureInfoByName to access the specified CORFEATURE object. The number of features supported by the acquisition device is returned by CorAcqDeviceGetFeatureCount.</p>	
<b>Input</b>	<i>feature</i>	Feature handle
	<i>selectingIndex</i>	Index of the selector, relative to the current feature, from 0 to the value returned by CorFeatureGetSelectingCount, minus 1.
<b>Output</b>	<i>featureName</i>	Acquisition device feature name.
	<i>nameSize</i>	Size (in bytes) of the buffer pointed to by <i>featureName</i> .
<b>Return Value</b>	CORSTATUS_OK if successful. For information on handling other CORSTATUS return values see the "Error Management" section.	
<b>See Also</b>	CorFeatureGetSelectingCount	

---

## EventInfo Module

The *EventInfo* module is used to retrieve information from the events sent by the *AcqDevice* or the *Manager* module. Each event supported by these modules provides a set of parameters that can be accessed individually through the *EventInfo* module.

### EventInfo Parameters

ID	Parameters	Attribute
0x00	COREVENTINFO_PRM_EVENT_COUNT	Integer 32-bit
0x01	COREVENTINFO_PRM_EVENT_INDEX	Integer 32-bit
0x02	COREVENTINFO_PRM_EVENT_TYPE	Integer 32-bit
0x03	COREVENTINFO_PRM_HOST_TIME_STAMP	Integer 64-bit
0x04	COREVENTINFO_PRM_AUX_TIME_STAMP	Integer 64-bit
0x05	COREVENTINFO_PRM_GENERIC_0	Integer 32-bit
0x06	COREVENTINFO_PRM_GENERIC_1	Integer 32-bit
0x07	COREVENTINFO_PRM_GENERIC_2	Integer 32-bit
0x08	COREVENTINFO_PRM_GENERIC_3	Integer 32-bit
0x09	COREVENTINFO_PRM_CUSTOM_DATA	void pointer
0x0a	COREVENTINFO_PRM_CUSTOM_SIZE	Integer 32-bit
0x0b	COREVENTINFO_PRM_EVENT_TYPE64	Integer 64-bit

ID	Parameter Aliases	Alias of
0x05	COREVENTINFO_PRM_FEATURE_INDEX	COREVENTINFO_PRM_GENERIC_0
0x05	COREVENTINFO_PRM_SERVER_INDEX	COREVENTINFO_PRM_GENERIC_0
0x06	COREVENTINFO_PRM_FILE_PERCENT_PROGRESS	COREVENTINFO_PRM_GENERIC_1

---

#### COREVENTINFO\_PRM\_AUX\_TIME\_STAMP

<b>Description</b>	Timestamp corresponding to the moment when the event occurred on the device. Note, not all devices support this timestamp.
<b>Type</b>	UINT64
<b>Values</b>	This value is specific to the device. See the device driver User's Manual for more information on the availability of this value and the associated unit.
<b>See Also</b>	COREVENTINFO_PRM_HOST_TIME_STAMP

---

#### COREVENTINFO\_PRM\_CUSTOM\_DATA

<b>Description</b>	Address of a buffer containing data associated to a custom event. This parameter is supported only in special versions of certain device drivers.
<b>Type</b>	void pointer
<b>Note</b>	See the device driver User's Manual for a description of the supported custom events.

---

## COREVENTINFO\_PRM\_CUSTOM\_SIZE

<b>Description</b>	Size of the custom data pointed to by COREVENTINFO_PRM_CUSTOM_DATA. This parameter is supported only in special versions of certain device drivers.
<b>Type</b>	UINT32
<b>Note</b>	See the device driver User's Manual for a description of the supported custom events.

---

## COREVENTINFO\_PRM\_EVENT\_COUNT

<b>Description</b>	Number of events that have occurred since the callback function was registered.
<b>Type</b>	UINT32
<b>Values</b>	Positive integer starting at 1.
<b>Note</b>	There is one separate count per module. For example the <i>AcqDevice</i> module event counter is independent of that of the <i>Manager</i> module.

---

## COREVENTINFO\_PRM\_EVENT\_INDEX

<b>Description</b>	Index of the event contained in the EventInfo object. This parameter is used by the events sent by the <i>AcqDevice</i> module only.
<b>Type</b>	UINT32
<b>Values</b>	Ranges from 0 to <i>CorAcqDeviceGetEventCount</i> – 1
<b>See Also</b>	<i>CorAcqDeviceRegisterCallbackByName</i> , <i>CorAcqDeviceRegisterCallbackByIndex</i>

---

## COREVENTINFO\_PRM\_EVENT\_TYPE

<b>Description</b>	Type of event contained in the EventInfo object. This parameter is used by the events sent by the <i>Manager</i> module only.
<b>Type</b>	UINT32
<b>Values</b>	See the <a href="#">CorManRegisterCallbackEx</a> function for a list of available events.

---

## COREVENTINFO\_PRM\_EVENT\_TYPE64

<b>Description</b>	Type of event contained in the EventInfo object. This parameter must be used for modules that support more than 32-bit events.
<b>Type</b>	UINT64
<b>Values</b>	See the different <i>RegisterCallbackEx</i> functions for a list of available events.
<b>Note</b>	The 32-bit LSBs are the same as COREVENTINFO_PRM_EVENT_TYPE.

---

## COREVENTINFO\_PRM\_FEATURE\_INDEX

<b>Description</b>	This parameter is an alias to the COREVENTINFO_PRM_GENERIC_0 parameter. For example it is used by the " <i>FeatureInfoChanged</i> " and " <i>FeatureValueChanged</i> " events of the <i>AcqDevice</i> module. In this case it represents the index of the feature whose attributes or value have changed.
<b>Type</b>	UINT32
<b>Values</b>	Ranges from 0 to <i>CorAcqDeviceGetFeatureCount</i> – 1.

---

## COREVENTINFO\_PRM\_FILE\_PERCENT\_PROGRESS

<b>Description</b>	This parameter is an alias to the COREVENTINFO_PRM_GENERIC_1 parameter. It is used by the following events of the <i>Manager</i> module: CORMAN_VAL_EVENT_TYPE_SERVER_FILE  It represents the percentage of completion of the file upload currently in progress.
<b>Type</b>	UINT32
<b>Values</b>	Ranges from 0 to 100
<b>See Also</b>	COREVENTINFO_PRM_EVENT_TYPE

---

## COREVENTINFO\_PRM\_GENERIC\_0

<b>Description</b>	First generic parameter shared by the different events. You should use aliases instead when they are available. Otherwise refer to the device driver User's Manual for a list of events using generic parameters.
<b>Type</b>	UINT32
<b>Values</b>	Specific to the event
<b>Note</b>	For example COREVENTINFO_PRM_FEATURE_INDEX is an alias of this parameter.

---

## COREVENTINFO\_PRM\_GENERIC\_1

<b>Description</b>	Second generic parameter shared by the different events. You should use aliases instead when they are available. Otherwise refer to the device driver User's Manual for a list of events using generic parameters.
<b>Type</b>	UINT32
<b>Values</b>	Specific to the event

---

## COREVENTINFO\_PRM\_GENERIC\_2

<b>Description</b>	Third generic parameter shared by the different events. You should use aliases instead when they are available. Otherwise refer to the device driver User's Manual for a list of events using generic parameters.
<b>Type</b>	UINT32
<b>Values</b>	Specific to the event

---

## COREVENTINFO\_PRM\_GENERIC\_3

<b>Description</b>	Fourth generic parameter shared by the different events. You should use aliases instead when they are available. Otherwise refer to the device driver User's Manual for a list of events using generic parameters.
<b>Type</b>	UINT32
<b>Values</b>	Specific to the event

---

## COREVENTINFO\_PRM\_HOST\_TIME\_STAMP

<b>Description</b>	Timestamp corresponding to the moment when the event occurred on the host.
<b>Type</b>	UINT64
<b>Values</b>	Under Windows, the value corresponding to the high-resolution performance counter is directly returned
<b>Note</b>	For more detail on how to convert this value to time units, refer to <i>QueryPerformanceCounter</i> in the Windows API documentation.

---

## COREVENTINFO\_PRM\_SERVER\_INDEX

<b>Description</b>	This parameter is an alias to the COREVENTINFO_PRM_GENERIC_0 parameter. It is used by the following events of the <i>Manager</i> module: CORMAN_VAL_EVENT_TYPE_SERVER_NEW CORMAN_VAL_EVENT_TYPE_SERVER_DISCONNECTED CORMAN_VAL_EVENT_TYPE_SERVER_CONNECTED  It represents the index of the server that has been added or has changed its availability state.
<b>Type</b>	UINT32
<b>Values</b>	Ranges from 0 to <i>CorManGetServerCount</i> – 1
<b>See Also</b>	COREVENTINFO_PRM_EVENT_TYPE

## EventInfo Functions

Function	Description
CorEventInfoGetPrm	Gets a parameter value from an EventInfo object

---

### CorEventInfoGetPrm

Gets a parameter value from an EventInfo object

<b>Prototype</b>	CORSTATUS <b>CorEventInfoGetPrm</b> (COREVENTINFO <i>hEventInfo</i> , UINT32 <i>prm</i> , void* <i>pValue</i> );
<b>Description</b>	Gets a parameter (simple and complex) value from an EventInfo object. Make certain that the data storage pointed to by <i>value</i> matches the data type of the specified parameter. See the description of each parameter to know what kind of data storage it requires.
<b>Input</b>	<i>hEventInfo</i> EventInfo handle <i>prm</i> EventInfo parameter requested
<b>Output</b>	<i>value</i> Current value of the requested parameter
<b>Return Value</b>	CORSTATUS_OK
<b>See Also</b>	EventInfo Parameters

# Sapera Basic Modules

---

## Overview

The Basic Modules constitutes the core of the Sapera programming interface. This module provides everything to acquire, display, and access images. This section covers the following topics:

- **Buffer Module**  
Functions to create, read, and write memory buffers.
- **Counter Module**  
Functions to count internal or external events (not available in Sapera LT for 64-bit Windows).
- **Display Module**  
Functions to control the display device.
- **File Module**  
Functions to create, read, write, load, and save files.
- **Graphic Module**  
Functions to perform graphic operations on buffer resources.
- **I/O Module**  
Functions to control a block of general inputs and outputs.
- **LUT Module**  
Functions to define Lookup Tables that can be used by the Acquisition, Display, and Processing modules.
- **Manager Module**  
Functions that allow an application to manage available static resources.
- **PCI Device Module**  
Functions to manage the configuration space of PCI devices (not available in Sapera LT for 64-bit Windows).
- **Transfer Module**  
Functions to move data between various sources and destinations.
- **View Module**  
Functions to control a viewing window within the display device.
- **Error Messages**  
Descriptions of the Sapera error and status messages
- **Macro Definitions**  
Descriptions of the Sapera macros used to ensure code portability
- **Data Definitions**  
Descriptions of the Sapera data types used to ensure code portability
- **File Formats**  
Buffer file formats supported in the Sapera File Module.



## Sapera Function General Return Codes

The following are general return codes that may be returned upon completion of a Sapera function:

- **CORSTATUS\_OK**  
Returned upon the successful completion of a function.
- **CORSTATUS\_NO\_MESSAGING\_MEMORY**  
Returned if there is not enough contiguous messaging memory available for sending or receiving a message. See "Configuring Sapera" in the *Sapera LT User's Manual* to learn how to increase Sapera messaging memory.
- **CORSTATUS\_NOT\_IMPLEMENTED**  
Returned if the function is not implemented on the server on which the function has been executed.
- **CORSTATUS\_TIMEOUT**  
Returned if no answer has been received from the server on which the function has been executed.

The return values listed in the function descriptions are described in greater detail in the Error Messages section.

---

## Buffer Module

The Buffer module functions create, read, and write memory buffers (located on the host system or onboard) of a given size and pixel format.

### Capabilities

ID	Capability
0x00	CORBUFFER_CAP_PIXEL_DEPTH

---

#### CORBUFFER\_CAP\_PIXEL\_DEPTH

<b>Description</b>	Specifies if the CORBUFFER_PRM_PIXEL_DEPTH parameter can be modified.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, the CORBUFFER_PRM_PIXEL_DEPTH parameter can be modified. FALSE, the CORBUFFER_PRM_PIXEL_DEPTH parameter cannot be modified.
<b>See Also</b>	CORBUFFER_PRM_PIXEL_DEPTH

## Parameters

ID	Parameters	Attribute
0x00	CORBUFFER_PRM_FORMAT	Read only
0x01	CORBUFFER_PRM_TYPE	Read only
0x02	CORBUFFER_PRM_DATASIZE	Read only
0x03	CORBUFFER_PRM_DATADEPTH	Read only
0x04	CORBUFFER_PRM_XMIN	Read/Write
0x05	CORBUFFER_PRM_YMIN	Read/Write
0x06	CORBUFFER_PRM_WIDTH	Read/Write
0x07	CORBUFFER_PRM_HEIGHT	Read/Write
0x08	CORBUFFER_PRM_ADDRESS	Read only
0x09	CORBUFFER_PRM_PHYSADDRESS	Read only
0x0a	CORBUFFER_PRM_ROOT	Read only
0x0b	CORBUFFER_PRM_PARENT	Read only
0x0c	CORBUFFER_PRM_MEM_WIDTH	Read only
0x0d	CORBUFFER_PRM_MEM_HEIGHT	Read only
0x0e	CORBUFFER_PRM_STATE	Read/Write
0x0f	CORBUFFER_PRM_SIGNED	Read only
0x10	CORBUFFER_PRM_NPAGES	Read only
0x11	CORBUFFER_PRM_PAGE	Read/Write
0x12	CORBUFFER_PRM_COUNTER_STAMP	Read/Write
0x13	CORBUFFER_PRM_SPACE_USED	Read/Write
0x14	Reserved	
0x15	Reserved	
0x16	Reserved	
0x17	Reserved	
0x18	CORBUFFER_PRM_LOCKED	Read/Write
0x19	CORBUFFER_PRM_PITCH	Read only
0x1a	CORBUFFER_PRM_PIXEL_DEPTH	Read/Write
0x1b	Reserved	
0x1c	CORBUFFER_PRM_	Read only
0x1d	CORBUFFER_PRM_MULTI_INDEX	Read only
0x1e	CORBUFFER_PRM_COLOR_ALIGNMENT	Read/Write
0x1f	CORBUFFER_PRM_IS_MULTI_FORMAT	Read only
0x20	CORBUFFER_PRM_PAGE_FORMAT	Read only

### CORBUFFER\_PRM\_ADDRESS

<b>Description</b>	32-bit address of the buffer
<b>Type</b>	UINT32
<b>Note</b>	<p>This is a linear address that allows the requesting process direct access to the buffer's contents, and is only valid within this processes address space.</p> <p>The address of a buffer allocated in video memory can only be obtained if the buffer parameter CORBUFFER_PRM_LOCKED has been set to a non-zero value.</p>

---

## CORBUFFER\_PRM\_COLOR\_ALIGNMENT

<b>Description</b>	Sets the color alignment when using the buffer format CORBUFFER_VAL_FORMAT_BICOLOR88 or CORBUFFER_VAL_FORMAT_BICOLOR1616.
<b>Type</b>	UINT32
<b>Values</b>	Possible values are CORBUFFER_VAL_COLOR_ALIGN_RGBG or CORBUFFER_VAL_COLOR_ALIGN_BGRG.

---

## CORBUFFER\_PRM\_COUNTER\_STAMP

<b>Description</b>	Unique value associated with a buffer after an image has been acquired into it. This value is normally expressed in microseconds. It has no meaning by itself; however, subtracting counter stamp values for two buffers gives the amount of time elapsed between a common reference point for their respective data transfers.
<b>Type</b>	UINT32
<b>See Also</b>	The following transfer module capabilities and parameter: CORXFER_CAP_COUNTER_STAMP_AVAILABLE, CORXFER_CAP_COUNTER_STAMP_MAX, CORXFER_CAP_COUNTER_STAMP_TIME_BASE, CORXFER_CAP_COUNTER_STAMP_EVENT_TYPE, and CORXFER_PRM_COUNTER_STAMP_TIME_BASE

---

## CORBUFFER\_PRM\_DATADEPTH

<b>Description</b>	Number of bits per buffer element.
<b>Type</b>	UINT32

---

## CORBUFFER\_PRM\_DATASIZE

<b>Description</b>	Size of one buffer element (in bytes).
<b>Type</b>	UINT32
<b>Values</b>	This value does depend on the buffer format.

---

## CORBUFFER\_PRM\_FORMAT

<b>Description</b>	Buffer data format. Defines a single buffer element's type.
<b>Type</b>	UINT32
<b>Values</b>	For a detailed description of the values, see CorBufferNew.

---

## CORBUFFER\_PRM\_HEIGHT

<b>Description</b>	Height of the buffer region of interest (ROI).
<b>Type</b>	UINT32
<b>Values</b>	Range within [0...MEM_HEIGHT]. Applies only to child buffers. For information on creating child buffers, see CorBufferNewChild.

---

## CORBUFFER\_PRM\_HOST\_COUNTER\_STAMP

<b>Description</b>	Host counter timestamp at which a specific event occurred. This value is determined by the timebase of the CPU clock. Subtracting counter stamp values for two buffers gives the amount of time elapsed between a common reference point for their respective data transfers. Note, the CPU clock is common to all applications and devices on the PC. For example, if you have several Teledyne DALSA boards installed, they all refer to the same CPU clock.
<b>Type</b>	UINT64
<b>See Also</b>	See CORXFER_PRM_BUFFER_TIMESTAMP_MODULE and CORXFER_PRM_BUFFER_TIMESTAMP_EVENT to specify an event and a module for this counter.

---

## CORBUFFER\_PRM\_IS\_MULTI\_FORMAT

<b>Description</b>	Returns TRUE if a buffer is multi-format, FALSE otherwise.
<b>Type</b>	BOOL
<b>See Also</b>	CORBUFFER_PRM_FORMAT

---

## CORBUFFER\_PRM\_LOCKED

<b>Description</b>	Defines if a buffer has been locked.
<b>Type</b>	UINT32
<b>Values</b>	Boolean. A non-zero value indicates the buffer is locked.
<b>Note</b>	<p>This parameter is used only for buffers created in video memory (that is, off-screen video buffers or overlay buffers). The buffer address can only be obtained if it is locked, otherwise the address could become invalid if another application (like a screen saver, full-screen DOS prompt, or pressing CTRL-ALT-DEL) takes control of the video memory.</p> <p>Insure that the buffer is only locked when necessary. If a buffer is used for processing, lock it just before its address is obtained and then unlock it once the processing is done.</p>

---

## CORBUFFER\_PRM\_MEM\_HEIGHT

<b>Description</b>	Buffer height. Defines the number of rows in the buffer.
<b>Type</b>	UINT32

---

## CORBUFFER\_PRM\_MEM\_WIDTH

<b>Description</b>	Buffer width. Defines the number of pixels per line in the buffer.
<b>Type</b>	UINT32

---

## CORBUFFER\_PRM\_MULTI\_INDEX

<b>Description</b>	The buffer resource index, for a buffer within a multi-buffer.
<b>Type</b>	UINT32
<b>Values</b>	Ranges from 0 to the multi-buffer count -1, as specified in CorBufferMultiNew.

---

## CORBUFFER\_PRM\_NPAGES

<b>Description</b>	Defines the number of pages within the buffer.
<b>Type</b>	UINT32

---

## CORBUFFER\_PRM\_PAGE

<b>Description</b>	Defines the buffer's active page for a multi-page buffer.
<b>Type</b>	UINT32
<b>Note</b>	The current page only applies when choosing what format to display when calling CorViewShow the function.

---

## CORBUFFER\_PRM\_PAGE\_FORMAT

<b>Description</b>	<p>Returns the individual formats included in the current buffer as a UINT32 list. The list terminates upon reaching a format with a value of 0, and should contain a number of formats equals to the value of the CORBUFFER_PRM_NPAGES parameter. An array of at least 64 elements should be allocated to store the value of this parameter.</p> <p>This applies only to buffer types for which pixel data is stored in separate planes (pages), instead of being packed together. For example, 8-bit RGB planar , 8-bit HSI planar or multiformat buffer types.</p> <p>Currently supported individual formats for multi-format buffer types are:</p> <ul style="list-style-type: none"><li>CORBUFFER_VAL_FORMAT_RGB888</li><li>CORBUFFER_VAL_FORMAT_MONO8</li><li>CORBUFFER_VAL_FORMAT_RGB161616</li><li>CORBUFFER_VAL_FORMAT_MONO16</li></ul>
<b>Type</b>	UINT32 list

---

## CORBUFFER\_PRM\_PARENT

<b>Description</b>	Child buffer's parent handle.
<b>Type</b>	CORBUFFER
<b>Note</b>	Applies only to child buffers, created as described in CorBufferNewChild

---

## CORBUFFER\_PRM\_PHYSADDRESS

<b>Description</b>	Physical address of the buffer.
<b>Type</b>	UINT32
<b>Note</b>	<p>The buffer physical address can be used to allow PCI devices access to the buffer contents. This address can be mapped to a linear address (using CorManMapBuffer) by a process running on the host, so as to give the process access to the buffer's contents.</p> <p>The 32-bit address of a buffer allocated in video memory can only be obtained if the buffer's CORBUFFER_PRM_LOCKED has been set to a non-zero value.</p>

---

## CORBUFFER\_PRM\_PITCH

<b>Description</b>	Buffer's memory pitch
<b>Type</b>	UINT32
<b>Values</b>	Contains the offset (in bytes) between two pixels in the same column on two consecutive lines, within the same buffer.
<b>Note</b>	When an off-screen or overlay buffer is created, the memory region allocated may be wider than the requested width (for alignment purposes, hardware optimization, and so forth). In this case, each buffer line is padded with extra bytes to get a buffer that is CORBUFFER_PRM_PITCH bytes wide. Care should be taken not to access these extra bytes, especially if the buffer has been allocated in video memory.

---

## CORBUFFER\_PRM\_PIXEL\_DEPTH

<b>Description</b>	The buffer's number of significant bits per component. By default this value is initialized to the maximum. Refer to Data Formats section to know the maximum pixel depth value for a specific format. This maximum value may also be obtained using the <b>CorManGetPixelDepthMax</b> function.
<b>Type</b>	UINT32
<b>Values</b>	Unsigned integer ranging from <b>CorManGetPixelDepthMin</b> (format) to <b>CorManGetPixelDepthMax</b> (format), where <i>format</i> is given by CORBUFFER_PRM_FORMAT.
<b>Note</b>	An example usage of this parameter is when acquiring into a 16-bit monochrome buffer using a 10-bit camera. The CORBUFFER_PRM_PIXEL_DEPTH may be manually set to 10 in order to keep the information within the buffer. If the buffer is saved (using the File module) under the Teledyne DALSA Format (CRC), the pixel depth value is stored. When processing the buffer the pixel depth value may be used to process the significant bits only (for example, creating a LUT with the minimum required size).

---

## CORBUFFER\_PRM\_ROOT

<b>Description</b>	Root buffer's handle.
<b>Type</b>	CORBUFFER
<b>Values</b>	Contains the buffer handle on top of the hierarchy. For information on creating child buffers, see CorBufferNewChild

---

## CORBUFFER\_PRM\_SIGNED

<b>Description</b>	Sign of the buffer elements.
<b>Type</b>	UINT32
<b>Values</b>	CORBUFFER_VAL_FORMAT_UNSIGNED CORBUFFER_VAL_FORMAT_SIGNED

---

## CORBUFFER\_PRM\_SPACE\_USED

<b>Description</b>	<p>Amount of space used in the buffer by the most recent data transfer. This value is usually equal to the buffer size, which indicates that the transfer was successful. If it is equal to 0, it means that no data has been acquired yet.</p> <p>If this value is non-zero, but less than the buffer size, this can indicate some kind of data transfer error. In this case, monitoring of acquisition and transfer events can give more information about the error.</p> <p>This value can also be smaller than the buffer size when acquiring variable length data streams.</p> <p>Also note that this value can also sometimes be equal to the buffer size, even if errors occurred during acquisition. In this case, monitoring of acquisition and transfer events can help identify possible errors.</p>
<b>Type</b>	UINT32
<b>Values</b>	Unsigned integer representing the size in bytes of the last data stream transferred in the buffer.

---

## CORBUFFER\_PRM\_STATE

<b>Description</b>	<p>Buffer state. Defines if the buffer is empty or full. If the buffer state is full then the state can also indicate an overflow condition.</p> <p>This parameter may be used as a flag in an automated processing task. The EMPTY state indicates that new data can be written to the buffer while the FULL state indicates that data has not been processed. The OVERFLOW state indicates errors such as limited data bandwidth. This parameter can also be used in conjunction with the transfer module while cycling through a list of buffers.</p> <p>For more information on using this parameter, see CORXFER_PRM_CYCLE_MODE. To ensure code portability, you should use the macros CORBUFFER_STATE_IS_EMPTY (UINT32 state), CORBUFFER_STATE_IS_FULL(UINT32 state), and CORBUFFER_STATE_IS_OVERFLOW(UINT32 state) to check the buffer state.</p>
<b>Type</b>	UINT32
<b>Values</b>	<p>CORBUFFER_VAL_STATE_EMPTY Specifies that the buffer is ready to receive new data.</p> <p>CORBUFFER_VAL_STATE_FULL Specifies that the buffer contains unprocessed data.</p> <p>CORBUFFER_VAL_STATE_OVERFLOW Specifies that the buffer contains incomplete data due to insufficient data bandwidth.</p>

---

## CORBUFFER\_PRM\_TYPE

<b>Description</b>	Defines the attributes of the buffer memory.
<b>Type</b>	UINT32
<b>Values</b>	For a detailed description of possible values, see CorBufferNew.

---

## CORBUFFER\_PRM\_WIDTH

<b>Description</b>	Buffer's region of interest (ROI) width in pixels.
<b>Type</b>	UINT32
<b>Values</b>	Unsigned integer. Range within [0...MEM_WIDTH]. Applies only to child buffers. For information on creating child buffers, see CorBufferNew.

---

## CORBUFFER\_PRM\_XMIN

<b>Description</b>	Buffer's region of interest (ROI) origin along the X axis.
<b>Type</b>	UINT32
<b>Values</b>	Unsigned integer. Range within [0...MEM_WIDTH-1]. Applies only to child buffers. For information on creating child buffers, see CorBufferNew.

---

## CORBUFFER\_PRM\_YMIN

<b>Description</b>	Buffer's region of interest (ROI) origin along the Y axis.
<b>Type</b>	UINT32
<b>Values</b>	Unsigned integer. Range within [0...MEM_HEIGHT-1]. Applies only to child buffers. For information on creating child buffers, see CorBufferNew.

## Macros

This section describes macros specific to the Sapera buffer module. They should always be used in your applications to ensure code portability.

---

### **CORBUFFER\_FORMAT\_INDEX (UINT32 format)**

**Definition** Gets buffer format index

**Return Value** Unsigned integer

---

### **CORBUFFER\_FORMAT\_DATADEPTH (UINT32 format)**

**Definition** Gets buffer data depth in bits

**Return Value** Unsigned integer

---

### **CORBUFFER\_FORMAT\_DATASIZE (UINT32 format)**

**Definition** Gets buffer data size in bytes

**Return Value** Unsigned integer

---

### **CORBUFFER\_FORMAT\_IS\_SIGNED (UINT32 format)**

**Definition** Checks buffer sign

**Return Value** CORDATA\_FORMAT\_SIGNED if buffer format is signed, CORDATA\_FORMAT\_UNSIGNED otherwise

---

### **CORBUFFER\_FORMAT\_NPAGES (UINT32 format)**

**Definition** Gets the number of pages needed to represent the buffer data format.

**Return Value** Unsigned integer ranging from 1 to n

**Info** CORBUFFER\_VAL\_FORMAT\_RGBP8, CORBUFFER\_VAL\_FORMAT\_RGBP16, and CORBUFFER\_VAL\_FORMAT\_HSIP8 are currently the only multi-page buffer format supported (3 pages, one per component). All other buffer formats (monochrome and packed color) have a single page.

---

### **CORBUFFER\_STATE\_IS\_EMPTY (UINT32 state)**

**Definition** Checks if buffer state is empty

**Return Value** TRUE if buffer state is empty, FALSE otherwise

---

### **CORBUFFER\_STATE\_IS\_FULL (UINT32 state)**

**Definition** Checks if a buffer state is full

**Return Value** TRUE if buffer state is full, FALSE otherwise



## Functions

Function	Description
CorBuffer	<i>Converts a Bayer-encoded image to an RGB image</i>
CorBufferClear	<i>Clears contents of a buffer resource</i>
CorBufferClearEx	<i>Clears contents of a buffer resource</i>
CorBufferClearBlack	<i>Clears contents of a buffer resource with the value corresponding to black according to the buffer format</i>
CorBufferColorConvert	<i>Converts a Bayer-encoded image to an RGB image</i>
CorBufferColorWhiteBalance	<i>Calculates the white balance coefficients used by the Bayer filter</i>
CorBufferConvertFormat	<i>Transfers images from the source buffer to the destination buffer and performs pixel format conversion if required</i>
CorBufferCopy	<i>Copies contents of a buffer resource into another buffer resource</i>
CorBufferCopyRect	<i>Copies a rectangular area of a buffer resource into another buffer resource</i>
CorBufferFree	<i>Frees handle to a buffer resource</i>
CorBufferGetPrm	<i>Gets buffer parameter value from a buffer resource</i>
CorBufferMap	<i>Maps a buffer using physical memory into the current process virtual address space</i>
CorBufferMapEx	<i>Map a region of a buffer using physical memory into the current process virtual address space</i>
CorBufferMergeComponents	<i>Merges source buffers into the different components of a color buffer</i>
CorBufferNew	<i>Creates in a specified server's memory a new buffer resource</i>
CorBufferNew1D	<i>Creates in a specified server's memory a new 1D buffer resource</i>
CorBufferNew2D	<i>Creates in a specified server's memory a new 2D buffer resource</i>
CorBufferNewChild	<i>Creates a new buffer resource within an existing buffer resource</i>
CorBufferNew1DChild	<i>Creates a new buffer resource within an existing 1D buffer resource</i>
CorBufferNew2DChild	<i>Creates a new buffer resource within an existing 2D buffer resource</i>
CorBufferNewEx	<i>Creates from a file and in a specified server's memory a new buffer resource</i>
CorBufferNew1DEx	<i>Creates from a file and in a specified server's memory a new 1D buffer resource</i>
CorBufferNew2DEx	<i>Creates from a file and in a specified server's memory a new 2D buffer resource</i>
CorBufferNewShared	<i>Creates in a server's memory a new buffer resource of the specified type that can be shared with other processes running on this server</i>
CorBufferNewSharedEx	<i>Creates in a specified server's memory a new buffer resource that references a previously allocated shared buffer.</i>
CorBufferRead	<i>Reads a series of elements from a buffer resource</i>
CorBufferReadDots	<i>Reads a set of elements from a buffer resource</i>
CorBufferReadElement	<i>Reads an element from a buffer resource</i>
CorBufferReadElementEx	<i>Reads an element from a buffer resource</i>
CorBufferReadLine	<i>Reads a set of linearly positioned elements from a buffer resource</i>
CorBufferReadRect	<i>Reads a set of elements forming a rectangular area from a buffer resource</i>
CorBufferSetPrm	<i>Sets a simple buffer parameter of a buffer resource</i>
CorBufferSetPrmEx	<i>Sets a complex buffer parameter of a buffer resource</i>
CorBufferSplitComponents	<i>Splits a color buffer into each of its components</i>
CorBufferUnmap	<i>Unmaps the buffer physical memory from the current process virtual address space</i>
CorBufferWrite	<i>Writes a series of elements into a buffer resource</i>

CorBufferWriteDots	<i>Writes a set of elements into a buffer resource</i>
CorBufferWriteElement	<i>Writes an element into a buffer resource</i>
CorBufferWriteElementEx	<i>Writes an element into a buffer resource</i>
CorBufferWriteLine	<i>Writes a set of linearly positioned elements into a buffer resource</i>
CorBufferWriteRect	<i>Writes aset of elements forming a rectangular area into a buffer resource</i>

---

### CorBufferClear

Clear contents of a buffer resource

<b>Prototype</b>	<code>CORSTATUS <b>CorBufferClear</b>(CORBUFFER <i>hBuffer</i>, UINT32 <i>value</i>);</code>
<b>Description</b>	<p>Clears contents of a buffer resource by writing a color value to all buffer elements.</p> <p>The <i>value</i> parameter will be read as an UINT8, UINT16, or an UINT32 according to the buffer's element size. If the element size is larger than an UINT32, use CorBufferClearEx.</p> <p>For certain formats, such as UYVY and YUY2, the color corresponding to black is not 0. Therefore, make certain that the color value assigned to <i>value</i> is defined according the pixel format of the buffer. \hCorBufferClearBlack should be used when setting a buffer to a black.</p>
<b>Input</b>	<p><i>hBuffer</i>    Buffer resource handle</p> <p><i>value</i>      Color value</p>
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorBufferClearEx and CorBufferClearBlack

---

### CorBufferClearEx

Clear contents of a buffer resource

<b>Prototype</b>	<code>CORSTATUS <b>CorBufferClearEx</b>(CORBUFFER <i>hBuffer</i>, const void *<i>value</i>, UINT32 <i>size</i>);</code>
<b>Description</b>	<p>Clears contents of a buffer resource by writing a color value to all buffer elements. Required for an element size larger then UINT32.</p> <p>For an element size less than or equal to UINT32, use either CorBufferClear (suggested) or CorBufferClearEx.</p>
<b>Input</b>	<p><i>hBuffer</i>    Buffer resource handle</p> <p><i>value</i>      Color value</p> <p><i>size</i>        Element size</p>
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorBufferClear and CorBufferClearEx

---

## CorBufferClearBlack

Clear buffer resource contents with the corresponding black value as per the buffer format

**Prototype**      CORSTATUS **CorBufferClearBlack**(CORBUFFER *hBuffer*);

**Description**      Clears buffer resource contents to the corresponding black color. The color value is automatically determined according to the buffer format.  
  
For certain formats such as UYVY and YUY2, the color corresponding to black is not 0. Thus calling this function instead of CorBufferClear with a value of 0, guarantees that the buffer will appear black.

**Input**             *hBuffer*    Buffer resource handle

**Output**            None

**Return Value**    CORSTATUS\_OK  
CORSTATUS\_INVALID\_HANDLE

**See Also**         CorBufferClear and CorBufferClearEx


# CorBufferColorConvert

Converts a Bayer-encoded image to an RGB image.

**Prototype**      `CORSTATUS CorBufferColorConvert( CORBUFFER src, CORBUFFER dst, UINT32 options, CORDATA wb, CORLUT lut);`

**Description**      Converts images from the color image format to RGB format. The Bayer format assigns each pixel in a monochrome image the value of one color channel. RGB images are created by using neighbouring pixel values to get the two missing color channels at each pixel.

Pixels in a row of a Bayer image alternate between the green channel value and either the red or the blue channel value. The default scheme is shown below.



The missing color channel values are determined using neighbouring pixel values for the color channel in question either by linear interpolation (`CORBUFFER_VAL_COLOR_METHOD_1`) or by one of the advanced methods (`CORBUFFER_VAL_COLOR_METHOD_2` or `METHOD_3`). The advanced methods are more computationally expensive than the interpolation method but give better image quality when the input image contains many strong edges.

If the input image is 16-bit and the significant bits are stored in the lower bits (for example, 10-bit camera) the buffer's pixel depth (`CORBUFFER_PRM_PIXEL_DEPTH`) must be set to the number of significant bits.

The white balance coefficients (*wb*) are the R, G, and B gains applied to the input image before the filtering. These gains are used to balance the three color components so that a pure white at the input gives a pure white at the output.

The output lookup table (*lut*) may be used to apply a color correction after the filtering. A commonly used correction is gamma (*CorLutGamma* function of LUT module).

**Input**      *src*      Input buffer handle. The input buffer format must be one of the following:  
CORBUFFER\_VAL\_FORMAT\_UINT8 CORBUFFER\_VAL\_FORMAT\_UINT16

*dst*      Output buffer handle. The output buffer format can be one of the following:  
CORBUFFER\_VAL\_FORMAT\_RGB888 CORBUFFER\_VAL\_FORMAT\_RGB8888

             If the input format is CORBUFFER\_VAL\_FORMAT\_UINT16, the output buffer format can also be CORBUFFER\_VAL\_FORMAT\_RGB101010.

*options*      This value must contain one of the **alignment options** listed below. The alignment mode must correspond to the upper left 2x2 square of your camera's bayer scheme. If the input buffer is a child, the alignment mode is internally recalculated with respect to the upper left corner.

CORBUFFER\_VAL\_COLOR\_ALIGN\_GB\_RG



CORBUFFER\_VAL\_COLOR\_ALIGN\_BG\_GR



CORBUFFER\_VAL\_COLOR\_ALIGN\_RG\_GB



CORBUFFER\_VAL\_COLOR\_ALIGN\_GR\_BG



CORBUFFER\_VAL\_COLOR\_ALIGN\_RG\_BG



CORBUFFER\_VAL\_COLOR\_ALIGN\_BG\_RG



The value must be ORed with one of the **filtering options** listed below. The filtering option specifies the method used for calculating the pixel values of the three color components.

CORBUFFER\_VAL\_COLOR\_METHOD\_1

This technique, based on 3x3 bi-linear interpolation, is fast but tends to smooth image edges.

	CORBUFFER_VAL_COLOR_METHOD_2	This advanced technique is better for preserving image edges. However it works well only when the image has a strong green content. If not, a little amount of noise may be visible in objects.
	CORBUFFER_VAL_COLOR_METHOD_3	This advanced technique is almost as good as method 2 for preserving the edges but is independent of the image green content. Little color artifacts of 1 pixel may be visible in edges.
	CORBUFFER_VAL_COLOR_METHOD_4	This technique, based on 2x2 interpolation, is the simplest and fastest. Compared to 3x3 it is better at preserving edge sharpness but introduces a slight jitter in pixel position. In practice it is a good choice for image display but less recommended than 3x3 for accurate image processing.
	CORBUFFER_VAL_COLOR_METHOD_5	This technique, based on a set of linear filters, works under the main assumption that edges have much stronger luminance than chrominance component.
	CORBUFFER_VAL_COLOR_METHOD_6	Reserved.
	CORBUFFER_VAL_COLOR_METHOD_7	Support for bi-color conversion for use with the Teledyne DALSA Piranha 4 camera.
<i>wb</i>	White balance coefficients. Can be calculated by <i>CorBufferBayerWhiteBalance</i> or set manually as follows: <pre>CORDATA wb; wb.frgb.red = &lt;Red Gain&gt; wb.frgb.green = &lt;Green Gain&gt; wb.frgb.blue = &lt;Blue Gain&gt;</pre> If no white balance is required, all gains must be set to 1.0.	
<i>lut</i>	LUT handle. Color lookup table applied after the filtering for color adjustment, for example, gamma correction. The number of entries required by the LUT must be $2^N$ , where N is the buffer's pixel depth (CORBUFFER_PRM_PIXEL_DEPTH). The LUT format must be one of the following according to the output format: CORLUT_VAL_FORMAT_COLORNI8 CORLUT_VAL_FORMAT_COLORNI16 If no correction is required, can be set to CORHANDLE_NULL.	
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INCOMPATIBLE_BUFFER CORSTATUS_INCOMPATIBLE_LUT CORSTATUS_ARG_INVALID_VALUE	
<b>See Also</b>	CorBufferColorWhiteBalance, CORBUFFER_PRM_PIXEL_DEPTH, CorLutNew and CorLutGamma	

---

## CorBufferColorWhiteBalance

Calculates the white balance coefficients used by the Color filter.

**Prototype**      `CORSTATUS CorBufferColorWhiteBalance( CORBUFFER src, UINT32 options, PCORDATA pWB);`

**Description**      Calculates the white balance coefficients used by CorBufferColorConvert on a color-encoded input image. The input buffer should be a region-of-interest (ROI) of a color-encoded image containing a uniformly illuminated white region. The intensity of the pixels should be as high as possible but not saturated. The coefficients are calculated as follows:

$$G_R = \text{Max}(\overline{R}, \overline{G}, \overline{B}) / \overline{R}$$

$$G_G = \text{Max}(\overline{R}, \overline{G}, \overline{B}) / \overline{G}$$

$$G_B = \text{Max}(\overline{R}, \overline{G}, \overline{B}) / \overline{B}$$

where  $\overline{R}$ ,  $\overline{G}$  and  $\overline{B}$  are the average value of each color component calculated on all the pixels of the input image.

**Input**              *src*              Input buffer handle. The input buffer format must be one of the following:  
CORBUFFER\_VAL\_FORMAT\_UINT8 CORBUFFER\_VAL\_FORMAT\_UINT16

*options*      Used for selecting alignment. This value must contain one of the following:

CORBUFFER\_VAL\_COLOR\_ALIGN\_GB\_RG



CORBUFFER\_VAL\_COLOR\_ALIGN\_BG\_GR



CORBUFFER\_VAL\_COLOR\_ALIGN\_RG\_GB



CORBUFFER\_VAL\_COLOR\_ALIGN\_GR\_BG



CORBUFFER\_VAL\_COLOR\_ALIGN\_RG\_BG



CORBUFFER\_VAL\_COLOR\_ALIGN\_BG\_RG



**Output**              *pWB*              Address of a CORDATA structure to store the coefficients.

**Return Value**      CORSTATUS\_OK  
CORSTATUS\_INCOMPATIBLE\_BUFFER  
CORSTATUS\_ARG\_INVALID\_VALUE

**See Also**              CorBufferColorConvert and CorBufferNewChild

---

## CorBufferConvertFormat

Transfer image from source buffer to destination buffer and perform pixel format conversion if required

**Prototype**      `CORSTATUS CorBufferConvertFormat( CORBUFFER hSrc, CORBUFFER hDst, UINT32 options);`

**Description**      Transfers image from the source buffer to the destination buffer and performs required pixel format conversion.

**Input**            *hSrc*      Source buffer resource handle  
*options*      Any of the following options can be specified:  
CORBUFFER\_CONVERT\_RANGE\_CLIP  
When a source pixel value is outside the destination buffer format's range, it gets clipped to the nearest valid value. This is the default method.  
CORBUFFER\_CONVERT\_RANGE\_REMAP  
The source buffer format is mapped to the destination buffer's format. When the source and destination pixel depth are different (for example, when converting from MONO16 to MONO8) the buffer CORBUFFER\_PRM\_PIXEL\_DEPTH value is used to determine how the pixel values are remapped. This option cannot be used when the destination is floating-point.

**Output**            *hDst*      Destination buffer resource handle

**Return Value**    CORSTATUS\_OK  
CORSTATUS\_ARG\_INVALID  
CORSTATUS\_INCOMPATIBLE\_BUFFER  
CORSTATUS\_INVALID\_HANDLE  
CORSTATUS\_NOT\_IMPLEMENTED

**Note**            For multiformat buffers (for example, CORBUFFER\_VAL\_FORMAT\_RGB888\_MONO8 and CORBUFFER\_VAL\_FORMAT\_RGB161616\_MONO16) this function can be used to extract only the mono or RGB components to a MONO8/RGB888/RGB8888 or MONO16/RGB161616/RGB161616 buffer.

**See Also**        CorBufferMergeComponents and CorBufferSplitComponents

---

## CorBufferCopy

Copy contents of a buffer resource into another buffer resource

**Prototype**      `CORSTATUS CorBufferCopy(CORBUFFER hSrc, UINT32 x, UINT32 y, CORBUFFER hDst);`

**Description**      Copies the source buffer to location (*x*,*y*) of the destination buffer. When the source buffer is larger than the destination buffer, only the section of the source that fits into the destination is copied. Buffers do not have to be located on the same server.

**Input**            *hSrc*      Buffer resource handle (source)  
*x*            Horizontal offset in destination buffer  
*y*            Vertical offset in destination buffer  
*hDst*        Buffer resource handle (destination)

**Output**            None

**Return Value**    CORSTATUS\_OK  
CORSTATUS\_ARG\_INVALID  
CORSTATUS\_ARG\_OUT\_OF\_RANGE  
CORSTATUS\_INVALID\_HANDLE

**See Also**        CorBufferCopyRect

---

## CorBufferCopyRect

Copy a rectangular area of a buffer resource into another buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferCopyRect</b> (CORBUFFER <i>hSrc</i> , UINT32 <i>xSrc</i> , UINT32 <i>ySrc</i> , UINT32 <i>width</i> , UINT32 <i>height</i> , CORBUFFER <i>hDst</i> , UINT32 <i>xDst</i> , UINT32 <i>yDst</i> );	
<b>Description</b>	Copies a rectangular area of the source buffer, defined by ( <i>xSrc</i> , <i>ySrc</i> , <i>width</i> , <i>height</i> ), to the location ( <i>xDst</i> , <i>yDst</i> ) in the destination buffer. When the source area is larger than the destination buffer, only the section of the source that fits the destination is copied. Buffers do not have to be located on the same server.	
<b>Input</b>	<i>hSrc</i>	Source buffer resource handle
	<i>xSrc</i>	Horizontal offset of rectangle in source buffer
	<i>ySrc</i>	Vertical offset of rectangle in source buffer
	<i>width</i>	Horizontal length of the rectangle
	<i>height</i>	Vertical length of the rectangle
	<i>hDst</i>	Destination buffer resource handle
	<i>xDst</i>	Horizontal offset in destination buffer
<b>Output</b>	<i>yDst</i>	Vertical offset in destination buffer
	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE	
<b>Note</b>	For 1-bit data buffers, <i>xSrc</i> , <i>xDst</i> and <i>width</i> must be a multiple of 8.	
<b>See Also</b>	CorBufferCopy	

---

## CorBufferFree

Free the handle to a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferFree</b> (CORBUFFER <i>hBuffer</i> );	
<b>Description</b>	Free the handle and all resources used by a buffer resource. Any child buffers <b>MUST</b> be freed before calling CorBufferFree for the parent buffer.	
<b>Input</b>	<i>hBufer</i>	Buffer resource handle
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_RESOURCE_LINKED	
<b>See Also</b>	CorBufferNew, CorBufferNewChild and CorBufferNewEx	



---

## CorBufferGetPrm

Gets buffer parameter value from a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferGetPrm</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>prm</i> , void * <i>value</i> );
<b>Description</b>	Get the buffer parameter value from a buffer resource. See the section Parameters for a descriptive list of all buffer parameters.
<b>Input</b>	<i>hBuffer</i> Buffer resource handle <i>prm</i> Buffer parameter requested
<b>Output</b>	<i>value</i> Current value of the parameter
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID
<b>See Also</b>	CorBufferSetPrm, CorBufferSetPrmEx and Parameters Section

---

## CorBufferMap

Map a buffer using physical memory into the virtual address space of the current process.

<b>Prototype</b>	CORSTATUS <b>CorBufferMap</b> ( CORBUFFER <i>hBuffer</i> );
<b>Description</b>	Maps a buffer using physical memory into the current process virtual address space
<b>Input</b>	<i>hBuffer</i> Buffer resource handle
<b>Notes</b>	This function should only be used for a buffer that has been created using the CORBUFFER_VAL_TYPE_UNMAPPED buffer type. For mapping a region, see the CorBufferMapEx function. This function is not available in Sapera LT for 64-bit Windows.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_RESOURCE_IN_USE CORSTATUS_NO_MEMORY
<b>See Also</b>	CorBufferMapEx, CorBufferUnmap

---

## CorBufferMapEx

Map a region of a buffer using physical memory into the virtual address space of the current process.

<b>Prototype</b>	CORSTATUS <b>CorBufferMapEx</b> ( CORBUFFER <i>hBuffer</i> , UINT64 <i>offset</i> , UINT32 <i>size</i> );
<b>Description</b>	Map a region of a buffer using physical memory into the current process virtual address space
<b>Input</b>	<i>hBuffer</i> Buffer resource handle <i>offset</i> Offset in byte from the origin <i>size</i> Size in byte of the region to be mapped
<b>Notes</b>	This function should only be used for a buffer that has been created using the CORBUFFER_VAL_TYPE_UNMAPPED buffer type. This function is not available in Sapera LT for 64-bit Windows.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_ARG_INVALID_VALUE CORSTATUS_RESOURCE_IN_USE CORSTATUS_NO_MEMORY
<b>See Also</b>	CorBufferUnmap

---

## CorBufferMergeComponents

Merge source buffers into the different components of a color buffer

<b>Prototype</b>	CORSTATUS <b>CorBufferMergeComponents</b> ( CORBUFFER <i>hCompA</i> , CORBUFFER <i>hCompB</i> , CORBUFFER <i>hCompC</i> , CORBUFFER <i>hDst</i> , UINT32 <i>options</i> );	
<b>Description</b>	Merges source buffers into the different components of a color buffer.	
<b>Input</b>	<i>hCompA</i>	Source buffer resource handle (can be set to NULL).
	<i>hCompB</i>	Source buffer resource handle (can be set to NULL).
	<i>hCompC</i>	Source buffer resource handle (can be set to NULL).
	<i>options</i>	Any of the following options can be specified:  CORBUFFER_CONVERT_RANGE_CLIP When a source pixel's value is outside the destination buffer format's range, it gets clipped to the nearest valid value. This is the default method.  CORBUFFER_CONVERT_RANGE_REMAP The source buffer's format is mapped to the destination buffer's format. When the source's and the destination's pixel depth are different (for example, when converting from MONO16 to MONO8) the buffers' CORBUFFER_PRM_PIXEL_DEPTH value is used to determine how the pixel values are remapped. This option cannot be used when the destination is floating-point.
<b>Output</b>	<i>hDst</i>	Destination buffer resource handle.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID CORSTATUS_INCOMPATIBLE_BUFFER CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_IMPLEMENTED	
<b>Note</b>	All the source buffers should have the same format, dimensions, and pixel depth.  For multiformat buffers, RGB888 and MONO8 are merged into a CORBUFFER_VAL_FORMAT_RGB888_MONO8 buffer and RGB161616 and MONO16 are merged into a CORBUFFER_VAL_FORMAT_RGB161616_MONO16 buffer (the 'hCompC' argument is ignored).	
<b>See Also</b>	CorBufferConvertFormat and CorBufferSplitComponents	

---

## CorBufferMultiFree

Free the handle to a multi-buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferMultiFree</b> (CORBUFFERMULTI <i>hBufferMulti</i> , CORBUFFER <i>hBuffers</i> []);	
<b>Description</b>	Free the handles and all resources used by a multi-buffer resource.	
<b>Input</b>	<i>hBufferMulti</i>	BufferMulti resource handle
	<i>hBuffers</i>	Array of Buffer resource handles
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_RESOURCE_LINKED	
<b>See Also</b>	CorBufferMultiNew	

---

## CorBufferMultiNew

Create in a specified server's memory a new multi-buffer resource

**Prototype**      `CORSTATUS CorBufferMultiNew (CORSERVER hServer, UINT32 width, UINT32 height,  
UINT32 format, UINT32 type, CORBUFFERMULTI *hBufferMulti, CORBUFFER hBuffers[],  
UINT32 count);`

**Description**      Creates in a server's memory multiple new buffer resources of the specified type, format, and size.

**Input**

<i>hServer</i>	Server handle
<i>width</i>	Width of new buffers in pixels
<i>height</i>	Height of new buffers in pixels
<i>format</i>	See Data Formats for detailed format descriptions.

### Monochrome and Unsigned integer

CORBUFFER\_VAL\_FORMAT\_MONO1  
CORBUFFER\_VAL\_FORMAT\_MONO8  
CORBUFFER\_VAL\_FORMAT\_MONO16  
CORBUFFER\_VAL\_FORMAT\_MONO32

### Integer (monochrome with sign)

CORBUFFER\_VAL\_FORMAT\_INT8  
CORBUFFER\_VAL\_FORMAT\_INT16  
CORBUFFER\_VAL\_FORMAT\_INT32

### Color

CORBUFFER\_VAL\_FORMAT\_RGB5551  
CORBUFFER\_VAL\_FORMAT\_RGB565  
CORBUFFER\_VAL\_FORMAT\_RGB888  
CORBUFFER\_VAL\_FORMAT\_RGB8888  
CORBUFFER\_VAL\_FORMAT\_RGB101010  
CORBUFFER\_VAL\_FORMAT\_RGB161616  
CORBUFFER\_VAL\_FORMAT\_RGB16161616  
CORBUFFER\_VAL\_FORMAT\_RGBP8  
CORBUFFER\_VAL\_FORMAT\_RGBP16  
CORBUFFER\_VAL\_FORMAT\_RGBR888  
CORBUFFER\_VAL\_FORMAT\_UYVY  
CORBUFFER\_VAL\_FORMAT\_YUY2  
CORBUFFER\_VAL\_FORMAT\_YVYU  
CORBUFFER\_VAL\_FORMAT\_YUYV  
CORBUFFER\_VAL\_FORMAT\_Y411  
CORBUFFER\_VAL\_FORMAT\_Y211  
CORBUFFER\_VAL\_FORMAT\_YUV  
CORBUFFER\_VAL\_FORMAT\_HSV  
CORBUFFER\_VAL\_FORMAT\_HSI  
CORBUFFER\_VAL\_FORMAT\_HSIP8  
CORBUFFER\_VAL\_FORMAT\_BICOLOR88  
CORBUFFER\_VAL\_FORMAT\_BICOLOR1616

### Multiformat

CORBUFFER\_VAL\_FORMAT\_RGB888\_MONO8  
CORBUFFER\_VAL\_FORMAT\_RGB161616\_MONO16

### Other

CORBUFFER\_VAL\_FORMAT\_FLOAT  
CORBUFFER\_VAL\_FORMAT\_COMPLEX  
CORBUFFER\_VAL\_FORMAT\_POINT  
CORBUFFER\_VAL\_FORMAT\_FPOINT

*type*      The following buffer types are valid.

CORBUFFER\_VAL\_TYPE\_SCATTER\_GATHER

The buffers are allocated in noncontiguous memory (paged pool). Pages are locked in physical memory so that a scatter-gather list can be constructed. This type allows allocation of very large sized buffers used as source and destination for the transfer resource. Note that the maximum amount of memory that can be allocated with respect to available memory on the computer depends upon the operating system and the application(s) used.

	<i>count</i>	Number of buffers to allocate
<b>Output</b>	<i>hBufferMulti</i>	BufferMulti resource handle. Can be used to assign all buffers to a transfer pair.
	<i>hBuffers</i>	Array of Buffer resource handles allocated.
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_INVALID_VALUE	
	CORSTATUS_ARG_NULL (if <i>hBufferMulti</i> is NULL)	
	CORSTATUS_DDRAW_ERROR	
	CORSTATUS_DDRAW_NOT_AVAILABLE	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CORSTATUS_NO_MEMORY	
	CorBufferMultiFree	

---

## CorBufferNew

Create in a specified server's memory a new buffer resource

**Prototype**      `CORSTATUS CorBufferNew(CORSERVER hServer, UINT32 width, UINT32 height, UINT32 format, UINT32 type, CORBUFFER *hBuffer);`

**Description**    Creates in a server's memory a new buffer resource of the specified type, format, and size.

**Input**

<i>hServer</i>	Server handle
<i>width</i>	Width of new buffer in pixels
<i>height</i>	Height of new buffer in pixels
<i>format</i>	See Data Formats for detailed format descriptions.

**Monochrome and Unsigned integer**

`CORBUFFER_VAL_FORMAT_MONO1`  
`CORBUFFER_VAL_FORMAT_MONO8`  
`CORBUFFER_VAL_FORMAT_MONO16`  
`CORBUFFER_VAL_FORMAT_MONO32`

**Integer (monochrome with sign)**

`CORBUFFER_VAL_FORMAT_INT8`  
`CORBUFFER_VAL_FORMAT_INT16`  
`CORBUFFER_VAL_FORMAT_INT32`

**Color**

`CORBUFFER_VAL_FORMAT_RGB5551`  
`CORBUFFER_VAL_FORMAT_RGB565`  
`CORBUFFER_VAL_FORMAT_RGB888`  
`CORBUFFER_VAL_FORMAT_RGB8888`  
`CORBUFFER_VAL_FORMAT_RGB101010`  
`CORBUFFER_VAL_FORMAT_RGB161616`  
`CORBUFFER_VAL_FORMAT_RGB16161616`  
`CORBUFFER_VAL_FORMAT_RGBP8`  
`CORBUFFER_VAL_FORMAT_RGBP16`  
`CORBUFFER_VAL_FORMAT_RGBR888`  
`CORBUFFER_VAL_FORMAT_UYVY`  
`CORBUFFER_VAL_FORMAT_YUY2`  
`CORBUFFER_VAL_FORMAT_YVYU`  
`CORBUFFER_VAL_FORMAT_YUYV`  
`CORBUFFER_VAL_FORMAT_Y411`  
`CORBUFFER_VAL_FORMAT_Y211`  
`CORBUFFER_VAL_FORMAT_YUV`  
`CORBUFFER_VAL_FORMAT_HSV`  
`CORBUFFER_VAL_FORMAT_HSI`  
`CORBUFFER_VAL_FORMAT_HSIP8`  
`CORBUFFER_VAL_FORMAT_BICOLOR88`  
`CORBUFFER_VAL_FORMAT_BICOLOR1616`

**Multiformat**

`CORBUFFER_VAL_FORMAT_RGB888_MONO8`  
`CORBUFFER_VAL_FORMAT_RGB161616_MONO16`

**Other**

`CORBUFFER_VAL_FORMAT_FLOAT`  
`CORBUFFER_VAL_FORMAT_COMPLEX`  
`CORBUFFER_VAL_FORMAT_POINT`  
`CORBUFFER_VAL_FORMAT_FPOINT`

*type*            The following buffer types are valid.

`CORBUFFER_VAL_TYPE_CONTIGUOUS`

The buffer is allocated in Contiguous Memory. The buffer data is contained in a single memory block (no segmentation). Allocated buffers can be used as source and destination for the transfer resource.

`CORBUFFER_VAL_TYPE_SCATTER_GATHER`

The buffer is allocated in noncontiguous memory (paged pool). Pages are locked in physical memory so that a scatter-gather list can be constructed. This type allows allocation of very large sized buffers used as source and destination for the

transfer resource. Note that the maximum amount of memory that can be allocated with respect to available memory on the computer depends upon the operating system and the application(s) used.

#### CORBUFFER\_VAL\_TYPE\_VIRTUAL

Similar to a scatter-gather buffer except that the memory pages are not locked. This type allows allocation of very large buffers, but they cannot be used as source or destination for the transfer resource.

#### CORBUFFER\_VAL\_TYPE\_UNMAPPED

The buffer is allocated in system memory. Pages are allocated but not mapped into the process virtual address space. Before trying to retrieve the buffer virtual address, the buffer's memory has to be mapped into the process virtual address space by calling either the `CorBufferMap` or the `CorBufferMapEx` function. This buffer type can be logically ORed with `CORBUFFER_VAL_TYPE_SCATTER_GATHER` to create a source buffer or destination buffer for a transfer resource.

#### CORBUFFER\_VAL\_TYPE\_OFFSCREEN

The buffer is allocated in system memory. The Display Module view created using this buffer type may use the display adapter's hardware to copy the system memory buffer to the display memory. A system memory off-screen buffer can be created using any pixel format, but calling `CorViewShow` with its corresponding view will take longer to execute if its pixel format is not listed in the `CORDISPLAY_PRM_PIXEL_TYPE_OFFSCREEN` parameter.

#### CORBUFFER\_VAL\_TYPE\_VIDEO

The buffer is allocated in off-screen video memory. The view created using a buffer of this type uses the display adapter's hardware to perform a fast copy from video memory to video memory. Typically, a buffer of this type is used when a graphical element is reused for several consecutive frames without modification. In this case, it is more efficient to keep this element in video memory and use the display hardware to copy it to the appropriate position in each frame.

#### CORBUFFER\_VAL\_TYPE\_OVERLAY

This buffer is allocated in video memory. Once you create a view using this buffer and call `CorViewShow` once, the display adapter's overlay hardware will keep updating the display with the buffer's contents without additional `CorViewShow` calls. The pixel format of an overlay buffer must be listed in the `CORDISPLAY_PRM_PIXEL_TYPE_OVERLAY` parameter. Typically, overlay buffers will support more pixel formats (like YUV) than off-screen buffers. Also, color keying is supported for overlays. The behavior of the overlay regarding key colors is determined by the `CORVIEW_PRM_MODE` parameter.

#### CORBUFFER\_VAL\_TYPE\_DUMMY

No memory is allocated for a dummy buffer in order that it does not contain any data elements. This type of buffer may be used as a placeholder by the Transfer Module when no data is to be physically transferred.

**Output** *hBuffer* Buffer resource handle

**Return Value** `CORSTATUS_OK`  
`CORSTATUS_ARG_INVALID_VALUE`  
`CORSTATUS_ARG_NULL` (if *hBuffer* is `NULL`)  
`CORSTATUS_DDRAW_ERROR`  
`CORSTATUS_DDRAW_NOT_AVAILABLE`  
`CORSTATUS_INVALID_HANDLE`  
`CORSTATUS_NO_MEMORY`

**Notes** Type `CORBUFFER_VAL_TYPE_MONO1` (1-bit data depth) buffers are created with the following restrictions:

- Width must be a multiple of 8
- Type must be `CONTIGUOUS`, `SCATTER_GATHER`, or `VIRTUAL`

Type `CORBUFFER_VAL_TYPE_OFFSCREEN`, `CORBUFFER_VAL_TYPE_VIDEO`, & `CORBUFFER_VAL_TYPE_OVERLAY` utilize Windows and VGA hardware DirectDraw (Windows XP 32-bit only) support to create and display buffers in off-screen VGA surfaces. Under different combinations of Windows version, DirectX version, and the VGA driver, the following three conditions may cause failure with DirectDraw in the creation of off-screen surface buffers.

- Having a screen saver activated.

- Opening a full screen Command session (DOS prompt).
  - Pressing CTL-ALT-DEL which hides the current Desktop and displays a Windows menu.
- Properly written Sopera applications should present any DirectDraw errors as a windows message box to the user. As part of the message, the above points can be presented as solutions to the problem. It is suggested that these conditions be avoided on the application target system. Review and test each condition to understand the behavior in your environment.

The multi-format buffer types (CORBUFFER\_VAL\_FORMAT\_RGB888\_MONO8 and CORBUFFER\_VAL\_FORMAT\_RGB161616\_MONO16) do not support Color (Bayer) conversion; loading and saving these buffer types only support the CRC and RAW formats. Use the CorBufferSplitComponents to split these buffers into two buffers with their respective RGB and MONO formats.

---

## CorBufferNew1D

Create in a specified server's memory at a given address a new 1D buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferNew1D</b> (CORSERVER <i>hServer</i> , UINT32 <i>width</i> , UINT32 <i>format</i> , UINT32 <i>type</i> , CORBUFFER * <i>hBuffer</i> );	
<b>Description</b>	Creates in a specified server's memory a new one-dimensional buffer resource of the specified type, format, and size.	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>width</i>	Width of new child buffer in pixels
	<i>format</i>	Format of new buffer. See CorBufferNew.
	<i>type</i>	Type of new buffer.
<b>Output</b>	<i>hBuffer</i>	Buffer resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID_VALUE CORSTATUS_ARG_NULL (if hBuffer is NULL) CORSTATUS_DDRAW_ERROR CORSTATUS_DDRAW_NOT_AVAILABLE CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY	
<b>See Also</b>	CorBufferFree	

---

## CorBufferNew2D

Create in a specified server's memory at a given address a new 2D buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferNew2D</b> (CORSERVER <i>hServer</i> , UINT32 <i>width</i> , UINT32 <i>height</i> , UINT32 <i>format</i> , UINT32 <i>type</i> , CORBUFFER * <i>hBuffer</i> );	
<b>Description</b>	Creates in a specified server's memory a new two-dimensional buffer resource of the specified type, height, format, and size.	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>width</i>	Width of new child buffer in pixels
	<i>height</i>	Height of new child buffer in lines
	<i>format</i>	Format of new buffer. See CorBufferNew.
	<i>type</i>	Type of new buffer
<b>Output</b>	<i>hBuffer</i>	Buffer resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID_VALUE CORSTATUS_ARG_NULL (if <i>hBuffer</i> is NULL) CORSTATUS_DDRAW_ERROR CORSTATUS_DDRAW_NOT_AVAILABLE CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY	
<b>See Also</b>	CorBufferFree	

---

## CorBufferNewChild

Create a new buffer resource within an existing buffer

<b>Prototype</b>	CORSTATUS <b>CorBufferNewChild</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>x</i> , UINT32 <i>y</i> , UINT32 <i>width</i> , UINT32 <i>height</i> , CORBUFFER * <i>hChild</i> );	
<b>Description</b>	Creates a new buffer resource as a sub-area of an existing parent buffer. The sub-area rectangle (specified by <i>x</i> , <i>y</i> , <i>width</i> and <i>height</i> ) must not exceed any of the parent's borders.	
<b>Input</b>	<i>hBuffer</i>	Buffer resource handle
	<i>x</i>	Horizontal offset between parent and child's top left corners.
	<i>y</i>	Vertical offset between parent and child's top left corners.
	<i>width</i>	Width of new child buffer in pixels.
	<i>height</i>	Height of new child buffer in pixels.
<b>Output</b>	<i>hChild</i>	Buffer resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID CORSTATUS_ARG_NULL (if <i>hChild</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY	
<b>Note</b>	The child buffer is not a separate copy of the parent buffer. A 1-bit data child buffer must have the same dimensions as the parent buffer.	
<b>See Also</b>	CorBufferFree	



---

## CorBufferNew1DChild

Create a new 1D buffer resource within an existing 1D buffer

<b>Prototype</b>	CORSTATUS <b>CorBufferNew1DChild</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>x</i> , UINT32 <i>width</i> , CORBUFFER * <i>hChild</i> );
<b>Description</b>	Creates a new one dimensional buffer resource as a sub-area of an existing parent buffer. The sub-area (specified by <i>x</i> and <i>width</i> ) must not exceed any of the parent's borders.
<b>Input</b>	<i>hBuffer</i> Buffer resource handle <i>x</i> Horizontal offset between parent and child's top left corners. <i>width</i> Width of new child buffer in pixels.
<b>Output</b>	<i>hChild</i> Buffer resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID CORSTATUS_ARG_NULL ( if <i>hChild</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY
<b>Note</b>	The child buffer is not a separate copy of the parent buffer. A 1-bit data child buffer must have the same dimensions as the parent buffer.
<b>See Also</b>	CorBufferFree

---

## CorBufferNew2DChild

Create a new 2D buffer resource within an existing 2D buffer

<b>Prototype</b>	CORSTATUS <b>CorBufferNew2DChild</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>x</i> , UINT32 <i>y</i> , UINT32 <i>width</i> , UINT32 <i>height</i> , CORBUFFER * <i>hChild</i> );
<b>Description</b>	Creates a new two dimensional buffer resource as a sub-area of an existing parent buffer. The sub-area (specified by <i>x</i> , <i>y</i> , <i>width</i> and <i>height</i> ) must not exceed any of the parent's borders.
<b>Input</b>	<i>hBuffer</i> Buffer resource handle <i>x</i> Horizontal offset between parent and child's top left corners. <i>y</i> Vertical offset between parent and child's top left corners. <i>width</i> Width of new child buffer in pixels. <i>height</i> Height of new child buffer in pixels.
<b>Output</b>	<i>hChild</i> Buffer resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID CORSTATUS_ARG_NULL (if <i>hChild</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY
<b>Note</b>	The child buffer is not a separate copy of the parent buffer. A 1-bit data child buffer must have the same dimensions than its parent.
<b>See Also</b>	CorBufferFree

---

## CorBufferNewEx

Create in a specified server's memory at a given address a new buffer resource

**Prototype**      `CORSTATUS CorBufferNewEx(CORSERVER hServer, UINT32 width, UINT32 height,  
UINT32 format, UINT32 type, UINT32 physAddress, UINT32 virtualAddress, CORBUFFER  
*hBuffer);`

**Description**      Creates in a specified server's memory (virtual or physical address) a new buffer resource of the specified type, format, and size.

If the physical address is specified as 0, the virtual address must not be 0, and that memory is not considered as contiguous. If the physical address is not specified as 0 then the virtual address should be specified as 0. In this case, the virtual address is determined automatically from the physical address and read by getting the CORBUFFER\_PRM\_ADDRESS parameter.

**Input**

<i>hServer</i>	Server handle
<i>width</i>	Width of new child buffer in pixels.
<i>height</i>	Height of new child buffer in pixels.
<i>format</i>	Format of new buffer, see CorBufferNew
<i>type</i>	New buffer type values: CORBUFFER_VAL_TYPE_SCATTER_GATHER or CORBUFFER_VAL_TYPE_CONTIGUOUS.
<i>physAddress</i>	Physical address of new buffer.
<i>virtualAddress</i>	Virtual address of new buffer.

**Output**      *hBuffer*      Buffer resource handle

**Return Value**      CORSTATUS\_OK  
CORSTATUS\_ARG\_INVALID\_VALUE  
CORSTATUS\_ARG\_NULL ( if *hBuffer* is NULL)  
CORSTATUS\_INVALID\_HANDLE  
CORSTATUS\_NO\_MEMORY

**See Also**      CorBufferFree and CORBUFFER\_PRM\_ADDRESS

---

## CorBufferNew1DEx

Create in a specified server's memory at a given address a new 1D buffer resource

**Prototype**      `CORSTATUS CorBufferNewEx(CORSERVER hServer, UINT32 width, UINT32 format,  
UINT32 type, UINT32 physAddress, UINT32 virtualAddress, CORBUFFER *hBuffer);`

**Description**      Creates in a specified server's memory (virtual or physical address) a new one dimensional buffer resource of the specified type, format, and size.

If the physical address is specified as 0, the virtual address must not be 0, and that memory is not considered as contiguous. If the physical address is not specified as 0 then the virtual address should be specified as 0. In this case the virtual address is determined automatically from the physical address and read by getting the CORBUFFER\_PRM\_ADDRESS parameter.

**Input**

<i>hServer</i>	Server handle
<i>width</i>	Width of new child buffer in pixels.
<i>format</i>	Format of new buffer, see CorBufferNew
<i>type</i>	New buffer type values: CORBUFFER_VAL_TYPE_SCATTER_GATHER or CORBUFFER_VAL_TYPE_CONTIGUOUS.
<i>physAddress</i>	Physical address of new buffer.
<i>virtualAddress</i>	Virtual address of new buffer.

**Output**      *hBuffer*      Buffer resource handle

**Return Value**      CORSTATUS\_OK  
CORSTATUS\_ARG\_INVALID\_VALUE  
CORSTATUS\_ARG\_NULL ( if *hBuffer* is NULL)  
CORSTATUS\_INVALID\_HANDLE  
CORSTATUS\_NO\_MEMORY

**See Also**      CorBufferFree and CORBUFFER\_PRM\_ADDRESS

---

## CorBufferNew2DEx

Create in a specified server's memory at a given address a new 2D buffer resource

**Prototype**      `CORSTATUS CorBufferNew2DEx(CORSERVER hServer, UINT32 width, UINT32 height,  
UINT32 format, UINT32 type, UINT32 physAddress, UINT32 virtualAddress, CORBUFFER  
*hBuffer);`

**Description**      Creates in a specified server's memory (virtual or physical address) a new two dimensional  
buffer resource of the specified type, format, and size.  
  
If the physical address is specified as 0, the virtual address must not be 0, and that memory is  
not considered as contiguous. If the physical address is not specified as 0 then the virtual  
address should be specified as 0. In this case the virtual address is determined automatically  
from the physical address and read by getting the CORBUFFER\_PRM\_ADDRESS parameter.

**Input**

<i>hServer</i>	Server handle
<i>width</i>	Width of new child buffer in pixels.
<i>height</i>	Height of new child buffer in pixels.
<i>format</i>	Format of new buffer, see CorBufferNew.
<i>type</i>	New buffer type value. CORBUFFER_VAL_TYPE_SCATTER_GATHER or CORBUFFER_VAL_TYPE_CONTIGUOUS.
<i>physAddress</i>	Physical address of new buffer.
<i>virtualAddress</i>	Virtual address of new buffer.

**Output**      *hBuffer*      Buffer resource handle

**Return Value**      CORSTATUS\_OK  
CORSTATUS\_ARG\_INVALID\_VALUE  
CORSTATUS\_ARG\_NULL (if *hBuffer* is NULL)  
CORSTATUS\_INVALID\_HANDLE  
CORSTATUS\_NO\_MEMORY

**See Also**      CorBufferFree and CORBUFFER\_PRM\_ADDRESS

---

## CorBufferNewShared

Create in a specified server's memory a new buffer resource that can be shared between processes

<b>Prototype</b>	CORSTATUS <b>CorBufferNewShared</b> (CORSERVER <i>hServer</i> , UINT32 <i>width</i> , UINT32 <i>height</i> , UINT32 <i>format</i> , UINT32 <i>type</i> , PCSTR <i>name</i> , CORBUFFER * <i>hBuffer</i> );	
<b>Description</b>	Creates in a server's memory a new buffer resource of the specified type, format, and size that can be shared with other processes running on this server	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>width</i>	Width of new buffer in pixels
	<i>height</i>	Height of new buffer in pixels
	<i>format</i>	Format of new buffer, see CorBufferNew.
	<i>type</i>	The following buffer types are valid. (See the " <i>Sapera LT User's Manual</i> " for further information).  CORBUFFER_VAL_TYPE_SCATTER_GATHER The buffer is allocated in noncontiguous memory (paged pool). Pages are locked in physical memory so that a scatter-gather list can be constructed. This type allows allocation of very large sized buffers used as source and destination for the transfer resource. Note that the maximum amount of memory that can be allocated with respect to available memory on the computer depends upon the operating system and the application(s) used.  CORBUFFER_VAL_TYPE_VIRTUAL Similar to a scatter-gather buffer except that the memory pages are not locked. This type allows allocation of very large buffers, but they cannot be used as source or destination for the transfer resource.
	<i>name</i>	Name to be given to the shared buffer.  This name has to be unique in the system since it will be used to reference a specific shared buffer resource
<b>Output</b>	<i>hBuffer</i>	Buffer resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID_VALUE CORSTATUS_ARG_NULL (if either <i>hBuffer</i> or <i>name</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY	
<b>Notes</b>	Type CORBUFFER_VAL_TYPE_MONO1 (1-bit data depth) buffers are restricted to a width that must be a multiple of 8.	
<b>See Also</b>	CorBufferFree	

---

## CorBufferNewSharedEx

Create in a specified server's memory a new buffer resource that references a previously allocated shared buffer

<b>Prototype</b>	CORSTATUS <b>CorBufferNewSharedEx</b> (CORSERVER <i>hServer</i> , UINT32 <i>type</i> PCSTR <i>name</i> , CORBUFFER * <i>hBuffer</i> );	
<b>Description</b>	Creates in a specified server's memory a new buffer resource that references a previously allocated shared buffer.	
<b>Input</b>	<i>HServer</i>	Server handle
	<i>Type</i>	The following buffer types are valid. (See the " <i>Sapera LT User's Manual</i> " for further information).  CORBUFFER_VAL_TYPE_SCATTER_GATHER The buffer is allocated in noncontiguous memory (paged pool). Pages are locked in physical memory so that a scatter-gather list can be constructed. This type allows allocation of very large sized buffers used as source and destination for the transfer resource. Note that the maximum amount of memory that can be allocated with respect to available memory on the computer depends upon the operating system and the application(s) used.  CORBUFFER_VAL_TYPE_VIRTUAL Similar to a scatter-gather buffer except that the memory pages are not locked. This type allows allocation of very large buffers, but they cannot be used as source or destination for the transfer resource.
<b>Output</b>	<i>name</i>	Name of a previously allocated shared buffer.
	<i>hBuffer</i>	Buffer resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID_VALUE CORSTATUS_ARG_NULL ( if <i>hBuffer</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY	
<b>See Also</b>	CorBufferNewShared and CorBufferFree	

---

## CorBufferRead

Read a series of elements from a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferRead</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>offset</i> , void * <i>array</i> , UINT32 <i>size</i> );	
<b>Description</b>	Reads a consecutive series of elements continuously from the specified buffer resource. Elements are read to the end of the buffer line and then continued from the beginning of the next line, until <i>length</i> elements have been read. Elements are then copied into a one-dimensional destination array.	
<b>Input</b>	<i>hBuffer</i>	Buffer resource handle
	<i>offset</i>	Offset to seek within the buffer prior to read (in pixels)
	<i>size</i>	Size of transfer ( <i>number of elements</i> × CORBUFFER_PRM_DATASIZE bytes). For 1-bit data buffers, size should be (( <i>number of elements</i> + 7) >> 3) bytes.
<b>Output</b>	<i>array</i>	Array which can accommodate the requested size ( <i>number of elements</i> × CORBUFFER_PRM_DATASIZE). For 1-bit data buffers, the array size should be (( <i>number of elements</i> + 7) >> 3) bytes.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>array</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE	
<b>Note</b>	Reading elements from video memory buffers may be very slow. For 1-bit data buffers, the offset must be a multiple of 8.	
<b>See Also</b>	CorBufferWrite	

---

## CorBufferReadDots

Read a set of elements from a buffer resource

Prototype	CORSTATUS <b>CorBufferReadDots</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>xStart</i> , UINT32 <i>yStart</i> , const UINT8 <i>*dirs</i> , UINT32 <i>nDirs</i> , void <i>*array</i> , UINT32 <i>size</i> );									
Description	Reads <i>nDirs</i> elements to an <i>array</i> from a set of locations in a buffer resource as defined by <i>xStart</i> , <i>yStart</i> and the list of directions given by <i>dirs</i> .									
Input	<i>hBuffer</i>	Buffer resource handle								
	<i>xStart</i>	Horizontal position of first element (dot) to read								
	<i>yStart</i>	Vertical position of first element (dot) to read								
	<i>dirs</i>	Series of bytes defining the path to follow. Each byte represents the direction to the next adjacent element to read, as indicated in the following table.								
		<b>Value</b>	1	2	3	4	5	6	7	8
		<b>Direction</b>	E	NE	N	NW	W	SW	S	SE
		A value of zero or greater than 8 is ignored; the previous element is read again.								
	<i>nDirs</i>	Amount of given directions (or dots to read)								
	<i>size</i>	Size of transfer ( <i>nDirs</i> ×CORBUFFER_PRM_DATASIZE bytes)								
Output	<i>array</i>	Array which can accommodate the requested number of elements ( <i>nDirs</i> ×CORBUFFER_PRM_DATASIZE)								
Return Value	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>array</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE									
Note	Reading elements from video memory buffers may be very slow. Function not supported by 1-bit data buffers.									
See Also	CorBufferWriteDots									

---

## CorBufferReadElement

Read an element from a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferReadElement</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>xPos</i> , UINT32 <i>yPos</i> , void <i>*element</i> , UINT32 <i>size</i> );		
<b>Description</b>	Reads a single element at ( <i>xPos</i> , <i>yPos</i> ) from a buffer resource.		
<b>Input</b>	<i>hBuffer</i>	Buffer resource handle	
	<i>xPos</i>	Horizontal position of the element in the buffer	
	<i>yPos</i>	Vertical position of the element in the buffer	
	<i>size</i>	Size of transfer (CORBUFFER_PRM_DATASIZE bytes)	
<b>Output</b>	<i>element</i>	Current value of the element	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>element</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE		
<b>Note</b>	Reading elements from video memory buffers may be very slow.  For multiformat buffer types the order is B/G/R/M. For CORBUFFER_VAL_FORMAT_RGB888_MONO8 this is a 32-bit value; for CORBUFFER_VAL_FORMAT_RGB161616_MONO16 this is a 64-bit value.		
<b>See Also</b>	CorBufferWriteElement		

---

## CorBufferReadElementEx

Read an element from a buffer resource

<b>Prototype</b>	<code>CONSTATUS <b>CorBufferReadElementEx</b>(CORBUFFER <i>hBuffer</i>, UINT32 <i>xPos</i>, UINT32 <i>yPos</i>, CORDATA *<i>element</i>);</code>
<b>Description</b>	Reads an element from a buffer resource and pack its value into the CORDATA argument.
<b>Input</b>	<i>hBuffer</i> Buffer resource handle <i>xPos</i> Horizontal position of the element in the buffer <i>yPos</i> Vertical position of the element in the buffer
<b>Output</b>	<i>element</i> Current value of the element. See Data Types for the <i>CORDATA</i> definition.
<b>Return Value</b>	CONSTATUS_OK CONSTATUS_ARG_NULL ( if <i>element</i> is NULL) CONSTATUS_ARG_OUT_OF_RANGE CONSTATUS_INVALID_HANDLE
<b>Note</b>	Reading elements from video memory buffers may be very slow. Multiformat buffers (for example, CORBUFFER_VAL_FORMAT_RGB888_MONO8 and CORBUFFER_VAL_FORMAT_RGB161616_MONO16) use the 'rgba' structure (red/green/blue/alpha) inside CORDATA values.
<b>See Also</b>	CorBufferWriteElementEx

---

## CorBufferReadLine

Read a set of linearly positioned elements from a buffer resource

<b>Prototype</b>	<code>CONSTATUS <b>CorBufferReadLine</b>(CORBUFFER <i>hBuffer</i>, UINT32 <i>x1</i>, UINT32 <i>y1</i>, UINT32 <i>x2</i>, UINT32 <i>y2</i>, UINT32 *<i>nElements</i>, void *<i>array</i>, UINT32 <i>size</i>);</code>
<b>Description</b>	Read elements in a line within a buffer, from position ( <i>x1</i> , <i>y1</i> ) to position ( <i>x2</i> , <i>y2</i> ), and copies them into an array.
<b>Input</b>	<i>hBuffer</i> Buffer resource handle <i>x1</i> Horizontal position of first element to read <i>y1</i> Vertical position of first element to read <i>x2</i> Horizontal position of last element to read <i>y2</i> Vertical position of last element to read <i>size</i> Size of transfer (MAX( ABS( <i>x2</i> - <i>x1</i> ), ABS( <i>y2</i> - <i>y1</i> ) + 1) × CORBUFFER_PRM_DATASIZE bytes)
<b>Output</b>	<i>array</i> Array which can accommodate the requested number of elements (MAX( ABS( <i>x2</i> - <i>x1</i> ), ABS( <i>y2</i> - <i>y1</i> ) + 1) × CORBUFFER_PRM_DATASIZE) <i>nElements</i> Number of elements read
<b>Return Value</b>	CONSTATUS_OK CONSTATUS_ARG_INVALID_VALUE CONSTATUS_ARG_NULL ( if <i>number of elements</i> or <i>array</i> is NULL) CONSTATUS_ARG_OUT_OF_RANGE CONSTATUS_INVALID_HANDLE
<b>Note</b>	Reading elements from video memory buffers may be very slow. Function not supported by 1-bit data buffers.
<b>See Also</b>	CorBufferWriteLine



---

## CorBufferReadRect

Read a set of elements forming a rectangular area from a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferReadRect</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>x</i> , UINT32 <i>y</i> , UINT32 <i>width</i> , UINT32 <i>height</i> , void * <i>array</i> , UINT32 <i>size</i> );		
<b>Description</b>	Reads the elements of a rectangular area from a buffer resource into an array.		
<b>Input</b>	<i>hBuffer</i>	Buffer resource handle	
	<i>x</i>	Horizontal offset in source buffer	
	<i>y</i>	Vertical offset in source buffer	
	<i>width</i>	Horizontal length of the rectangle (must be 2 or greater)	
	<i>height</i>	Vertical length of the rectangle (must be 2 or greater)	
	<i>size</i>	Size of transfer ( <i>width</i> × <i>height</i> ×CORBUFFER_PRM_DATASIZE bytes) For 1-bit data buffers, <i>size</i> should be (( <i>width</i> × <i>height</i> ) >> 3) bytes	
<b>Output</b>	<i>array</i>	Array which can accommodate the requested number of elements ( <i>width</i> × <i>height</i> ×CORBUFFER_PRM_DATASIZE) For 1-bit data buffers, the <i>array</i> size should be (( <i>width</i> × <i>height</i> ) >> 3) bytes	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>array</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE		
<b>Note</b>	Reading elements from video memory buffers may be very slow. For 1-bit data buffers, <i>x</i> and <i>width</i> must be in multiples of 8.		
<b>See Also</b>	CorBufferWriteRect		

---

## CorBufferSetPrm

Set a simple buffer parameter of a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferSetPrm</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );		
<b>Description</b>	Sets a simple parameter of a buffer resource. A simple parameter fits inside an UINT32.		
<b>Input</b>	<i>hBuffer</i>	Buffer resource handle	
	<i>prm</i>	Buffer parameter to set	
	<i>value</i>	New value of the parameter	
<b>Output</b>	None		
<b>Return Value</b>	CORSTATUS_OK		
	CORSTATUS_ARG_INVALID_VALUE		
	CORSTATUS_INVALID_HANDLE		
	CORSTATUS_PRM_INVALID		
	CORSTATUS_PRM_NOT_AVAILABLE		
	CORSTATUS_PRM_READ_ONLY		
<b>Note</b>	For complex parameters, use CorBufferSetPrmEx. See the Parameters section.		
<b>See Also</b>	CorBufferGetPrm and CorBufferSetPrmEx		

---

## CorBufferSetPrmEx

Set a complex buffer parameter of a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferSetPrmEx</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>prm</i> , const void * <i>value</i> );
<b>Description</b>	Sets a complex parameter of a buffer resource. A complex parameter is greater than an UINT32.
<b>Input</b>	<i>hBuffer</i> Buffer resource handle <i>prm</i> Buffer parameter to set <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID_VALUE CORSTATUS_ARG_NULL ( if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_PRM_READ_ONLY
<b>Note</b>	If the parameter size is UINT32, either CorBufferSetPrm or CorBufferSetPrmEx can be used.
<b>See Also</b>	CorBufferGetPrm, CorBufferSetPrm and Parameters section

---

## CorBufferSplitComponents

Split a color buffer into each of its components

<b>Prototype</b>	CORSTATUS <b>CorBufferSplitComponents</b> ( CORBUFFER <i>hSrc</i> , CORBUFFER <i>hCompA</i> , CORBUFFER <i>hCompB</i> , CORBUFFER <i>hCompC</i> , UINT32 <i>options</i> );
<b>Description</b>	Splits a color buffer into each of its components.
<b>Input</b>	<i>hSrc</i> Source buffer resource handle. <i>options</i> Any of the following options can be specified: CORBUFFER_CONVERT_RANGE_CLIP When a source pixel's value is outside the destination buffer format's range, it gets clipped to the nearest valid value. This is the default method. CORBUFFER_CONVERT_RANGE_REMAP The source buffer's format is mapped to the destination buffer's format. When the source and the destination pixel depths are different (for example, when converting from MONO16 to MONO8) the buffers' CORBUFFER_PRM_PIXEL_DEPTH value is used to determine how the pixel values are remapped. This option cannot be used when the destination is floating-point.
<b>Output</b>	<i>hCompA</i> Destination buffer resource handle (can be set to NULL). <i>hCompB</i> Destination buffer resource handle (can be set to NULL). <i>hCompC</i> Destination buffer resource handle (can be set to NULL).
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID CORSTATUS_INCOMPATIBLE_BUFFER CORSTATUS_NOT_IMPLEMENTED CORSTATUS_INVALID_HANDLE
<b>Note</b>	All the destination buffers should have the same format, dimensions, and pixel depth. Multiformat buffers CORBUFFER_VAL_FORMAT_RGB888_MONO8 and CORBUFFER_VAL_FORMAT_RGB161616_MONO16 are split into corresponding RGB888/RGB161616 and MONO8/MONO16 buffers (the 'hCompC' argument is ignored).
<b>See Also</b>	CorBufferConvertFormatand CorBufferMergeComponents

---

## CorBufferUnmap

Unmap the buffer physical memory from the current process virtual address space

<b>Prototype</b>	CORSTATUS <b>CorBufferUnmap</b> ( CORBUFFER <i>hBuffer</i> );
<b>Description</b>	Unmap the buffer physical memory from the current process virtual address space
<b>Input</b>	<i>hBuffer</i> Buffer resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY  This function is not available in Sapera LT for 64-bit Windows.
<b>See Also</b>	CorBufferMap and CorBufferMapEx

---

## CorBufferWrite

Write a series of elements to a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferWrite</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>offset</i> , const void * <i>array</i> , UINT32 <i>size</i> );
<b>Description</b>	Writes a series of elements from a one-dimensional source array to the buffer resource.
<b>Input</b>	<i>hBuffer</i> Buffer resource handle  <i>offset</i> Offset to seek within the buffer prior to write (in pixels)  <i>array</i> Array which contains the elements to be written: ( <i>number of elements</i> ×CORBUFFER_PRM_DATASIZE) bytes. For 1-bit data buffers, the array size should be $((\text{number of elements} + 7) >> 3)$ bytes  <i>size</i> Size of transfer ( <i>number of elements</i> ×CORBUFFER_PRM_DATASIZE) bytes For 1-bit data buffers, the array size is $((\text{number of elements} + 7) >> 3)$ bytes
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>array</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE
<b>Note</b>	For 1-bit data buffers, <i>offset</i> must be a multiple of 8.
<b>See Also</b>	CorBufferRead

---

## CorBufferWriteDots

Write at specific locations a series of elements to a buffer resource

Prototype	CORSTATUS <b>CorBufferWriteDots</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>xStart</i> , UINT32 <i>yStart</i> , const UINT8 <i>*dirs</i> , UINT32 <i>nDirs</i> , const void <i>*array</i> , UINT32 <i>size</i> );								
Description	Writes <i>nDirs</i> elements from an <i>array</i> to the set of locations in a buffer resource as defined by <i>xStart</i> , <i>yStart</i> and the list of directions given by <i>dirs</i> .								
Input	<i>hBuffer</i>	Buffer resource handle							
	<i>xStart</i>	Horizontal position of first element (dot) to write							
	<i>yStart</i>	Vertical position of first element (dot) to write							
	<i>dirs</i>	Series of bytes defining the path to follow. Each byte represents the direction to the next adjacent element to write, as indicated in the following below:							
	<b>Value</b>	1	2	3	4	5	6	7	8
	<b>Direction</b>	E	NE	N	NW	W	SW	S	SE
		A value of zero or greater than 8 is ignored; the previous element is written again.							
	<i>nDirs</i>	Amount of given directions (or dots to read)							
	<i>array</i>	Array which contains the elements to be written ( <i>nDirs</i> ×CORBUFFER_PRM_DATASIZE)							
	<i>size</i>	Size of transfer ( <i>nDirs</i> ×CORBUFFER_PRM_DATASIZE bytes)							
Output	None								
Return Value	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>dirs</i> or <i>array</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE								
Note	Not supported by 1-bit data buffers.								
See Also	\hCorBufferReadDots								

---

## CorBufferWriteElement

Write an element to a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferWriteElement</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>xPos</i> , UINT32 <i>yPos</i> , const void <i>*element</i> , UINT32 <i>size</i> );	
<b>Description</b>	Writes the value pointed to by <i>element</i> , to location ( <i>xPos</i> , <i>yPos</i> ) in the <i>buffer resource</i> .	
<b>Input</b>	<i>hBuffer</i>	Buffer resource handle
	<i>xPos</i>	Horizontal position of the element in the buffer
	<i>yPos</i>	Vertical position of the element in the buffer
	<i>element</i>	New value for the specified location (CORBUFFER_PRM_DATASIZE)
	<i>size</i>	Number of bytes to write corresponding to (CORBUFFER_PRM_DATASIZE bytes)
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>element</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE	
<b>Note</b>	For multiformat buffer types the order is B/G/R/M. For CORBUFFER_VAL_FORMAT_RGB888_MONO8 this is a 32-bit value; for CORBUFFER_VAL_FORMAT_RGB161616_MONO16 this is a 64-bit value.	
<b>See Also</b>	\hCorBufferReadElement	

---

## CorBufferWriteElementEx

Write an element to a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferWriteElementEx</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>xPos</i> , UINT32 <i>yPos</i> , CORDATA <i>element</i> );
<b>Description</b>	Writes the value in <i>element</i> , to location ( <i>xPos</i> , <i>yPos</i> ) in the buffer resource.
<b>Input</b>	<i>hBuffer</i> Buffer resource handle <i>xPos</i> Horizontal position of the element in the buffer <i>yPos</i> Vertical position of the element in the buffer <i>element</i> New value for the specified location. See Data Types for CORDATA definition.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE
<b>Note</b>	Multiformat buffers (for example, CORBUFFER_VAL_FORMAT_RGB888_MONO8 and CORBUFFER_VAL_FORMAT_RGB161616_MONO16) use the 'rgba' structure (red/green/blue/alpha) inside CORDATA values.
<b>See Also</b>	CorBufferReadElementEx

---

## CorBufferWriteLine

Write a set of linearly positioned elements into a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferWriteLine</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>x1</i> , UINT32 <i>y1</i> , UINT32 <i>x2</i> , UINT32 <i>y2</i> , UINT32 <i>nElements</i> , const void <i>array</i> , UINT32 <i>size</i> );
<b>Description</b>	Writes a line into a buffer, from element at position ( <i>x1</i> , <i>y1</i> ) to element at position ( <i>x2</i> , <i>y2</i> ). The new value of each line element is specified by the contents of <i>array</i> . If position ( <i>x2</i> , <i>y2</i> ) is outside the buffer boundary the line write ends. The number of elements written is stored in <i>nElements</i> , under all conditions.
<b>Input</b>	<i>hBuffer</i> Buffer resource handle <i>x1</i> Horizontal position of first element to be written <i>y1</i> Vertical position of first element to be written <i>x2</i> Horizontal position of last element to be written <i>y2</i> Vertical position of last element to be written <i>array</i> Array containing the elements to be written (MAX(ABS( <i>x2</i> - <i>x1</i> ), ABS( <i>y2</i> - <i>y1</i> ) + 1) × CORBUFFER_PRM_DATASIZE) <i>size</i> Number of bytes to write: (MAX( ABS( <i>x2</i> - <i>x1</i> ), ABS( <i>y2</i> - <i>y1</i> ) + 1) × CORBUFFER_PRM_DATASIZE bytes)
<b>Output</b>	<i>nElements</i> Number of elements written
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>nElements</i> or <i>array</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE
<b>Note</b>	For 1-bit data buffers, <i>offset</i> must be a multiple of 8.
<b>See Also</b>	CorBufferReadLine

---

## CorBufferWriteRect

Write a set of elements forming a rectangular area into a buffer resource

<b>Prototype</b>	CORSTATUS <b>CorBufferWriteRect</b> (CORBUFFER <i>hBuffer</i> , UINT32 <i>x</i> , UINT32 <i>y</i> , UINT32 <i>width</i> , UINT32 <i>height</i> , const void * <i>array</i> , UINT32 <i>size</i> );	
<b>Description</b>	Writes the contents of an array to a rectangular region into a buffer resource.	
<b>Input</b>	<i>hBuffer</i>	Buffer resource handle
	<i>x</i>	Horizontal offset in destination buffer
	<i>y</i>	Vertical offset in destination buffer
	<i>width</i>	Horizontal length of the rectangle (must be 2 or higher)
	<i>height</i>	Vertical length of the rectangle (must be 2 or higher)
	<i>array</i>	Array which contains the elements to be written ( <i>width</i> × <i>height</i> ×CORBUFFER_PRM_DATASIZE)
		For 1-bit data buffers, the <i>array</i> size should be (( <i>width</i> × <i>height</i> ) >> 3) bytes
	<i>size</i>	Size of transfer ( <i>width</i> × <i>height</i> ×CORBUFFER_PRM_DATASIZE bytes).
		For 1-bit data buffers, <i>size</i> should be (( <i>width</i> × <i>height</i> ) >> 3) bytes
<b>Output</b>	None	For 1-bit data buffers, <i>x</i> and <i>width</i> must be multiples of 8.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID_VALUE CORSTATUS_ARG_NULL ( if <i>array</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	\hCorBufferReadRect	

---

# Display Module

The Display Module is used to control the display device.

## Parameters

ID	Parameter	Attribute
0x00	CORDISPLAY_PRM_WIDTH	Read/Write
0x01	CORDISPLAY_PRM_HEIGHT	Read/Write
0x02	CORDISPLAY_PRM_REFRESH	Read/Write
0x03	CORDISPLAY_PRM_INTERLACED	Read/Write
0x04	Reserved	
0x05	Reserved	
0x06	Reserved	
0x07	Reserved	
0x08	Reserved	
0x09	Reserved	
0x0a	CORDISPLAY_PRM_PIXEL_DEPTH	Read/Write
0x0b	CORDISPLAY_PRM_LABEL	Read/Write
0x0c	CORDISPLAY_PRM_PIXEL_TYPE_OFFSCREEN	Read Only
0x0d	CORDISPLAY_PRM_PIXEL_TYPE_OVERLAY	Read Only
0x0e	CORDISPLAY_PRM_TYPE	Read Only
0x0f	CORDISPLAY_PRM_INDEX	Read Only
0x10	Reserved	
0x11	Reserved	
0x12	Reserved	
0x13	Reserved	

---

### CORDISPLAY\_PRM\_HEIGHT

**Description** Height (in lines) of the display surface.  
**Type** UINT32  
**Note** This parameter is read-only on the system display.

---

### CORDISPLAY\_PRM\_INDEX

**Description** The display resource index, as specified in the call to CorDisplayGetHandle.  
**Type** UINT32  
**See Also** CorDisplayGetHandle

---

### CORDISPLAY\_PRM\_INTERLACED

**Description** Specifies whether or not the display device is interlaced.  
**Type** UINT32  
**Values** TRUE  
FALSE  
**Note** This parameter is read-only on the system display.

---

## **CORDISPLAY\_PRM\_LABEL**

<b>Description</b>	The display device's string ID.
<b>Type</b>	CHAR[128]
<b>Values</b>	Zero-terminated array of characters with a fixed size of 128 bytes.
<b>Note</b>	This parameter is read-only.

---

## **CORDISPLAY\_PRM\_PIXEL\_DEPTH**

<b>Description</b>	The size of the display surface pixels (in bits).
<b>Type</b>	UINT32
<b>Note</b>	This parameter is read-only on the system display.

---

## **CORDISPLAY\_PRM\_PIXEL\_TYPE\_OFFSCREEN**

<b>Description</b>	Displays the pixel formats that the display supports for off-screen surfaces.
<b>Type</b>	UINT32[32]
<b>Values</b>	Zero-terminated array of UINT32 values with a fixed size of 32 dwords.
<b>See Also</b>	CorBufferNew and Data Formats

---

## **CORDISPLAY\_PRM\_PIXEL\_TYPE\_OVERLAY**

<b>Description</b>	Displays the pixel formats that the display supports for overlay surface.
<b>Type</b>	UINT32[32]
<b>Values</b>	Zero-terminated array of UINT32 values with a fixed size of 32 dwords.
<b>Note</b>	The available pixel formats may not be correctly detected if there is another application using the display adapter's overlay hardware at the same time.
<b>See Also</b>	CorBufferNew and Data Formats

---

## **CORDISPLAY\_PRM\_REFRESH**

<b>Description</b>	Display device's refresh rate.
<b>Type</b>	UINT32
<b>Note</b>	This parameter is read-only on the system display.

---

## **CORDISPLAY\_PRM\_TYPE**

<b>Description</b>	The display type.
<b>Type</b>	UINT32
<b>Values</b>	<p>CORDISPLAY_VAL_TYPE_SYSTEM A display under the control of the primary Windows display driver. This is the same display that normally displays the Windows desktop. In Sapera, it belongs to the System server.</p> <p>CORDISPLAY_VAL_TYPE_DUPLICATE A secondary display that shows the same contents as the primary Windows VGA display..</p> <p>CORDISPLAY_VAL_TYPE_EXTENDED A secondary display that extends the desktop from the primary Windows VGA display.</p> <p>CORDISPLAY_VAL_TYPE_INDEPENDENT A secondary display that is completely independent from the primary Windows VGA display.</p>
<b>Note</b>	An independent display has limited support in Sapera. Most capabilities and parameters are not available and certain functions may not be implemented.



---

## **CORDISPLAY\_PRM\_WIDTH**

**Description** Width (in pixels) of the display surface.

**Type** UINT32

**Note** This parameter is read-only on the system display.

## Functions

Function	Description
CorDisplayGetCap	<i>Gets display capability value from a display device</i>
CorDisplayGetCount	<i>Gets the number of display devices on a server</i>
CorDisplayGetDC	<i>Gets the Windows device context corresponding to the entire screen</i>
CorDisplayGetHandle	<i>Gets an handle to a display device</i>
CorDisplayGetPrm	<i>Gets display parameter value from a display device</i>
CorDisplayRelease	<i>Releases handle to a display device</i>
CorDisplayReleaseDC	<i>Releases the Windows device context corresponding to the entire screen</i>
CorDisplayRelease	<i>Resets a display device</i>
CorDisplayResetModule	<i>Resets the resources associated with the server's display device(s)</i>
CorDisplaySetPrm	<i>Sets a simple display parameter of a display device</i>
CorDisplaySetPrmEx	<i>Sets a complex display parameter of a display device</i>

---

### CorDisplayGetCap

Get display capability value from a display device

**Prototype**      `CORSTATUS CorDisplayGetCap(CORDISPLAY hDisplay, UINT32 cap, void *value);`

**Description**    Gets a display capability value from a display device.

**Input**            *hDisplay*    Display resource handle  
                    *cap*        Display device capability requested

**Output**          *value*        Value of the capability

**Return Value**   `CORSTATUS_OK`  
                    `CORSTATUS_ARG_NULL` ( if *value* is NULL)  
                    `CORSTATUS_CAP_INVALID`  
                    `CORSTATUS_CAP_NOT_AVAILABLE`  
                    `CORSTATUS_INVALID_HANDLE`

---

### CorDisplayGetCount

Get the number of display devices on a server

**Prototype**      `CORSTATUS CorDisplayGetCount(CORSERVER hServer, UINT32 *count);`

**Description**    Gets the number of display devices on a server.

**Input**            *hServer*    Server handle  
**Output**          *count*        Number of display devices

**Return Value**   `CORSTATUS_OK`  
                    `CORSTATUS_ARG_NULL` ( if *count* is NULL)  
                    `CORSTATUS_INVALID_HANDLE`

**Note**            The content of *count* is 0 when there is no display device available.

---

## CorDisplayGetDC

Get Windows device context for a display device

<b>Prototype</b>	CORSTATUS <b>CorDisplayGetDC</b> (CORDISPLAY <i>hDisplay</i> , void * <i>pDC</i> );	
<b>Description</b>	Gets the Windows device context corresponding to the entire screen for the specified display device	
<b>Input</b>	<i>hDisplay</i>	Display resource handle
<b>Output</b>	<i>pDC</i>	The device context
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>pDC</i> is NULL) CORSTATUS_INVALID_HANDLE	

---

## CorDisplayGetHandle

Get an handle to a display device

<b>Prototype</b>	CORSTATUS <b>CorDisplayGetHandle</b> (CORSERVER <i>hServer</i> , UINT32 <i>index</i> , CORDISPLAY * <i>hDisplay</i> );	
<b>Description</b>	Gets an handle to a display device.	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>index</i>	Specifies which display device to select. Valid values are in the range [0... <i>count</i> -1], where <i>count</i> is the value returned by CorDisplayGetCount.
<b>Output</b>	<i>hDisplay</i>	Display resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>hDisplay</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_INVALID_HANDLE CORSTATUS_RESOURCE_IN_USE	
<b>See Also</b>	CorDisplayGetCount and CorDisplayRelease	

---

## CorDisplayGetPrm

Get display parameter value from a display device

<b>Prototype</b>	CORSTATUS <b>CorDisplayGetParam</b> (CORDISPLAY <i>hDisplay</i> , UINT32 <i>prm</i> , void * <i>value</i> );	
<b>Description</b>	Gets parameter value from a display device.	
<b>Input</b>	<i>hDisplay</i>	Display resource handle
	<i>prm</i>	Display parameter requested
<b>Output</b>	<i>value</i>	Current value of the parameter
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID CORSTATUS_PRM_NOT_AVAILABLE	
<b>See Also</b>	CorDisplaySetPrm	

---

## CorDisplayRelease

Release handle to a display device

<b>Prototype</b>	CORSTATUS <b>CorDisplayRelease</b> (CORDISPLAY <i>hDisplay</i> );
<b>Description</b>	Releases handle to display device
<b>Input</b>	<i>hDisplay</i> Display resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorDisplayGetHandle

---

## CorDisplayReleaseDC

Release Windows device context for a display device

<b>Prototype</b>	CORSTATUS <b>CorDisplayReleaseDC</b> (CORDISPLAY <i>hDisplay</i> );
<b>Description</b>	Releases the Windows device context corresponding to the entire screen for the specified display device
<b>Input</b>	<i>hDisplay</i> Display resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE

---

## CorDisplayReset

Reset a display device

<b>Prototype</b>	CORSTATUS <b>CorDisplayReset</b> (CORDISPLAY <i>hDisplay</i> );
<b>Description</b>	Resets a display device. Restores the default values of display parameters of the specified display device.
<b>Input</b>	<i>hDisplay</i> Display resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorDisplayRelease

---

## CorDisplayResetModule

Reset the resources associated with the server's display device(s)

<b>Prototype</b>	CORSTATUS <b>CorDisplayResetModule</b> (CORSERVER <i>hServer</i> );
<b>Description</b>	Resets the resources associated with the server's display device(s). Releases all resources (handle, memory) currently allocated. Make certain no other application is currently using any display device resource. This function should be used with caution.
<b>Input</b>	<i>hServer</i> Server handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE

---

## CorDisplaySetPrm

Set a simple display parameter of a display device

<b>Prototype</b>	CORSTATUS <b>CorDisplaySetPrm</b> (CORDISPLAY <i>hDisplay</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );
<b>Description</b>	Sets a simple display parameter of a display device
<b>Input</b>	<i>hDisplay</i> Display resource handle <i>prm</i> Display parameter to set <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_CAP_NOT_AVAILABLE CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID CORSTATUS_PRM_INVALID_VALUE CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_PRM_READ_ONLY
<b>Note</b>	A simple parameter fits inside an UINT32. If the parameter is complex, use CorDisplaySetPrmEx.
<b>See Also</b>	CorDisplayGetPrm and CorDisplaySetPrmEx

---

## CorDisplaySetPrmEx

Set a complex display parameter of a display device

<b>Prototype</b>	CORSTATUS <b>CorDisplaySetPrmEx</b> (CORDISPLAY <i>hDisplay</i> , UINT32 <i>prm</i> , const void * <i>value</i> );
<b>Description</b>	Sets a complex display parameter of a display device
<b>Input</b>	<i>hDisplay</i> Display resource handle <i>prm</i> Display parameter to set <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>value</i> is NULL) CORSTATUS_ARG_OUT_OF_RANGE CORSTATUS_CAP_NOT_AVAILABLE CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID CORSTATUS_PRM_INVALID_VALUE CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_PRM_READ_ONLY
<b>Note</b>	A complex parameter is one whose size is greater than an UINT32. If the parameter size is UINT32, use either CorDisplaySetPrm or CorDisplaySetPrmEx.
<b>See Also</b>	CorDisplayGetPrm and CorDisplaySetPrm

---

# File Module

The File Module functions create, read, write, load, and save files of a given size and format.

## Parameters

ID	Parameter	Attribute
0x00	CORFILE_PRM_FORMAT	Read Only
0x01	CORFILE_PRM_DATAFORMAT	Read Only
0x02	CORFILE_PRM_DATASIZE	Read Only
0x03	CORFILE_PRM_DATADEPTH	Read Only
0x04	CORFILE_PRM_XMIN	Read Only
0x05	CORFILE_PRM_YMIN	Read Only
0x06	CORFILE_PRM_WIDTH	Read Only
0x07	CORFILE_PRM_HEIGHT	Read Only
0x08	CORFILE_PRM_MEM_WIDTH	Read Only
0x09	CORFILE_PRM_MEM_HEIGHT	Read Only
0x0a	CORFILE_PRM_SIGNED	Read Only
0x0b	CORFILE_PRM_COMPRESSION	Read Only
0x0c	CORFILE_PRM_LUT	Read/Write
0x0d	CORFILE_PRM_SIZE	Read/Write
0x0e	CORFILE_PRM_NUM_FRAMES	Read Only
0x0f	CORFILE_PRM_FRAMERATE	Read Only
0x010	CORFILE_PRM_NAME	Read Only
0x011	CORFILE_PRM_ACCESS	Read Only

---

### CORFILE\_PRM\_ACCESS

<b>Description</b>	File access. Determines the type of reading or writing operations permitted.
<b>Type</b>	UINT32
<b>Values</b>	CORFILE__VAL_ACCESS_RDONLY CORFILE__VAL_ACCESS_RDWR CORFILE__VAL_ACCESS_WRONLY

---

### CORFILE\_PRM\_COMPRESSION

<b>Description</b>	File compression type
<b>Type</b>	UINT32
<b>Values</b>	CORFILE_VAL_COMPRESSION_NONE CORFILE_VAL_COMPRESSION_RLE CORFILE_VAL_COMPRESSION_LZW CORFILE_VAL_COMPRESSION_JPEG CORFILE_VAL_COMPRESSION_JPEG_2000 CORFILE_VAL_COMPRESSION_I263 (Intel H.263) CORFILE_VAL_COMPRESSION_CVID (Radius Cinepack codec) CORFILE_VAL_COMPRESSION_IV32 (Intel Indeo 3.2) CORFILE_VAL_COMPRESSION_MSVC (Microsoft Video 1) CORFILE_VAL_COMPRESSION_IV50 (Intel Indeo 5.0) CORFILE_VAL_COMPRESSION_UNKNOWN

---

## CORFILE\_PRM\_DATADEPTH

<b>Description</b>	Number of bits per File element.
<b>Type</b>	UINT32

---

## CORFILE\_PRM\_DATAFORMAT

<b>Description</b>	File data format. Determines the buffer format corresponding to a single file element's type.
<b>Type</b>	UINT32
<b>Values</b>	For a detailed description of the values, see Data Formats

---

## CORFILE\_PRM\_DATASIZE

<b>Description</b>	Size of one File element (in bytes).
<b>Type</b>	UINT32
<b>Values</b>	This value will depend on the File data format.

---

## CORFILE\_PRM\_FORMAT

<b>Description</b>	File format.
<b>Type</b>	UINT32
<b>Values</b>	Windows bitmap files : CORFILE_VAL_FORMAT_BMP
	TIFF files: CORFILE_VAL_FORMAT_TIF
	CORFILE_VAL_FORMAT_TIFF
	Teledyne DALSA raw data files: CORFILE_VAL_FORMAT_CRC
	Raw data files: CORFILE_VAL_FORMAT_RAW
	JPEG files: CORFILE_VAL_FORMAT_JPG
	CORFILE_VAL_FORMAT_JPEG
	JPEG 2000 files: CORFILE_VAL_FORMAT_JPEG_2000
	AVI files: CORFILE_VAL_FORMAT_AVI
	Others: CORFILE_VAL_FORMAT_UNKNOWN

---

## CORFILE\_PRM\_FRAMERATE

<b>Description</b>	Frame rate (number of images per second) of a specified image sequence.
<b>Type</b>	FLOAT

---

## CORFILE\_PRM\_HEIGHT

<b>Description</b>	Height of the File's region of interest (ROI).
<b>Type</b>	UINT32
<b>Values</b>	Range within [0...MEM_HEIGHT].

---

## CORFILE\_PRM\_MEM\_HEIGHT

<b>Description</b>	File's height. Determines the number of rows in the File.
<b>Type</b>	UINT32

---

**CORFILE\_PRM\_LUT**

<b>Description</b>	File Lookup table if any
<b>Type</b>	PUINT8
<b>Values</b>	Array of 256, 3x8 bit, RGB values (CORDATA_FORMAT_RGB888)

---

**CORFILE\_PRM\_MEM\_WIDTH**

<b>Description</b>	File's width. Determines the number of columns in the File.
<b>Type</b>	UINT32

---

**CORFILE\_PRM\_NAME**

<b>Description</b>	The File name.
<b>Type</b>	CHAR[128]
<b>Values</b>	Null-terminated array of characters with a fixed size of 128 bytes.

---

**CORFILE\_PRM\_NUM\_FRAMES**

<b>Description</b>	Determines the number of image buffers in the File.
<b>Type</b>	UINT32

---

**CORFILE\_PRM\_SIGNED**

<b>Description</b>	Sign of the File elements.
<b>Type</b>	UINT32
<b>Values</b>	CORDATA_FORMAT_UNSIGNED CORDATA_FORMAT_SIGNED

---

**CORFILE\_PRM\_SIZE**

<b>Description</b>	File's size. Determines the size in bytes of the specified File.
<b>Type</b>	UINT32

---

**CORFILE\_PRM\_WIDTH**

<b>Description</b>	Width of the File's region of interest (ROI).
<b>Type</b>	UINT32
<b>Values</b>	Range within [0...MEM_WIDTH].

---

**CORFILE\_PRM\_XMIN**

<b>Description</b>	Origin of the File's region of interest (ROI) along the X axis.
<b>Type</b>	UINT32
<b>Values</b>	Range within [0...MEM_WIDTH-1].

---

**CORFILE\_PRM\_YMIN**

<b>Description</b>	Origin of the File's region of interest (ROI) along the Y axis.
<b>Type</b>	UINT32
<b>Values</b>	Range within [0...MEM_HEIGHT-1].



## Functions

Function	Description
CorFileAddSequence	<i>Adds a sequence of image buffers to a File</i>
CorFileCopy	<i>Copies the content of a File resource into another File resource</i>
CorFileFree	<i>Frees handle to a File resource</i>
CorFileGetPrm	<i>Gets File parameter value from a File resource</i>
CorFileLoad	<i>Loads an image from a File into a Buffer resource</i>
CorFileLoadSequence	<i>Loads a sequence of images from a file into separate buffers</i>
CorFileNew	<i>Creates in a specified server's memory a new File resource</i>
CorFileRead	<i>Reads a series of elements from a File resource</i>
CorFileReadEx	<i>Reads a series of elements from a File resource</i>
CorFileSave	<i>Saves to a File the contents of a Buffer resource</i>
CorFileSaveSequence	<i>Saves a sequence of image buffers to a File</i>
CorFileSeek	<i>Moves file pointer to a specified location</i>
CorFileSetPrm	<i>Sets a simple File parameter of a File resource</i>
CorFileSetPrmEx	<i>Sets a complex File parameter of a File resource</i>
CorFileWrite	<i>Writes a series of elements into a File resource</i>

---

## CorFileAddSequence

Add a sequence of image buffers to a File

**Prototype**      `CORSTATUS CorFileAddSequence(CORFILE hFile, CORHANDLE *hSrc, UINT32 nFrames,  
FLOAT frameRate, PCSTR options);`

**Description**    Add to a File the content of a sequence of image Buffers.

**Input**

<i>hFile</i>	File resource handle
<i>hSrc</i>	Array of Buffer resource handles
<i>nFrames</i>	Number of image buffers within the sequence
<i>frameRate</i>	Playback rate in number of images per second for the sequence.
<i>options</i>	Argument-parsing string (may be set to NULL for automatic detection of the file format). The case insensitive switches available are listed below and may be used to form the expression: <b>-format</b> [value] or <b>-f</b> [value] The file format value supported is: <b>avi</b> or <b>corfile_format_avi</b> . example: <b>-f</b> CORFILE_VAL_FORMAT_AVI <b>-compression</b> [value] or <b>-c</b> [value] The codec supported for compression is: none or corfile_val_compression_none (No compression)

**Output**          None

**Return Value**   `CORSTATUS_OK`  
`CORSTATUS_FILE_OPTIONS_ERROR`  
`CORSTATUS_FILE_WRITE_ERROR`  
`CORSTATUS_FILE_OPEN_ERROR`  
`CORSTATUS_FILE_CREATE_ERROR`  
`CORSTATUS_FILE_READ_ERROR`  
`CORSTATUS_INCOMPATIBLE_FORMAT`  
`CORSTATUS_FILE_FORMAT_UNKNOWN`  
`CORSTATUS_INVALID_HANDLE`  
`CORSTATUS_NO_MEMORY`

**Note**            The only format currently supported is AVI (Audio Video Interleave). The buffers within the sequence must be the same data format as the images stored in the AVI file. The File should be opened in read/write mode.  
For the list of input buffer formats supported by CorFileAddSequence see section Buffer file formats.

**See Also**        CorFileLoadSequence, CorFileSaveSequence and CorFileGetPrm

---

## CorFileCopy

Copies contents of a File resource into another File resource

**Prototype**      `CORSTATUS CorFileCopy(CORFILE hSrc, CORFILE hDst);`

**Description**    Copies the contents of the source file into the destination buffer.

**Input**

<i>hSrc</i>	File resource handle (source)
<i>hDst</i>	File resource handle (destination)

**Output**          None

**Return Value**   `CORSTATUS_OK`  
`CORSTATUS_ARG_INVALID`  
`CORSTATUS_ARG_OUT_OF_RANGE`  
`CORSTATUS_INVALID_HANDLE`  
`CORSTATUS_INVALID_HANDLE`  
`CORSTATUS_INVALID_HANDLE`  
`CORSTATUS_INVALID_HANDLE`

**Note**            The source and destination files may be located on different servers

---

## CorFileFree

Frees handle to a File resource

**Prototype**      `CORSTATUS CorFileFree(CORFILE hFile);`  
**Description**    Frees handle to a File resource.  
**Input**            *hFile*      File resource handle  
**Output**           None  
**Return Value**   `CORSTATUS_OK`  
                    `CORSTATUS_FILE_CLOSE_ERROR`  
                    `CORSTATUS_INVALID_HANDLE`  
                    `CORSTATUS_NOT_AVAILABLE`

---

## CorFileGetPrm

Gets File parameter value from a File resource

**Prototype**      `CORSTATUS CorFileGetPrm(CORFILE hFile, UINT32 prm, void *value);`  
**Description**    Gets File parameter value from a File resource.  
**Input**            *hFile*      File resource handle  
                    *prm*      File parameter requested  
**Output**           *value*      Current value of the parameter  
**Return Value**   `CORSTATUS_OK`  
                    `CORSTATUS_ARG_NULL` ( if *value* is NULL)  
                    `CORSTATUS_FILE_FORMAT_UNKNOWN`  
                    `CORSTATUS_FILE_WRITE_ONLY`  
                    `CORSTATUS_INVALID_HANDLE`  
                    `CORSTATUS_PRM_INVALID`  
                    `CORSTATUS_PRM_NOT_AVAILABLE`  
**See Also**        `CorFileSetPrm` and `CorFileSetPrmEx`

---

## CorFileLoad

Loads an image from a file into a Buffer resource

**Prototype**      `CORSTATUS CorFileLoad(CORFILE hFile, CORHANDLE hDst, PCSTR options);`

**Description**      Load an image from a File into a Buffer resource. Currently, the following file formats are supported:

TIFF    Tag Image File Format.  
BMP    Microsoft Windows Bitmap Format.  
CRC    Teledyne DALSA raw data file format.  
RAW    Raw data file format.  
JPEG    Jpeg file format.

For a detailed description of some of these file formats (BMP, CRC, and RAW), refer to the section “Buffer File Formats” of the *Appendix B: File Formats*.

**Input**

*hFile*            File resource handle

*hDst*            Buffer resource handle

*options*          Argument-parsing string (may be set to NULL for automatic detection of the file format). The case insensitive switches available are listed below and may be used to form the argument string:

**-format** [value] or **-f** [value] - for file format.

The file format value supported is one of the following:

**raw** or **corfile\_format\_raw** - for raw data files.

**Bmp** or **corfile\_format\_bmp** - for windows bitmap files.

**tif**, **tiff**, **corfile\_format\_tif** or **corfile\_format\_tiff** - for TIF files.

**jpg**, **jpeg**, **corfile\_format\_jpg** or **corfile\_format\_jpeg** - for JPEG files.

**jp2**, **jpeg\_2000**, or **corfile\_format\_jpg\_2000** – for JPEG 2000 files.

**crc** or **corfile\_format\_crc** - for Teledyne DALSA raw data files.

**auto** or **corfile\_format\_unknown** - for automatic detection of image format.

example: **-format AUTO**

The following switches are required only for raw data files:

**-width** [value] or **-w** [value], example: **-width 512**

**-height** [value] or **-h** [value], example: **-h 512**

**-offset** [value] or **-o** [value], example: **-offset 64**

The following switch is used for JPEG 2000 files only:

**-component** [value] or **-cmp** [value]

That switch determines which component (red, green, or blue) of a color JPEG 2000 file will be loaded when *hDst* is monochrome. Value is 0 for red, 1 for green, and 2 for blue.

**Output**            None

**Return Value**    `CORSTATUS_OK`  
`CORSTATUS_ARG_INVALID_VALUE`  
`CORSTATUS_FILE_OPEN_ERROR`  
`CORSTATUS_FILE_OPTIONS_ERROR`  
`CORSTATUS_FILE_FORMAT_UNKNOWN`  
`CORSTATUS_FILE_READ_ERROR`  
`CORSTATUS_FILE_WRITE_ONLY`  
`CORSTATUS_INCOMPATIBLE_FORMAT`  
`CORSTATUS_INVALID_HANDLE`

**Note**            If the Buffer isn't large enough, the image is clipped to Buffer's size. The Buffer must be the same format as the image stored in the file (use `CorFileGetPrm` to get the file data format).

**See Also**        `CorFileSave` and `CorFileGetPrm`

---

## CorFileLoadSequence

Loads a sequence of images from a File into separate Buffers

<b>Prototype</b>	CORSTATUS <b>CorFileLoadSequence</b> (CORFILE <i>hFile</i> , CORHANDLE * <i>hDst</i> , UINT32 <i>nFrames</i> , UINT32 <i>startFrame</i> , PCSTR <i>options</i> );	
<b>Description</b>	Loads a sequence of images from a File into separate Buffers.	
<b>Input</b>	<i>hFile</i>	File resource handle
	<i>hDst</i>	Array of Buffer resource handles
	<i>nFrames</i>	Number of Buffers within the array
	<i>startFrame</i>	Index of the first image of the sequence to load
	<i>options</i>	See CorFileAddSequence
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_FILE_OPTIONS_ERROR	
	CORSTATUS_FILE_READ_ERROR	
	CORSTATUS_INVALID_HANDLE	
	CORSTATUS_NO_MEMORY	
	CORSTATUS_INCOMPATIBLE_FORMAT	
<b>Note</b>	CORSTATUS_FILE_FORMAT_UNKNOWN	
	If a specified Buffer is not large enough, the corresponding image is clipped to the Buffer's size. The Buffers must be the same format as the images stored in the file (use CorFileGetPrm to get the file data format).	
<b>See Also</b>	CorFileAddSequence and CorFileSaveSequence	

---

## CorFileNew

Create in a specified server's memory a new File resource

<b>Prototype</b>	CORSTATUS <b>CorFileNew</b> (CORSERVER <i>hServer</i> , const char <i>filename</i> [], const char <i>mode</i> [], CORFILE * <i>hFile</i> );	
<b>Description</b>	Creates in a specified server's memory a new File resource.	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>filename</i>	File name
	<i>mode</i>	Specified open mode, as follows:
		"r", "rb" for read only files (the file must exist). "w", "wb" for write only files (if the file exists, its content is destroyed). "r+" for both reading and writing (the file must exist).
<b>Output</b>	<i>hFile</i>	File resource handle
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>hFile</i> or <i>filename</i> or <i>mode</i> is NULL)	
	CORSTATUS_FILE_CREATE_ERROR	
	CORSTATUS_FILE_OPEN_ERROR	
	CORSTATUS_FILE_OPEN_MODE_INVALID	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CORSTATUS_NO_MEMORY	
	CorFileFree	

---

## CorFileRead

Read a series of elements from a File resource

<b>Prototype</b>	CORSTATUS <b>CorFileRead</b> (CORFILE <i>hFILE</i> , void * <i>array</i> , UINT32 <i>nItem</i> , UINT32 <i>itemSize</i> );	
<b>Description</b>	Reads a consecutive series of elements from the specified File resource and copies them into a one-dimensional destination array.	
<b>Input</b>	<i>hFile</i>	File resource handle
	<i>nItem</i>	Number of elements to read
	<i>itemSize</i>	Size of an element (bytes)
<b>Output</b>	<i>array</i>	Array to accommodate the requested number of elements ( <i>nItem</i> × <i>itemSize</i> )
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>array</i> is NULL)	
	CORSTATUS_FILE_READ_ERROR	
	CORSTATUS_FILE_WRITE_ONLY	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorFileReadEx and CorFileWrite	

---

## CorFileReadEx

Reads a series of elements from a File resource

<b>Prototype</b>	CORSTATUS <b>CorFileReadEx</b> (CORFILE <i>hFILE</i> , void * <i>array</i> , UINT32 <i>nItem</i> , UINT32 <i>itemSize</i> , UINT32 * <i>nRead</i> );	
<b>Description</b>	Reads a consecutive series of elements from the specified File resource and copies them into a one-dimensional destination array.	
<b>Input</b>	<i>hFile</i>	File resource handle
	<i>nItem</i>	Number of elements to read
	<i>itemSize</i>	Size of an element (bytes)
<b>Output</b>	<i>array</i>	Array to accommodate the requested number of elements ( <i>nItem</i> × <i>itemSize</i> )
	<i>nRead</i>	Number of bytes read
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>array</i> is NULL)	
	CORSTATUS_FILE_READ_ERROR	
	CORSTATUS_FILE_WRITE_ONLY	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorFileRead and CorFileWrite	

---

## CorFileSave

Save to a File the content of a Buffer resource

**Prototype**      `CORSTATUS CorFileSave(CORFILE hFile, CORHANDLE hSrc, PCSTR options);`

**Description**      Saves to a File the content of a Buffer resource.

Current supported file formats are BMP, TIFF, JPEG, raw Teledyne DALSA file and RAW data files.

For the list of input buffer formats supported by CorFileSave see section Buffer file formats.

**Input**

<i>hFile</i>	File resource handle
<i>hSrc</i>	Buffer resource handle
<i>options</i>	Argument-parsing string. The case insensitive switches available are listed below and may be used to form the expression:

**-format** [value] or **-f** [value]

The file format value supported is one of the following:

**raw** or **corfile\_format\_raw**.

**bmp** or **corfile\_format\_bmp**.

**tif**, **tiff**, **corfile\_format\_tif** or **corfile\_format\_tiff**.

**crc** or **corfile\_format\_crc**.

**jpg**, **jpeg**, **corfile\_format\_jpg** or **corfile\_format\_jpeg**.

**jp2**, **jpeg\_2000** or **corfile\_format\_jpg**.

example: **-f** tif

**-quality** [value] or **-q** [value]

This option is used to set the jpeg compression level. The quality value is an integer within [1, 100] interval. example: **-q** 90. When saving a JPEG 2000 file, if the quality value is 100, a lossless compression method is used. When quality is not specified, default value is 0 to minimize file size.

**-compression** [value] or **-c** [value]

This options is used to set the TIFF compression algorithm.

The following values are supported:

**none** or **corfile\_val\_compression\_none**

**rle** or **corfile\_val\_compression\_rle**

**lzw** or **corfile\_val\_compression\_lzw**

**jpg**, **jpeg** or **corfile\_val\_compression\_jpg**

It should be noted that the Lempel-Ziv-Welch algorithm (used when value **lzw** is set) has been enabled in Sapera only once the related patents have expired.

**Output**      None

**Return Value**      `CORSTATUS_OK`  
`CORSTATUS_ARG_NULL` ( if *options* is NULL)  
`CORSTATUS_FILE_OPTIONS_ERROR`  
`CORSTATUS_FILE_WRITE_ERROR`  
`CORSTATUS_INVALID_HANDLE`  
`CORSTATUS_NO_MEMORY`  
`CORSTATUS_INCOMPATIBLE_FORMAT`  
`CORSTATUS_FILE_FORMAT_UNKNOWN`

**Note**      Multiformat buffers (for example, `CORBUFFER_VAL_FORMAT_RGB888_MONO8` and `CORBUFFER_VAL_FORMAT_RGB161616_MONO16`) only support saving as CRC and RAW formats.

**See Also**      `CorFileLoad`

---

## CorFileSaveSequence

Saves a sequence of image buffers to a File

<b>Prototype</b>	CORSTATUS <b>CorFileSaveSequence</b> (CORFILE <i>hFile</i> , CORHANDLE * <i>hSrc</i> , UINT32 <i>nFrames</i> , FLOAT <i>frameRate</i> , PCSTR <i>options</i> );		
<b>Description</b>	Saves a sequence of image buffers to a File.		
<b>Input</b>	<i>hFile</i>	File resource handle	
	<i>hSrc</i>	Array of Buffer resource handles	
	<i>nFrames</i>	Number of Buffers within the array	
	<i>options</i>	See <b>CorFileAddSequence</b>	
<b>Output</b>	None		
<b>Return Value</b>	CORSTATUS_OK		
	CORSTATUS_ARG_NULL ( if <i>options</i> is NULL)		
	CORSTATUS_FILE_OPTIONS_ERROR		
	CORSTATUS_FILE_WRITE_ERROR		
	CORSTATUS_INVALID_HANDLE		
	CORSTATUS_NO_MEMORY		
	CORSTATUS_INCOMPATIBLE_FORMAT		
	CORSTATUS_FILE_FORMAT_UNKNOWNCORSTATUS_FORMAT_UNKNOWN		
<b>Note</b>	For the list of input buffer formats supported by CorFileSaveSequence see section Buffer Data Formats Supported as Input by FileSave Functions.		
<b>See Also</b>	CorFileAddSequence and CorFileLoadSequence		

---

## CorFileSeek

Move file pointer to a specified location

<b>Prototype</b>	CORSTATUS <b>CorFileSeek</b> (CORFILE <i>hFile</i> , INT32 <i>offset</i> , INT32 <i>origin</i> );		
<b>Description</b>	Move file pointer to a specified location		
<b>Input</b>	<i>hFile</i>	File resource handle	
	<i>offset</i>	Number of bytes from origin	
	<i>origin</i>	Initial position	
		Beginning of file:	CORFILE_BEGIN
		Current position:	CORFILE_CURRENT
<b>Output</b>	None		
	End of file: CORFILE_END		
<b>Return Value</b>	CORSTATUS_OK		
	CORSTATUS_ARG_INVALID_VALUE		
	CORSTATUS_FILE_SEEK_ERROR		
	CORSTATUS_INVALID_HANDLE		



---

## CorFileSetPrm

Set a simple File parameter of a File resource

<b>Prototype</b>	CORSTATUS <b>CorFileSetPrm</b> (CORFILE <i>hFile</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );
<b>Description</b>	Sets a simple File parameter of a File resource
<b>Input</b>	<i>hFile</i> File resource handle <i>prm</i> File parameter to set <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID_VALUE CORSTATUS_FILE_READ_ONLY CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_PRM_READ_ONLY
<b>Note</b>	A simple parameter fits inside an UINT32. If the parameter is complex, use CorFileSetPrmEx.
<b>See Also</b>	CorFileGetPrm and CorFileSetPrmEx

---

## CorFileSetPrmEx

Set a complex File parameter of a File resource

<b>Prototype</b>	CORSTATUS <b>CorFileSetPrmEx</b> (CORFILE <i>hFile</i> , UINT32 <i>prm</i> , const void * <i>value</i> );
<b>Description</b>	Sets a complex File parameter of a File resource.
<b>Input</b>	<i>hFile</i> File resource handle <i>prm</i> File parameter to set <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID_VALUE CORSTATUS_ARG_NULL ( if <i>value</i> is NULL) CORSTATUS_FILE_FORMAT_UNKNOWN CORSTATUS_FILE_READ_ONLY CORSTATUS_INVALID_HANDLE CORSTATUS_PRM_INVALID CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_PRM_READ_ONLY
<b>Note</b>	A complex parameter is one whose size is greater than an UINT32. If the parameter size is UINT32, use either CorFileSetPrm or CorFileSetPrmEx. Only the LUT parameter (CORFILE_PRM_LUT) can be set in a File resource, the other parameters are Read Only.
<b>See Also</b>	CorFileGetPrm and CorFileSetPrmEx

---

## CorFileWrite

Write a series of elements to a File resource

<b>Prototype</b>	CORSTATUS <b>CorFileWrite</b> (CORFILE <i>hFile</i> , const void * <i>array</i> , UINT32 <i>nItem</i> , UINT32 <i>itemSize</i> );		
<b>Description</b>	Writes a series of elements from an one-dimensional source array to a File resource.		
<b>Input</b>	<i>hFile</i>	File resource handle	
	<i>array</i>	Array which contains the elements to be written	
	<i>nItem</i>	Number of elements to write	
	<i>itemSize</i>	Size of an element in bytes	
<b>Output</b>	None		
<b>Return Value</b>	CORSTATUS_OK		
	CORSTATUS_ARG_NULL ( if <i>array</i> is NULL)		
	CORSTATUS_FILE_READ_ONLY		
	CORSTATUS_FILE_WRITE_ERROR		
	CORSTATUS_INVALID_HANDLE		
<b>See Also</b>	CorFileRead		

---

## I/O Module

The General I/O Module is used to control a block of general inputs and outputs (I/O signal pins). A block of general inputs and outputs is a group of I/Os which can be read and/or written all at once. For a TTL level type I/O, its state is considered **on** or **active** if the measured voltage on the I/O is 5V (typical).

### Definitions

This section describes the methods related to the I/O module.

---

#### CORGIO\_VAL\_INPUT\_CONTROL\_METHOD\_1

**Numerical Value** 0x00000001 (Hardware Latch)

**Description** This method latches the value of the input I/O pins when there is a signal pulse on the input control pin.

---

#### CORGIO\_VAL\_OUTPUT\_CONTROL\_METHOD\_1

**Numerical Value** 0x00000001 (Auto latch)

**Description** This method generates a pulse on the output control pin each time a new value is written to it by the user.

---

#### CORGIO\_VAL\_OUTPUT\_CONTROL\_METHOD\_2

**Numerical Value** 0x00000001 (Manual latch)

**Description** This method allows the function CorGpioSetOutputControlState to control the state of the output control pin.

### Capabilities

ID	Capability
0x00	CORGIO_CAP_IO_COUNT
0x01	CORGIO_CAP_DIR_INPUT
0x02	CORGIO_CAP_DIR_OUTPUT
0x03	CORGIO_CAP_DIR_TRISTATE
0x04	CORGIO_CAP_INPUT_CONTROL_METHOD
0x05	CORGIO_CAP_INPUT_CONTROL_POLARITY
0x06	CORGIO_CAP_OUTPUT_CONTROL_METHOD
0x07	CORGIO_CAP_OUTPUT_CONTROL_POLARITY
0x08	CORGIO_CAP_OUTPUT_TYPE
0x09	CORGIO_CAP_INPUT_LEVEL
0x0a	CORGIO_CAP_CONNECTOR
0x0b	CORGIO_CAP_EVENT_TYPE
0x0c	CORGIO_CAP_FAULT_DETECT
0x0d	CORGIO_CAP_POWER_GOOD
0x0e	CORGIO_CAP_READ_ONLY

---

#### CORGIO\_CAP\_CONNECTOR

**Description** Specifies which connectors can be use for this I/O device

**Type** UINT32

**Values** See CORGIO\_PRM\_CONNECTOR.

---

## **CORGIO\_CAP\_DIR\_INPUT**

<b>Description</b>	Specifies which I/O can be set as inputs.
<b>Type</b>	UINT32
<b>Values</b>	If bit 'n' is 1, then the associated I/O can be an input.

---

## **CORGIO\_CAP\_DIR\_OUTPUT**

<b>Description</b>	Specifies which I/O can be set as outputs.
<b>Type</b>	UINT32
<b>Values</b>	If bit 'n' is 1, then the associated I/O can be an output.

---

## **CORGIO\_CAP\_DIR\_TRISTATE**

<b>Description</b>	Specifies which I/O can be tri-stated.
<b>Type</b>	UINT32
<b>Values</b>	If bit 'n' is 1, then the associated I/O can be tri-stated.

---

## **CORGIO\_CAP\_EVENT\_TYPE**

<b>Description</b>	Specifies the event type(s) that can be registered.
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_EVENT_TYPE_RISING_EDGE (0x000000001) CORGIO_VAL_EVENT_TYPE_FALLING_EDGE (0x000000002) CORGIO_VAL_EVENT_TYPE_FAULT (0x000000004)
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

## **CORGIO\_CAP\_FAULT\_DETECT**

<b>Description</b>	Specifies if the I/O device has a fault detection.
<b>Type</b>	BOOL
<b>Values</b>	If TRUE, the device has a fault detection
<b>Note</b>	See CORGIO_PRM_FAULT_DETECT.

---

## **CORGIO\_CAP\_INPUT\_CONTROL\_METHOD**

<b>Description</b>	Specifies which input control methods are available for this I/O device.
<b>Type</b>	UINT32
<b>Values</b>	See CORGIO_PRM_OUTPUT_CONTROL_METHOD.

---

## **CORGIO\_CAP\_INPUT\_CONTROL\_POLARITY**

<b>Description</b>	Specifies which signal polarities are available for the input control pin on this I/O device
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_POLARITY_ACTIVE_LOW CORGIO_VAL_POLARITY_ACTIVE_HIGH CORGIO_VAL_POLARITY_RISING_EDGE CORGIO_VAL_POLARITY_FALLING_EDGE CORGIO_VAL_POLARITY_BOTH_EDGE CORGIO_VAL_POLARITY_DOUBLE_PULSE_RISING_EDGE CORGIO_VAL_POLARITY_DOUBLE_PULSE_FALLING_EDGE

---

## CORGIO\_CAP\_INPUT\_LEVEL

<b>Description</b>	Specifies the input levels for this I/O device.
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_INPUT_LEVEL_TTL CORGIO_VAL_INPUT_LEVEL_422 CORGIO_VAL_INPUT_LEVEL_LVDS CORGIO_VAL_INPUT_LEVEL_24VOLTS CORGIO_VAL_INPUT_LEVEL_LVTTL CORGIO_VAL_INPUT_LEVEL_12VOLTS
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

## CORGIO\_CAP\_IO\_COUNT

<b>Description</b>	Specifies the number of individual I/Os in the block.
<b>Type</b>	UINT32

---

## CORGIO\_CAP\_OUTPUT\_CONTROL\_METHOD

<b>Description</b>	Specifies which output control methods are available for this I/O device.
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_OUTPUT_CONTROL_METHOD_OFF CORGIO_VAL_OUTPUT_CONTROL_METHOD_1 CORGIO_VAL_OUTPUT_CONTROL_METHOD_2 CORGIO_VAL_OUTPUT_CONTROL_METHOD_3 CORGIO_VAL_OUTPUT_CONTROL_METHOD_4 CORGIO_VAL_OUTPUT_CONTROL_METHOD_5

---

## CORGIO\_CAP\_OUTPUT\_CONTROL\_POLARITY

<b>Description</b>	Specifies which signal polarities are available for the output control pin on this I/O device.
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_POLARITY_ACTIVE_LOW CORGIO_VAL_POLARITY_ACTIVE_HIGH CORGIO_VAL_POLARITY_RISING_EDGE CORGIO_VAL_POLARITY_FALLING_EDGE CORGIO_VAL_POLARITY_BOTH_EDGE CORGIO_VAL_POLARITY_DOUBLE_PULSE_RISING_EDGE CORGIO_VAL_POLARITY_DOUBLE_PULSE_FALLING_EDGE

---

## CORGIO\_CAP\_OUTPUT\_TYPE

<b>Description</b>	Specifies the output types for this I/O device.
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_OUTPUT_TYPE_PNP (0x00000001) CORGIO_VAL_OUTPUT_TYPE_NPN (0x00000002) CORGIO_VAL_OUTPUT_TYPE_LED (0x00000004) CORGIO_VAL_OUTPUT_TYPE_OPTOCOUPLE (0x00000008) CORGIO_VAL_OUTPUT_TYPE_TTL (0x00000010) CORGIO_VAL_OUTPUT_TYPE_LVTTL (0x00000020)
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

**CORGIO\_CAP\_POWER\_GOOD**

**Description** Specifies if the I/O device has a power good output.

**Type** BOOL

**Values** If TRUE, the device has a power good output.  
This output is an open collector output.  
See CORGIO\_PRM\_POWER\_GOOD.

---

**CORGIO\_CAP\_READ\_ONLY**

**Description** Specifies if the I/O is read-only. If an I/O is reserved for the grab controller (for example, external trigger, strobe or board sync), it is read-only and the GIO module cannot modify the state of that I/O.

**Type** BOOL

**Values** If TRUE, the I/O is read-only.

## Parameters

ID	Parameters	Attribute
0x00	CORGIO_PRM_LABEL	Read Only
0x01	CORGIO_PRM_DEVICE_ID	Read Only
0x02	<i>Reserved</i>	
0x03	CORGIO_PRM_DIR_OUTPUT	Read/Write
0x04	CORGIO_PRM_DIR_TRISTATE	Read/Write
0x05	CORGIO_PRM_INPUT_CONTROL_METHOD	Read/Write
0x06	CORGIO_PRM_INPUT_CONTROL_POLARITY	Read/Write
0x07	CORGIO_PRM_OUTPUT_CONTROL_METHOD	Read/Write
0x08	CORGIO_PRM_OUTPUT_CONTROL_POLARITY	Read/Write
0x09	CORGIO_PRM_OUTPUT_TYPE	Read/Write
0x0a	CORGIO_PRM_INPUT_LEVEL	Read/Write
0x0b	CORGIO_PRM_CONNECTOR	Read/Write
0x0c	CORGIO_PRM_FAULT_DETECT	Read Only
0x0d	CORGIO_PRM_POWER_GOOD	Read/Write

---

### CORGIO\_PRM\_CONNECTOR

<b>Description</b>	Selects which connector is used for this I/O device
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_CONNECTOR_1 (0x00000001) CORGIO_VAL_CONNECTOR_2 (0x00000002) If bit 'n' is 1, then the associated connector can be used.
<b>Note</b>	This value is board specific.

---

### CORGIO\_PRM\_DEVICE\_ID

<b>Description</b>	The General I/O's device ID.
<b>Type</b>	UINT32
<b>Note</b>	CORGIO_PRM_DEVICE_ID is a read-only parameter.

---

### CORGIO\_PRM\_DIR\_OUTPUT

<b>Description</b>	Specifies which I/O are set as outputs.
<b>Type</b>	UINT32
<b>Values</b>	If bit 'n' is 1, then the associated I/O is an output; otherwise it is an input.

---

### CORGIO\_PRM\_DIR\_TRISTATE

<b>Description</b>	Specifies which I/O are to be tri-stated.
<b>Type</b>	UINT32
<b>Values</b>	If bit 'n' is 1, then the associated I/O is tri-stated; otherwise it is not.

---

## CORGIO\_PRM\_FAULT\_DETECT

<b>Description</b>	Use to get the fault detect status for this I/O device.
<b>Type</b>	BOOL
<b>Values</b>	If TRUE, a fault has been detected.
<b>Note</b>	If TRUE, the fault needs to be corrected and the device needs to be reset.

---

## CORGIO\_PRM\_INPUT\_CONTROL\_METHOD

<b>Description</b>	Selects which input control method is activated for this I/O device.
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_INPUT_CONTROL_METHOD_OFF (0x00000000) CORGIO_VAL_INPUT_CONTROL_METHOD_1 (0x00000001) CORGIO_VAL_INPUT_CONTROL_METHOD_2 (0x00000002) CORGIO_VAL_INPUT_CONTROL_METHOD_3 (0x00000004) CORGIO_VAL_INPUT_CONTROL_METHOD_4 (0x00000008) CORGIO_VAL_INPUT_CONTROL_METHOD_5 (0x00000010)

---

## CORGIO\_PRM\_INPUT\_CONTROL\_POLARITY

<b>Description</b>	Specifies which signal polarity to use for the input control pin on this I/O device
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_POLARITY_ACTIVE_LOW (0x00000001) CORGIO_VAL_POLARITY_ACTIVE_HIGH (0x00000002) CORGIO_VAL_POLARITY_RISING_EDGE (0x00000004) CORGIO_VAL_POLARITY_FALLING_EDGE (0x00000008) CORGIO_VAL_POLARITY_BOTH_EDGE (0x00000010) CORGIO_VAL_POLARITY_DOUBLE_PULSE_RISING_EDGE (0x00000020) CORGIO_VAL_POLARITY_DOUBLE_PULSE_FALLING_EDGE (0x00000040)

---

## CORGIO\_PRM\_INPUT\_LEVEL

<b>Description</b>	Selects which input level is used for this I/O device.
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_INPUT_LEVEL_TTL (0x00000001) CORGIO_VAL_INPUT_LEVEL_422 (0x00000002) CORGIO_VAL_INPUT_LEVEL_LVDS (0x00000004) CORGIO_VAL_INPUT_LEVEL_24VOLTS (0x00000008) CORGIO_VAL_INPUT_LEVEL_OPTO (0x00000010) CORGIO_VAL_INPUT_LEVEL_LVTTL (0x00000020) CORGIO_VAL_INPUT_LEVEL_12VOLTS (0x00000040)

---

## CORGIO\_PRM\_LABEL

<b>Description</b>	The General I/O's string ID.
<b>Type</b>	CHAR[128]
<b>Values</b>	Zero-terminated array of characters with a fixed size of 128 bytes.
<b>Note</b>	CORGIO_PRM_LABEL is a read-only parameter.



---

## CORGIO\_PRM\_OUTPUT\_CONTROL\_METHOD

<b>Description</b>	Selects which output control method is activated for this I/O device
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_OUTPUT_CONTROL_METHOD_OFF (0x00000000) CORGIO_VAL_OUTPUT_CONTROL_METHOD_1 (0x00000001) CORGIO_VAL_OUTPUT_CONTROL_METHOD_2 (0x00000002) CORGIO_VAL_OUTPUT_CONTROL_METHOD_3 (0x00000004) CORGIO_VAL_OUTPUT_CONTROL_METHOD_4 (0x00000008) CORGIO_VAL_OUTPUT_CONTROL_METHOD_5 (0x00000010)

---

## CORGIO\_PRM\_OUTPUT\_CONTROL\_POLARITY

<b>Description</b>	Specifies which signal polarity to use for the output control pin on this I/O device
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_POLARITY_ACTIVE_LOW (0x00000001) CORGIO_VAL_POLARITY_ACTIVE_HIGH (0x00000002) CORGIO_VAL_POLARITY_RISING_EDGE (0x00000004) CORGIO_VAL_POLARITY_FALLING_EDGE (0x00000008) CORGIO_VAL_POLARITY_BOTH_EDGE (0x00000010) CORGIO_VAL_POLARITY_DOUBLE_PULSE_RISING_EDGE (0x00000020) CORGIO_VAL_POLARITY_DOUBLE_PULSE_FALLING_EDGE (0x00000040)

---

## CORGIO\_PRM\_OUTPUT\_TYPE

<b>Description</b>	Selects which output type is activated for this I/O device.
<b>Type</b>	UINT32
<b>Values</b>	CORGIO_VAL_OUTPUT_TYPE_PNP (0x00000001) CORGIO_VAL_OUTPUT_TYPE_NPN (0x00000002) CORGIO_VAL_OUTPUT_TYPE_LED (0x00000004) CORGIO_VAL_OUTPUT_TYPE_OPTOCOUPLER (0x00000008) CORGIO_VAL_OUTPUT_TYPE_TTL (0x00000010) CORGIO_VAL_OUTPUT_TYPE_LVTTL (0x00000020)

---

## CORGIO\_PRM\_POWER\_GOOD

<b>Description</b>	Sets the power good output.
<b>Type</b>	BOOL
<b>Values</b>	TRUE or FALSE See CORGIO_CAP_POWER_GOOD.

## Functions

Function	Description
CorGioGetCap	<i>Gets a general I/O capability value</i>
CorGioGetCount	<i>Gets the number of general I/O devices on a server</i>
CorGioGetHandle	<i>Gets a handle to a general I/O device</i>
CorGioGetPrm	<i>Gets a general I/O parameter value</i>
CorGioGetState	<i>Gets the current I/O states</i>
CorGioRegisterCallback	<i>Registers a function that will be called when an input I/O generates an interrupt</i>
CorGioRegisterCallbackEx	<i>Registers a function that will be called when an input I/O generates an interrupt</i>
CorGioRelease	<i>Releases a handle to a general I/O device</i>
CorGioReset	<i>Resets a general I/O device</i>
CorGioResetModule	<i>Resets the resources associated with the server's general I/O device(s)</i>
CorGioSetPrm	<i>Sets a simple general I/O parameter</i>
CorGioSetPrmEx	<i>Sets a complex general I/O parameter</i>
CorGioSetOutputControlState	<i>Set the state of the IO ouput.</i>
CorGioSetState	<i>Sets the state of the I/Os</i>
CorGioUnregisterCallback	<i>Unregisters a callback function</i>
CorGioUnregisterCallbackEx	<i>Unregisters a callback function</i>

---

### CorGioGetCap

Get general I/O capability value

**Prototype**      `CORSTATUS CorGioGetCap(CORGIO hGio, UINT32 cap, void *value);`  
**Description**    Gets general I/O capability value.  
**Input**            *hGio*      General I/O resource handle  
                       *cap*        General I/O device capability requested  
**Output**           *value*     Value of the capability  
**Return Value**    CORSTATUS\_OK  
                       CORSTATUS\_ARG\_NULL (if *value* is NULL), CORSTATUS\_CAP\_INVALID and  
                       CORSTATUS\_INVALID\_HANDLE

---

### CorGioGetCount

Get the number of general I/O devices on a server

**Prototype**      `CORSTATUS CorGioGetCount(CORSERVER hServer, UINT32 *count);`  
**Description**    Gets the number of general I/O devices available on a server.  
**Input**            *hServer*    Server handle  
**Output**           *count*     Number of general I/O devices  
**Return Value**    CORSTATUS\_OK  
                       CORSTATUS\_ARG\_NULL (if *count* is NULL), CORSTATUS\_INVALID\_HANDLE  
**Note**            The content of *count* is 0 when there is no general I/O device available.

---

## CorGioGetHandle

Get a handle to a general I/O device

<b>Prototype</b>	CORSTATUS <b>CorGioGetHandle</b> (CORSERVER <i>hServer</i> , UINT32 <i>deviceId</i> , CORGIO * <i>hGio</i> );	
<b>Description</b>	Gets a handle to a general I/O device.	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>deviceId</i>	Specifies which general I/O device to select. Valid values are in the range [0... <i>count</i> -1], where <i>count</i> is the value returned by CORGIOGetCount.
<b>Output</b>	<i>hGio</i>	General I/O resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>hGio</i> is NULL), CORSTATUS_ARG_OUT_OF_RANGE, CORSTATUS_INVALID_HANDLE, CORSTATUS_NO_MEMORY and CORSTATUS_RESOURCE_IN_USE	
<b>See Also</b>	CorGioGetCount and CorGioRelease	

---

## CorGioGetPrm

Get general I/O parameter value

<b>Prototype</b>	CORSTATUS <b>CorGioGetPrm</b> (CORGIO <i>hGio</i> , UINT32 <i>prm</i> , void * <i>value</i> );	
<b>Description</b>	Gets general I/O parameter value.	
<b>Input</b>	<i>hGio</i>	General I/O resource handle
	<i>prm</i>	General I/O parameter requested
<b>Output</b>	<i>value</i>	Current value of the parameter
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE and CORSTATUS_PRM_INVALID	
<b>See Also</b>	CorGioRelease and CorGioSetPrmEx	

---

## CorGioGetState

Get the state of the I/Os

<b>Prototype</b>	CORSTATUS <b>CorGioGetState</b> (CORGIO <i>hGio</i> , UINT32 * <i>value</i> );	
<b>Description</b>	Gets the state of the I/Os.	
<b>Input</b>	<i>hGio</i>	General I/O resource handle
<b>Output</b>	<i>value</i>	Current I/O values. If a bit is '1', then the corresponding I/O is <b>high</b> ; otherwise, it is <b>low</b> .
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE and CORSTATUS_SERVICE_NOT_AVAILABLE	
<b>See Also</b>	CorGioSetPrm and CorGioSetPrmEx	

---

## CorGioRegisterCallback

Register a function that will be called when an input I/O generates an interrupt.

<b>Prototype</b>	CORSTATUS <b>CorGioRegisterCallback</b> ( CORGIO <i>hGio</i> , UINT32 <i>eventType</i> , UINT32 <i>io</i> , void* <i>callbackFct</i> , void * <i>context</i> )	
<b>Description</b>	Registers a function that will be called when an input I/O generates an interrupt.	
<b>Input</b>	<i>hGio</i>	General I/O resource handle
	<i>eventType</i>	Type of event to register: CORGIO_VAL_EVENT_TYPE_RISING_EDGE CORGIO_VAL_EVENT_TYPE_FALLING_EDGE CORGIO_VAL_EVENT_TYPE_FAULT CORGIO_VAL_EVENT_TYPE_MASK
	<i>io</i>	If bit 'n' is 1, then the corresponding I/O will cause <i>callbackFct</i> to be called.
	<i>callbackFct</i>	Callback function to be registered. Define your callback function as follows:  <i>CORSTATUS CCONV</i> <i>callback</i> ( void * <i>context</i> , <i>UINT32 eventType</i> , <i>UINT32 eventCount</i> );  When called, <i>context</i> will have the value you have specified at callback function registration; <i>eventType</i> will contain the event(s) that triggered the call to your callback function; <i>eventCount</i> should increment by one at each call, with a starting value of 1. In case the counter resource cannot keep up because there is too many events to be signaled, <i>eventCount</i> will take nonconsecutive values, indicating that events have been lost.
		See the Data Types section for the PCORCALLBACK definition.
	<i>context</i>	Context pointer to be passed to the callback function when called.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE, CORSTATUS_RESOURCE_IN_USE (if attempting to associate a callback function to an I/O that already has a callback) CORSTATUS_SERVICE_NOT_AVAILABLE	
<b>See Also</b>	CorGioUnregisterCallback	

---

## CorGioRegisterCallbackEx

Register callback function for an acquisition resource

<b>Prototype</b>	CORSTATUS CORAPIFUNC <b>CorGioRegisterCallbackEx</b> (CORGIO hGio, UINT32 eventType, UINT32 io, PCOREVENTINFOCALLBACK callbackFunc, void *context);	
<b>Description</b>	Registers a function that will be called when an input I/O generates an interrupt.	
<b>Input</b>	<i>hGio</i>	General I/O resource handle
	<i>eventType</i>	Type of event to register: CORGIO_VAL_EVENT_TYPE_RISING_EDGE CORGIO_VAL_EVENT_TYPE_FALLING_EDGE CORGIO_VAL_EVENT_TYPE_FAULT CORGIO_VAL_EVENT_TYPE_MASK
	<i>io</i>	If bit 'n' is 1, then the corresponding I/O will cause <i>callbackFct</i> to be called.
	<i>callback</i>	Callback function to register. The callback function is defined as follows: <i>CORSTATUS CCONV</i> <i>callback(void *context, UINT64 eventType, UINT64 eventCount);</i>  When the event occurs in the acquisition device the specified callback function is called. The callback function provides information on the corresponding event (in the <i>PCOREVENTINFOCALLBACK</i> handle). Refer to the <i>EventInfo</i> module for more detail on the available information. The context pointer is also returned by the callback function allowing you to exchange user information between the callback and your application context..  See the Data Types section for the PCORCALLBACK definition.
	<i>context</i>	Context pointer passed to the callback function when called
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_AVAILABLE CORSTATUS_RESOURCE_IN_USE	
<b>Note</b>	The values may be ORed if more than one event is desired.	
	This function allows timestamp events to be registered. However, device drivers continue to support both functions.	
<b>See Also</b>	CorGioUnregisterCallbackEx	

---

## CorGioRelease

Release handle to a general I/O device

<b>Prototype</b>	CORSTATUS <b>CorGioRelease</b> (CORGIO hGio);	
<b>Description</b>	Releases handle to a general I/O device.	
<b>Input</b>	<i>hGio</i>	General I/O resource handle
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorGioGetHandle	

---

## CorGioReset

Reset a general I/O device

<b>Prototype</b>	CORSTATUS <b>CorGioReset</b> (CORGIO <i>hGio</i> );
<b>Description</b>	Resets a general I/O device. Restores the default values for general I/O parameters.
<b>Input</b>	<i>hGio</i> General I/O resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE and CORSTATUS_SERVICE_NOT_AVAILABLE

---

## CorGioResetModule

Reset the resources associated with the server's general I/O device(s)

<b>Prototype</b>	CORSTATUS <b>CorGioResetModule</b> (CORSERVER <i>hServer</i> );
<b>Description</b>	Resets the resources associated with the server's general I/O device(s). Releases all resources (handle, memory) currently allocated. Make certain that no other application is currently using any general I/O device resource. This function should be use with caution.
<b>Input</b>	<i>hServer</i> Server handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE

---

## CorGioSetPrm

Set a simple general I/O parameter

<b>Prototype</b>	CORSTATUS <b>CorGioSetPrm</b> (CORGIO <i>hGio</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );
<b>Description</b>	Sets a simple general I/O parameter.
<b>Input</b>	<i>hGio</i> General I/O resource handle <i>prm</i> General I/O parameter to set <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY CORSTATUS_PRM_INVALID CORSTATUS_PRM_INVALID_VALUE CORSTATUS_PRM_MUTUALLY_EXCLUSIVE CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_PRM_OUT_OF_RANGE CORSTATUS_PRM_READ_ONLY
<b>Note</b>	A simple parameter fits inside an UINT32. If the parameter is complex, use CorGioSetPrmEx.
<b>See Also</b>	CorGioGetPrm and CorGioSetPrmEx

---

## CorGioSetPrmEx

Set a complex general I/O parameter

<b>Prototype</b>	CORSTATUS <b>CorGioSetPrmEx</b> (CORGIO <i>hGio</i> , UINT32 <i>prm</i> , void * <i>value</i> );
<b>Description</b>	Sets a complex general I/O parameter.
<b>Input</b>	<i>hGio</i> General I/O resource handle <i>prm</i> General I/O parameter to set <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE CORSTATUS_NO_MEMORY CORSTATUS_PRM_INVALID CORSTATUS_PRM_INVALID_VALUE CORSTATUS_PRM_MUTUALLY_EXCLUSIVE CORSTATUS_PRM_NOT_AVAILABLE CORSTATUS_PRM_OUT_OF_RANGE CORSTATUS_PRM_READ_ONLY
<b>Note</b>	A complex parameter is one whose size is greater than an UINT32. If the parameter size is UINT32, used either CorGioSetPrm or CorGioSetPrmEx.
<b>See Also</b>	CorGioGetPrm and CorGioSetPrm

---

## CorGioSetOutputControlState

Set the state of the IO output. This is a board specific function. See the board user's manual.

<b>Prototype</b>	CORSTATUS <b>CorGioSetOutputControlState</b> (CORGIO <i>hGio</i> ,UINT32 <i>ioMask</i> , UINT32 <i>value</i> );
<b>Description</b>	Sets the state of the I/O output.
<b>Input</b>	<i>hGio</i> General I/O resource handle <i>ioMask</i> If a bit is '1', then the corresponding Output will be affected. <i>value</i>
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE CORSTATUS_SERVICE_NOT_AVAILABLE
<b>See Also</b>	CorGioGetPrm and CorGioSetPrmEx

---

## CorGioSetState

Set the state of the I/Os

<b>Prototype</b>	CORSTATUS <b>CorGioSetState</b> (CORGIO <i>hGio</i> , UINT32 <i>ioMask</i> , UINT32 <i>value</i> );	
<b>Description</b>	Sets the state of the general I/O pins, if available on the hardware.	
<b>Input</b>	<i>hGio</i>	General I/O resource handle
	<i>ioMask</i>	Mask specifying the I/Os to modify. If bit 'n' is 1, then the I/O will be written with the corresponding bit in <i>value</i> .
	<i>value</i>	New I/O values. If a bit is '1', the corresponding I/O will be set to <b>high</b> ; otherwise, it will be set to <b>low</b> . Value represents a bit-field.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INCOMPATIBLE (if trying to set the state of an input pin) CORSTATUS_INVALID_HANDLE and CORSTATUS_SERVICE_NOT_AVAILABLE	
<b>See Also</b>	CorGioGetPrm and CorGioSetPrmEx	

---

## CorGioUnregisterCallback

Unregister a callback function.

<b>Prototype</b>	CORSTATUS <b>CorGioUnregisterCallback</b> (CORGIO <i>hGio</i> , void* <i>callbackFct</i> );	
<b>Description</b>	Unregisters a callback function.	
<b>Input</b>	<i>hGio</i>	General I/O resource handle
	<i>callbackFct</i>	Pointer to a callback function that has been previously registered.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorGioRegisterCallback	

---

## CorGioUnregisterCallbackEx

Unregister callback function for an I/O resource

<b>Prototype</b>	CORSTATUS CORAPIFUNC <i>CorGioUnregisterCallbackEx</i> (CORGIO <i>hGio</i> , PCOREVENTINFOCALLBACK <i>callbackFunc</i> );	
<b>Description</b>	Unregisters a callback function.	
<b>Input</b>	<i>hGio</i>	General I/O resource handle
	<i>callbackFct</i>	Callback function to unregister. See Data Types section for the PCOREVENTINFOCALLBACK definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorGioRegisterCallbackEx	



---

# Module

The LUT (Lookup Table) Module defines LUT data structures that are used by the Acquisition, Display, and Processing modules. Refer to the functions CorAcqSetLut and CorViewSetLut for a description on how to apply the LUTs to the Acquisition and Display hardware, respectively.

## Parameters

ID	Parameter	Attribute
0x00	CORLUT_PRM_ADDRESS	Read Only
0x01	CORLUT_PRM_DATASIZE	Read Only
0x02	CORLUT_PRM_FORMAT	Read Only
0x03	CORLUT_PRM_NPAGES	Read Only
0x04	CORLUT_PRM_NENTRIES	Read Only
0x05	CORLUT_PRM_SIZE	Read Only
0x06	CORLUT_PRM_PHYSADDRESS	Read Only
0x07	CORLUT_PRM_SIGNED	Read Only

---

### CORLUT\_PRM\_ADDRESS

**Description** Address of the buffer containing the lookup table.  
**Type** UINT32  
**Values** 32-bit address of the buffer.

---

### CORLUT\_PRM\_DATASIZE

**Description** Size of one lookup table element (in bytes).  
**Type** UINT32  
**Values** Will have a value of 1 or 2.

---

### CORLUT\_PRM\_FORMAT

**Description** Lookup table data format. Determines a single LUT element's type.  
**Type** UINT32  
**Values** For a detailed description of the values, see CorLutNew.

---

### CORLUT\_PRM\_NENTRIES

**Description** The number of elements in a lookup table; also, the number of different pixel values which can be transformed by the LUT.  
**Type** UINT32  
**Values** Usually ranges from 256 to 65536.

---

### CORLUT\_PRM\_NPAGES

**Description** The number of pages in the lookup table. Usually understood as the number of color planes represented in the LUT.  
**Type** UINT32  
**Values** 1: Monochrome LUT  
3: Color LUT

---

**CORLUT\_PRM\_PHYSADDRESS**

<b>Description</b>	Physical address of the buffer containing the lookup table.
<b>Type</b>	UINT32
<b>Values</b>	32-bit address of the buffer.

---

**CORLUT\_PRM\_SIGNED**

<b>Description</b>	Sign of the lookup table elements.
<b>Type</b>	UINT32
<b>Values</b>	CORLUT_VAL_FORMAT_UNSIGNED CORLUT_VAL_FORMAT_SIGNED

---

**CORLUT\_PRM\_SIZE**

<b>Description</b>	Size of the lookup table data buffer (in bytes).
<b>Type</b>	UINT32
<b>Values</b>	The value is a product of the number of entries, the element size, and the number of color components (1 for monochrome, 3 for color).

## Functions

Function	Description
CorLutAdd	<i>Performs addition operation on a LUT resource</i>
CorLutAnd	<i>Performs logical AND operation on a LUT resource</i>
CorLutASub	<i>Performs absolute subtraction operation on a LUT resource</i>
CorLutBit	<i>Sets a binary pattern in a LUT resource</i>
CorLutClip	<i>Clips the lookup table values of a LUT resource</i>
CorLutCopy	<i>Copies a source LUT resource to a destination LUT resource</i>
CorLutFree	<i>Releases handle to a LUT resource</i>
CorLutGamma	<i>Computes by means of a gamma law the lookup table values of a LUT resource</i>
CorLutGetPrm	<i>Gets LUT parameter value from a LUT resource</i>
CorLutLoad	<i>Loads a LUT resource from a file</i>
CorLutMax	<i>Performs maximum operation on a LUT resource</i>
CorLutMin	<i>Performs minimum operation on a LUT resource</i>
CorLutNew	<i>Creates in a specified server's memory a new LUT resource</i>
CorLutNewFromFile	<i>Creates from a file and in a specified server's memory a new LUT resource</i>
CorLutNormal	<i>Sets a normal lookup table for a LUT resource</i>
CorLutOr	<i>Performs logical OR operation on a LUT resource</i>
CorLutRead	<i>Reads a series of elements from a LUT resource</i>
CorLutReadEx	<i>Reads an element from a LUT resource</i>
CorLutReverse	<i>Sets a reverse lookup table for a LUT resource</i>
CorLutRoll	<i>Shifts the lookup table values of a LUT resource</i>
CorLutSave	<i>Saves to a file the content of a LUT resource</i>
CorLutScale	<i>Performs scaling operation on a LUT resource</i>
CorLutSetPrm	<i>Sets a simple LUT parameter of a LUT resource</i>
CorLutSetPrmEx	<i>Sets a complex LUT parameter of a LUT resource</i>
CorLutShift	<i>Shifts the lookup table values of a LUT resource</i>
CorLutSlope	<i>Slopes the lookup table values of a LUT resource</i>
CorLutSub	<i>Performs subtraction operation on a LUT resource</i>
CorLutThreshold1	<i>Sets a single-threshold lookup table for a LUT resource</i>
CorLutThreshold2	<i>Sets a double-threshold for the lookup table values of a LUT resource</i>
CorLutWrite	<i>Writes a series of elements into a LUT resource</i>
CorLutWriteEx	<i>Writes an element into a LUT resource</i>
CorLutXor	<i>Performs logical XOR operation on a LUT resource</i>

---

## CorLutAdd

Perform addition operation on a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutAdd</b> (CORLUT hLut, CORDATA k);	
<b>Description</b>	Modifies the LUT values through the addition operation, using a gray level of $k$ . Each entry is calculated as follows: $lut[i] = lut[i] + k$	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	$k$	Constant. See Data Types for CORDATA definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutASubCorLutSub	

---

## CorLutAnd

Perform logical AND operation on a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutAnd</b> (CORLUT hLut, CORDATA k);	
<b>Description</b>	Modifies the LUT values through the logical AND operation, using a gray level of $k$ . Each entry is calculated as follows: $lut[i] = lut[i] \text{ AND } k$	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	$k$	Constant. See Data Types for CORDATA definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutOr and CorLutXor	

---

## CorLutASub

Perform absolute difference operation on a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutASub</b> (CORLUT hLut, CORDATA k);	
<b>Description</b>	Modifies the LUT values through the absolute difference operation, using a gray level of $k$ . Each entry is calculated as follows: $lut[i] = \text{abs}(lut[i] - k)$	
<b>Input</b>	<i>hLut</i>	LUT to be transformed
	$k$	Constant. See Data Types for CORDATA definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutAdd and CorLutSub	

---

## CorLutBit

Set a binary pattern in a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutBit</b> (CORLUT <i>hLut</i> , UINT32 <i>bit</i> , CORDATA <i>k</i> );	
<b>Description</b>	Sets a binary pattern in a LUT resource. Only entries that the bit, as specified by the <i>bit</i> argument, is set to 1, are set to the color <i>k</i> . Each entry is calculated as follows: $lut[i] = (i \& (1L \ll bit)) ? k : lut[i]$	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>bit</i>	Selected bit
	<i>k</i>	Color assigned when bit is on. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	

---

## CorLutClip

Clip the lookup table values of a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutClip</b> (CORLUT <i>hLut</i> , INT32 <i>imin</i> , INT32 <i>imax</i> , CORDATA <i>omin</i> , CORDATA <i>omax</i> );	
<b>Description</b>	Computes the values of a LUT resource so that the gray levels clip to the specified values. This will keep only the pixels in the range [ <i>imin</i> ... <i>imax</i> ] and map them to the range [ <i>omin</i> ... <i>omax</i> ].	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>imin</i>	Minimum index of clipping region
	<i>imax</i>	Maximum index of clipping region
	<i>omin</i>	Minimum color to which the minimum index is mapped. See Data Types for <i>CORDATA</i> definition.
	<i>omax</i>	Maximum color to which the maximum index is mapped. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_INCOMPATIBLE, CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	

---

## CorLutCopy

Copy a source LUT resource to a destination LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutCopy</b> (CORLUT <i>hSrc</i> , CORLUT <i>hDst</i> );	
<b>Description</b>	Copies the values of one LUT to another.	
<b>Input</b>	<i>hSrc</i>	LUT resource handle (source)
	<i>hDst</i>	LUT resource handle (destination)
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_INVALID, CORSTATUS_INCOMPATIBLE_LUT and CORSTATUS_INVALID_HANDLE	
<b>Note</b>	When the source LUT size is larger than the destination LUT size, only the section of the source that fits the destination is copied.	

---

## CorLutFree

Release handle to a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutFree</b> (CORLUT <i>hLut</i> );
<b>Description</b>	Releases handle to a LUT resource.
<b>Input</b>	<i>hLut</i> LUT resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorLutNew and CorLutNewFromFile

---

## CorLutGamma

Compute by means of a gamma law the lookup table values of a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutGamma</b> (CORLUT <i>hLut</i> , FLOAT <i>factor</i> );
<b>Description</b>	Computes the values of a LUT resource using an inverse gamma law with <i>factor</i> . Used to correct the camera's light response, which is often set to be a power function (referred to as the gamma function). A gamma factor of 1 means no correction will be applied, and a normal LUT is computed.
<b>Input</b>	<i>hLut</i> LUT resource handle <i>factor</i> Gamma law factor; must be positive
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE, CORSTATUS_INCOMPATIBLE_LUT and CORSTATUS_INVALID_HANDLE

---

## CorLutGetPrm

Get LUT parameter value from a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutGetPrm</b> (CORLUT <i>hLut</i> , UINT32 <i>prm</i> , void * <i>value</i> );
<b>Description</b>	Gets LUT parameter value from a LUT resource
<b>Input</b>	<i>hLut</i> LUT resource handle <i>prm</i> LUT parameter requested
<b>Output</b>	<i>value</i> Current value of the parameter
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>value</i> is NULL), CORSTATUS_INVALID_HANDLE and CORSTATUS_PRM_INVALID
<b>See Also</b>	CorLutSetPrm and CorLutSetPrmEx

---

## CorLutLoad

Load a LUT resource from a file

<b>Prototype</b>	CORSTATUS <b>CorLutLoad</b> (CORLUT hLut, const char *filename);
<b>Description</b>	Loads a LUT resource from a file.
<b>Input</b>	<i>hLut</i> LUT resource handle <i>filename</i> String specifying the path and filename
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>filename</i> is NULL) CORSTATUS_FILE_OPEN_ERROR, CORSTATUS_FILE_READ_ERROR, CORSTATUS_INVALID_HANDLE and CORSTATUS_NO_MEMORY
<b>Note</b>	If the LUT buffer is not large enough, data read from file is clipped to the LUT's size.
<b>See Also</b>	CorLutSave and LUT File Format

---

## CorLutMax

Perform maximum operation on a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutMax</b> (CORLUT hLut, CORDATA k);
<b>Description</b>	Replaces each element of the existing LUT by the maximum of either its value or the specified gray level <i>k</i> . Each entry is calculated as follows: $lut[i] = \max(k, lut[i])$
<b>Input</b>	<i>hLut</i> LUT resource handle <i>k</i> Constant. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorLutMin

---

## CorLutMin

Perform minimum operation on a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutMin</b> (CORLUT hLut, CORDATA k);
<b>Description</b>	Replaces each element of the existing LUT by the minimum of either its value or the specified gray level <i>k</i> . Each entry is calculated as follows: $lut[i] = \min(k, lut[i])$
<b>Input</b>	<i>hLut</i> LUT resource handle <i>k</i> Constant. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorLutMax

---

## CorLutNew

Create in a specified server's memory a new LUT resource

**Prototype**      `CORSTATUS CorLutNew(CORSERVER hServer, UINT32 nEntries, UNIT32 format, CORLUT *hLut);`

**Description**      Allocates and initializes a LUT of the specified size and format.

**Input**

<i>hServer</i>	Server handle
<i>nEntries</i>	Number of entries in the LUT
<i>format</i>	The format of the LUT entries is determined either by the ORing the format and bit width values, or using one of the combined values. The sign value can optionally be ORed to the result.

**Format values:**

**Monochrome:** Each element stores monochrome data. The LUT is a single vector of such elements.

CORLUT\_VAL\_FORMAT\_MONO8  
CORLUT\_VAL\_FORMAT\_MONO9  
CORLUT\_VAL\_FORMAT\_MONO10  
CORLUT\_VAL\_FORMAT\_MONO11  
CORLUT\_VAL\_FORMAT\_MONO12  
CORLUT\_VAL\_FORMAT\_MONO13  
CORLUT\_VAL\_FORMAT\_MONO14  
CORLUT\_VAL\_FORMAT\_MONO15  
CORLUT\_VAL\_FORMAT\_MONO16

**Unsigned integer (same as monochrome):** Each element stores monochrome data. The LUT is a single vector of such elements.

CORLUT\_VAL\_FORMAT\_UINT8  
CORLUT\_VAL\_FORMAT\_UINT9  
CORLUT\_VAL\_FORMAT\_UINT10  
CORLUT\_VAL\_FORMAT\_UINT11  
CORLUT\_VAL\_FORMAT\_UINT12  
CORLUT\_VAL\_FORMAT\_UINT13  
CORLUT\_VAL\_FORMAT\_UINT14  
CORLUT\_VAL\_FORMAT\_UINT15  
CORLUT\_VAL\_FORMAT\_UINT16

**Signed integer (monochrome with a sign)**

Each element stores monochrome data. The LUT is a single vector of such elements

CORLUT\_VAL\_FORMAT\_INT8  
CORLUT\_VAL\_FORMAT\_INT9  
CORLUT\_VAL\_FORMAT\_INT10  
CORLUT\_VAL\_FORMAT\_INT11  
CORLUT\_VAL\_FORMAT\_INT12  
CORLUT\_VAL\_FORMAT\_INT13  
CORLUT\_VAL\_FORMAT\_INT14  
CORLUT\_VAL\_FORMAT\_INT15  
CORLUT\_VAL\_FORMAT\_INT16

**Color non-interlaced:** One element stores data for one color component. Each color component is represented as a separate vector of single-component elements.

CORLUT\_VAL\_FORMAT\_COLORNi8  
CORLUT\_VAL\_FORMAT\_COLORNi9  
CORLUT\_VAL\_FORMAT\_COLORNi10  
CORLUT\_VAL\_FORMAT\_COLORNi11  
CORLUT\_VAL\_FORMAT\_COLORNi12  
CORLUT\_VAL\_FORMAT\_COLORNi13  
CORLUT\_VAL\_FORMAT\_COLORNi14  
CORLUT\_VAL\_FORMAT\_COLORNi15  
CORLUT\_VAL\_FORMAT\_COLORNi16



**Color interlaced:** One element stores data for the three color components. The LUT is a single vector of such elements.

CORLUT\_VAL\_FORMAT\_COLORI8  
 CORLUT\_VAL\_FORMAT\_COLORI9  
 CORLUT\_VAL\_FORMAT\_COLORI10  
 CORLUT\_VAL\_FORMAT\_COLORI11  
 CORLUT\_VAL\_FORMAT\_COLORI12  
 CORLUT\_VAL\_FORMAT\_COLORI13  
 CORLUT\_VAL\_FORMAT\_COLORI14  
 CORLUT\_VAL\_FORMAT\_COLORI15  
 CORLUT\_VAL\_FORMAT\_COLORI16

**Output** *hLut* LUT resource handle

**Return Value** CORSTATUS\_OK  
 CORSTATUS\_ARG\_INVALID\_VALUE, CORSTATUS\_ARG\_NULL ( if *hLut* is NULL),  
 CORSTATUS\_INVALID\_HANDLE and CORSTATUS\_NO\_MEMORY

**See Also** CorLutFree and CorLutNewFromFile

---

## CorLutNewFromFile

Create from a file and in specified server's memory a new LUT resource

**Prototype** CORSTATUS **CorLutNewFromFile**(CORSERVER *hServer*, const *char* \**filename*, CORLUT \**hLut*);

**Description** Allocates and initializes a LUT of the same format as the designated file's LUT.

**Input** *hServer* Server handle  
*filename* String specifying the path and name

**Output** *hLut* LUT resource handle

**Return Value** CORSTATUS\_OK  
 CORSTATUS\_ARG\_NULL ( if *filename* is NULL)  
 CORSTATUS\_FILE\_OPEN\_ERROR, CORSTATUS\_FILE\_READ\_ERROR,  
 CORSTATUS\_INVALID\_HANDLE and CORSTATUS\_NO\_MEMORY

**Note** Same as calling CorLutNew then CorLutLoad.

**See Also** CorLutFree and CorLutNew

---

## CorLutNormal

Set a normal lookup table for a LUT resource

**Prototype** CORSTATUS **CorLutNormal**(CORLUT *hLut*);

**Description** Defines a normal (linear) LUT.  
 Each entry is assigned the following value:  $lut[i] = i * (2^n / CORLUT\_PRM\_NENTRIES)$   
 where  $n$  = number of bits per entry (See CORLUT\_PRM\_FORMAT)

**Input** *hLut* LUT resource handle

**Output** None

**Return Value** CORSTATUS\_OK  
 CORSTATUS\_INVALID\_HANDLE

---

## CorLutOr

Perform logical OR operation on a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutOr</b> (CORLUT <i>hLut</i> , CORDATA <i>k</i> );	
<b>Description</b>	Modifies the values of a LUT through the logical OR operation, using a gray level of <i>k</i> . Each entry is calculated as follows: $lut[i] = lut[i] \text{ OR } k$	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>k</i>	Constant. See Data Types for CORDATA definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutXor	

---

## CorLutRead

Read a series of elements from a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutRead</b> (CORLUT <i>hLut</i> , UINT32 <i>offset</i> , void * <i>array</i> , UINT32 <i>size</i> );	
<b>Description</b>	Reads a consecutive series of elements from the specified LUT and copies them into an one-dimensional destination array.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>offset</i>	Offset to seek within the LUT prior to copy
	<i>size</i>	Size of transfer ( <i>nElements</i> × <i>elementSize</i> bytes)
<b>Output</b>	<i>array</i>	Array which can accommodate the requested number of elements ( <i>nElements</i> × <i>elementSize</i> )
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>array</i> is NULL ), CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutWrite	

---

## CorLutReadEx

Read an element from a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutReadEx</b> (CORLUT <i>hLut</i> , UINT32 <i>offset</i> , CORDATA * <i>element</i> );	
<b>Description</b>	Reads an element from the specified LUT.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>offset</i>	Offset to seek within the LUT prior to read
<b>Output</b>	<i>element</i>	Current value of the element. See Data Types for CORDATA definition.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>element</i> is NULL ), CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutWriteEx	

---

## CorLutReverse

Sets a reverse lookup table for a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutReverse</b> (CORLUT <i>hLut</i> );
<b>Description</b>	Sets a reverse LUT: $lut[i] = max - i$ , where <i>max</i> is the highest pixel value. For instance, for an unsigned 8 bit/pixel image, <i>max</i> is set to 255; an unsigned 16 bit/pixel has <i>max</i> set to 65535.
<b>Input</b>	<i>hLut</i> LUT resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE

---

## CorLutRoll

Shift the lookup table values of a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutRoll</b> (CORLUT <i>hLut</i> , INT32 <i>rol</i> );
<b>Description</b>	Shifts a LUT, wrapping the values at each end. The direction of shift is determined by the sign of the argument <i>rol</i> . A positive <i>rol</i> shifts the LUT from the low indexes to the higher ones, while a negative <i>rol</i> shifts the LUT from high indexes to lower ones.
<b>Input</b>	<i>hLut</i> LUT resource handle <i>rol</i> Number of shifts of the LUT indexes
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE and CORSTATUS_NO_MEMORY
<b>See Also</b>	CorLutShift

---

## CorLutSave

Saves to a file the content of a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutSave</b> (CORLUT <i>hLut</i> , const char * <i>filename</i> );
<b>Description</b>	Saves to a file the content of a LUT resource.
<b>Input</b>	<i>hLut</i> LUT resource handle <i>filename</i> String specifying the path and filename
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>filename</i> is NULL), CORSTATUS_FILE_CREATE_ERROR, CORSTATUS_FILE_WRITE_ERROR and CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorLutLoad and LUT File Format

---

## CorLutScale

Perform scaling operation on a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutScale</b> (CORLUT <i>hLut</i> , CORDATA <i>k</i> );	
<b>Description</b>	Modifies the values of a LUT through a scaling operation, using a gray level of <i>k</i> . Each entry is calculated as follows: $lut[i] = lut[i] * k / maxcolor$	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>k</i>	Constant. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	

---

## CorLutSetPrm

Set a simple LUT parameter of a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutSetPrm</b> (CORLUT <i>hLut</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );	
<b>Description</b>	Sets a simple LUT parameter of a LUT resource.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>prm</i>	LUT parameter to set
	<i>value</i>	New value of the parameter
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE, CORSTATUS_PRM_INVALID and CORSTATUS_PRM_READ_ONLY	
<b>Note</b>	A simple parameter fits inside an UINT32. If the parameter is complex, use CorLutSetPrmEx. All LUT parameters are read-only parameters. Therefore, you can get their values with CorLutGetPrm but cannot change these values with CorLutSetPrm.	
<b>See Also</b>	CorLutGetPrm and CorLutSetPrmEx	

---

## CorLutSetPrmEx

Set a complex LUT parameter of a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutSetPrmEx</b> (CORLUT <i>hLut</i> , UINT32 <i>prm</i> , const void <i>*value</i> );	
<b>Description</b>	Sets a complex LUT parameter of a LUT resource.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>prm</i>	LUT parameter to set
	<i>value</i>	New value of the parameter
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>value</i> is NULL), CORSTATUS_INVALID_HANDLE	
	CORSTATUS_PRM_INVALID and CORSTATUS_PRM_READ_ONLY	
<b>Note</b>	A complex parameter is one whose size is greater than an UINT32. If the parameter size is UINT32, use either CorLutSetPrm or CorLutSetPrmEx.	
<b>See Also</b>	CorLutGetPrm and CorLutSetPrm	

---

## CorLutShift

Shift the lookup table values of a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutShift</b> (CORLUT <i>hLut</i> , INT32 <i>nShift</i> );	
<b>Description</b>	Shifts the values of a LUT by <i>nShift</i> . If <i>nShift</i> is positive, values are shifted left; if <i>nShift</i> is negative, values are shifted right.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>nShift</i>	Number of shift bits
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutRoll	

---

## CorLutSlope

Slope the lookup table values of a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutSlope</b> (CORLUT <i>hLut</i> , INT32 <i>i1</i> , CORDATA <i>c1</i> , INT32 <i>i2</i> , CORDATA <i>c2</i> );	
<b>Description</b>	Modifies the values of the LUT so that the pixels in the range [ <i>i1</i> ... <i>i2</i> ] are mapped to the range [ <i>c1</i> ... <i>c2</i> ]. Pixels outside of the range are unchanged.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>i1</i>	Minimum index of slope region.
	<i>c1</i>	Minimum color to which the minimum index is mapped. See Data Types for <i>CORDATA</i> definition.
	<i>i2</i>	Maximum index of slope region
	<i>c2</i>	Maximum color to which the maximum index is mapped. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_INCOMPATIBLE, CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	

---

## CorLutSub

Perform subtraction operation on a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutSub</b> (CORLUT <i>hLut</i> , CORDATA <i>k</i> );	
<b>Description</b>	Modifies the values of a LUT through the subtraction operation, using a gray level of <i>k</i> . Each entry is calculated as follows: $lut[i] = lut[i] - k$	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>k</i>	Constant. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutAdd and CorLutASub	

---

## CorLutThreshold1

Sets a single-threshold lookup table for a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutThreshold1</b> (CORLUT <i>hLut</i> , CORDATA <i>thrs</i> );	
<b>Description</b>	Sets a threshold LUT. Pixels under <i>thrs</i> are set to the lowest color value, the others are set to the highest color value.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>thrs</i>	Threshold gray level. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutThreshold2	

---

## CorLutThreshold2

Sets a double-threshold lookup table for a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutThreshold2</b> (CORLUT <i>hLut</i> , CORDATA <i>thrs1</i> , CORDATA <i>thrs2</i> );	
<b>Description</b>	Sets a threshold LUT. Pixels in the range [ <i>thrs1</i> ... <i>thrs2</i> ] are mapped to the highest color value, the others are set to the lowest color value.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>thrs1</i>	Threshold gray level. See Data Types for <i>CORDATA</i> definition.
	<i>thrs2</i>	Threshold gray level. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutThreshold1	

---

## CorLutWrite

Write a series of elements into a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutWrite</b> (CORLUT <i>hLut</i> , UINT32 <i>offset</i> , void <i>*array</i> , UINT32 <i>size</i> );	
<b>Description</b>	Writes a series of elements from an one-dimensional source array to a LUT resource.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>offset</i>	Offset to seek within the LUT prior to copy
	<i>array</i>	Array which contains the elements to be written ( <i>nElements</i> × <i>elementSize</i> )
	<i>size</i>	Size of transfer ( <i>nElements</i> × <i>elementSize</i> )
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>array</i> is NULL),	
	CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutRead	

---

## CorLutWriteEx

Write an element into a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutWriteEx</b> (CORLUT <i>hLut</i> , UINT32 <i>offset</i> , CORDATA <i>data</i> );	
<b>Description</b>	Writes an element to a LUT resource.	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>offset</i>	Offset to seek within the LUT prior to write
	<i>data</i>	New value of the element. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutReadEx	

---

## CorLutXor

Perform logical XOR operation on a LUT resource

<b>Prototype</b>	CORSTATUS <b>CorLutXor</b> (CORLUT <i>hLut</i> , CORDATA <i>k</i> );	
<b>Description</b>	Modifies the values of a LUT through the logical XOR operation, using a gray level of <i>k</i> . Each entry is calculated as follows: $lut[i] = lut[i] \text{ XOR } k$	
<b>Input</b>	<i>hLut</i>	LUT resource handle
	<i>k</i>	Constant. See Data Types for <i>CORDATA</i> definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorLutOr	

---

# Manager Module

The Manager Module allows the application to connect to other available resources (boards).

## CORMAN\_SAPERA\_VERSION\_INFO Structure Definition

```
typedef struct
{
    // Version number = major.minor.revision.build (for example, 6.12.01.0712)
    UINT32 major;
    UINT32 minor;
    UINT32 revision;
    UINT32 build;
    UINT32 licenseType;           // License type =
                                //     CORMAN_VAL_SAPERA_LICENSE_RUNTIME or
                                //     CORMAN_VAL_SAPERA_LICENSE_EVAL or
                                //     CORMAN_VAL_SAPERA_LICENSE_SDK
    UINT32 evalDaysRemaining;    // Number of days left for evaluation version
} CORMAN_SAPERA_VERSION_INFO, *PCORMAN_SAPERA_VERSION_INFO;
```

## Functions

Function	Description
CorManAllocContigBuffer	<i>Allocates a contiguous memory block</i>
CorManClose	<i>Closes the Sopera standard API</i>
CorManDetectAllServers	<i>Detects GenCP cameras after a Sopera application has been started</i>
CorManExecuteCmd	<i>Executes an application on a specified server</i>
CorManFreeContigBuffer	<i>Frees a contiguous memory block</i>
CorManGetHandleByIndex	<i>Gets a handle registered on a remote server by index.</i>
CorManGetHandleByName	<i>Gets a handle registered on a remote server from its name.</i>
CorManGetInstallationDirectory	<i>Gets full path of installation directory.</i>
CorManGetLocalServer	<i>Gets handle for local server</i>
CorManGetPixelDepthMax	<i>Returns the maximum number of significant bits per component for a data format</i>
CorManGetPixelDepthMin	<i>Returns the minimum number of significant bits per component for a data format</i>
CorManGetRemoteServerByName	<i>Gets the server handle corresponding to a specific name on a remote server</i>
CorManGetRemoteServerChild	<i>Gets the server handle corresponding to one child of a parent remote server.</i>
CorManGetRemoteServerParent	<i>Gets the server handle corresponding to the parent of one child remote server.</i>
CorManGetSoperaVersionInfo	<i>Gets Sopera LT version and license information</i>
CorManGetServerByIndex	<i>Gets server handle by index</i>
CorManGetServerByName	<i>Gets server handle from its name</i>
CorManGetServerCount	<i>Gets number of available servers</i>
CorManGetServerSerialNumber	<i>Gets the serial number for the specified server</i>
CorManGetStatusText	<i>Gets text for ID and info fields in status code</i>
CorManGetStatusTextEx	<i>Gets text for all fields in status code</i>
CorManGetStringFromFormat	<i>Gets a text description of a Sopera data format</i>
CorManIsBufferTypeSupported	<i>Identifies buffer types supported by an acquisition server</i>
CorManIsLocalHandle	<i>Checks for a local handle</i>
CorManIsServerAccessible	<i>Checks if a server is accessible in the server database</i>



CorManIsSystemHandle	<i>Checks for a System handle</i>
CorManLogMessage	<i>Adds a "printf-like" user string in the Sapera Log Viewer.</i>
CorManLogStatus	<i>Adds a predefined string corresponding to a status in the Sapera Log Viewer.</i>
CorManMapBuffer	<i>Maps a contiguous memory block in current process address space</i>
CorManOpen	<i>Initializes the Sapera standard API</i>
CorManRegisterCallback	<i>Registers a callback function to be called when receiving a user command</i>
CorManRegisterCallbackEx	<i>Registers a callback function to be called for server related events</i>
CorManRegisterHandle	<i>Adds a handle to the local handle database to allow other servers to access it</i>
CorManReleaseHandle	<i>Releases a handle obtained from CorManGetHandleByName or CorManGetHandleByIndex</i>
CorManReleaseServer	<i>Releases a server handle</i>
CorManResetServer	<i>Resets a server (hardware reset)</i>
CorManSetLocalServerName	<i>Sets name of local server</i>
CorManGetTimeout	<i>Gets communication time out</i>
CorManSetTimeout	<i>Sets communication time out</i>
CorManSoftResetServer	<i>Resets a server (software reset)</i>
CorManUnmapBuffer	<i>Unmaps a previously mapped contiguous memory block in current process address space</i>
CorManUnregisterCallback	<i>Unregisters the callback function to be called when receiving a user command</i>
CorManUnregisterCallbackEx	<i>Unregisters the callback function to be called for server related events</i>
CorManUnregisterHandle	<i>Removes a handle from the local handle database</i>
CorManUserCmd	<i>Sends a user command to a server</i>
CorManWaitForServerReady	<i>Waits until a given server is ready</i>
CorManWriteFile	<i>Returns the file transfer progress</i>

---

## CorManAllocContigBuffer

Allocate a contiguous memory block

<b>Prototype</b>	CORSTATUS <b>CorManAllocContigBuffer</b> (UINT32 <i>nBytes</i> , UINT32 * <i>physAddr</i> , void ** <i>addr</i> );	
<b>Description</b>	Allocates a block in contiguous memory. Contiguous memory is allocated as a single memory block in physical memory which is not pageable and not moveable.	
<b>Input</b>	<i>nBytes</i>	Number of bytes requested
<b>Output</b>	<i>physAddr</i>	Physical address
	<i>addr</i>	Virtual address
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>physAddr</i> or <i>addr</i> is NULL) and CORSTATUS_NO_MEMORY	
<b>See Also</b>	CorManFreeContigBuffer	

---

## CorManClose

Closes the Sapera standard API

<b>Prototype</b>	<code>CORSTATUS CorManClose(void);</code>
<b>Description</b>	Terminates all access to the standard C library. This must be the last Sapera call in an application program.
<b>Return Value</b>	<code>CORSTATUS_OK</code> <code>CORSTATUS_INSUFFICIENT_RESOURCES</code>
<b>Notes</b>	This function must not be called from the <code>DllMain</code> function of a Windows DLL
<b>See Also</b>	<code>CorManOpen</code>

---

## CorManDetectAllServers

Detects Sapera servers after an application has been started

<b>Prototype</b>	<code>CORSTATUS CorManDetectAllServers(UINT32 <i>serverType</i>);</code>
<b>Description</b>	<p>Use this function to detect GenCP cameras after a Sapera application has been started. In a typical application, device detection (discovery) is initiated during application startup. If a GenCP camera is connected after an application has been launched, it will not be detected automatically. Use this function to trigger the camera discovery process.</p> <p>Note that you must register the <code>CORMAN_VAL_EVENT_TYPE_SERVER_NEW</code> event before calling this function.</p>
<b>Input</b>	<p><i>serverType</i> Specifies the type of server to detect. Currently, the only possible value is:</p> <ul style="list-style-type: none"><li><code>CORMAN_VAL_DETECTION_SERVER_TYPE_GENCP</code>: Detect GenCP servers only</li></ul>
<b>Return Value</b>	<code>CORSTATUS_OK</code> <code>CORSTATUS_INSUFFICIENT_RESOURCES</code>
<b>Notes</b>	This function has no effect for GigE-Vision cameras, for which simply registering the <code>CORMAN_VAL_EVENT_TYPE_SERVER_NEW</code> event is sufficient
<b>See Also</b>	<code>CorManRegisterCallback</code> , <code>CorManRegisterCallbackEx</code>

---

## CorManExecuteCmd

Executes an application on a specified server

<b>Prototype</b>	<code>CORSTATUS CorManExecuteCmd(CORSERVER hServer, const char <i>szCmdLine</i>[])</code>
<b>Description</b>	Executes a command line application on a remote server. For example, this function can run a user application on a processing board.
<b>Input</b>	<p><i>hServer</i> Board server handle</p> <p><i>szCmdLine</i> String containing the application name to execute (including any application arguments)</p>
<b>Return Value</b>	<code>CORSTATUS_OK</code> <code>CORSTATUS_NO_MEMORY</code> , <code>CORSTATUS_ARG_INVALID</code> , <code>CORSTATUS_INVALID_HANDLE</code> , <code>CORSTATUS_SERVER_NOT_FOUND</code> , <code>CORSTATUS_TIMEOUT</code> and <code>CORSTATUS_BOARD_NOT_READY</code>
<b>Notes</b>	The executed application uses the environment variables (for example, <code>PATH</code> ) defined in the remote server's system.

---

## CorManFreeContigBuffer

Free a contiguous memory buffer

<b>Prototype</b>	CORSTATUS <b>CorManFreeContigBuffer</b> (void * <i>addr</i> );
<b>Description</b>	Frees a contiguous memory block. Contiguous memory is allocated as a single memory block in physical memory which is not pageable and not moveable.
<b>Input</b>	<i>addr</i> Virtual address
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>addr</i> is NULL) and CORSTATUS_ARG_INVALID
<b>See Also</b>	CorManAllocContigBuffer

---

## CorManGetHandleByIndex

Gets a handle registered on a remote server by index.

<b>Prototype</b>	CORSTATUS <b>CorManGetHandleByIndex</b> (CORSERVER <i>hServer</i> , UINT32 <i>index</i> , PCORHANDLE <i>pHandle</i> );
<b>Description</b>	Gets a handle from a remote server's handle database by index. The handle must have been previously registered using CorManRegisterHandle on the remote server.
<b>Input</b>	<i>hServer</i> Handle to the remote server where the handle is registered. <i>index</i> Index to the remote server's handle database.
<b>Output</b>	<i>pHandle</i> Pointer to a handle.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>pHandle</i> is NULL) and CORSTATUS_NOT_ACCESSIBLE
<b>See Also</b>	CorManRegisterHandle, CorManGetHandleByName and CorManReleaseHandle

---

## CorManGetHandleByName

Gets a handle registered on a remote server from its name.

<b>Prototype</b>	CORSTATUS <b>CorManGetHandleByName</b> (CORSERVER <i>hServer</i> , PSTR <i>name</i> , PCORHANDLE <i>pHandle</i> );
<b>Description</b>	Gets a handle from a remote server's handle database from its name. The handle must have been previously registered using CorManRegisterHandle on the remote server.
<b>Input</b>	<i>hServer</i> Handle to the remote server on which to get the handle. <i>name</i> Name of the handle in the remote server's handle database.
<b>Output</b>	<i>pHandle</i> Pointer to a handle.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>name</i> or <i>pHandle</i> is NULL) CORSTATUS_NOT_ACCESSIBLE
<b>See Also</b>	CorManRegisterHandle, CorManGetHandleByIndex and CorManReleaseHandle

---

## CorManGetInstallationDirectory

Gets full path of installation directory

<b>Prototype</b>	CORSTATUS <b>CorManGetInstallationDirectory</b> (CORSERVER <i>hServer</i> , PSTR <i>pInstallDir</i> , UINT32 <i>strSize</i> );	
<b>Description</b>	Gets the directory where Sapera LT or a Sapera driver is installed.	
<b>Input</b>	<i>hServer</i>	Handle of Sapera LT system server or Sapera board server.
	<i>strSize</i>	Size of buffer for storing the installation directory.
<b>Output</b>	<i>pInstallDir</i>	Product installation directory (for example, "c:\Program Files\Teledyne DALSA\Sapera").
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL	
<b>See Also</b>	CorManGetLocalServer, CorManGetServerByIndex and CorManGetServerByName	

---

## CorManGetLocalServer

Get handle for local server

<b>Prototype</b>	CORSERVER <b>CorManGetLocalServer</b> ();	
<b>Description</b>	Gets server handle corresponding to current process.	
<b>Input</b>	None	
<b>Output</b>	None	
<b>Return Value</b>	Local server handle	
<b>Notes</b>	Under Win32, the returned server handle may not be the same as the one you get when you use CorManGetServerByName for the local system.	
<b>See Also</b>	CorManGetServerByName	

---

## CorManGetPixelDepthMax

Gets the maximum pixel depth

<b>Prototype</b>	UINT32 <b>CorManGetPixelDepthMax</b> (UINT32 <i>format</i> );	
<b>Description</b>	Returns the maximum number of significant bits per component for a data format. This value is documented for each data format in the Data Formats section.	
<b>Input</b>	<i>format</i>	Data format (Refer to Data Formats section for a detailed list).
<b>Output</b>	None	
<b>Return Value</b>	The maximum number of bits per component.	
<b>See Also</b>	CORBUFFER_PRM_PIXEL_DEPTH	

---

## CorManGetPixelDepthMin

Gets the minimum pixel depth

<b>Prototype</b>	UINT32 <b>CorManGetPixelDepthMin</b> (UINT32 <i>format</i> );	
<b>Description</b>	Returns the minimum number of significant bits per component for a data format. This value is documented for each data format in the Data Formats section.	
<b>Input</b>	<i>format</i>	Data format (Refer to Data Formats section for a detailed list).
<b>Output</b>	None	
<b>Return Value</b>	The minimum number of bits per component.	
<b>See Also</b>	CORBUFFER_PRM_PIXEL_DEPTH	

---

## CorManGetRemoteServerByName

Get the server handle from a specific remote server name

<b>Prototype</b>	CORSTATUS <b>CorManGetServerByName</b> (CORSERVER <i>hRemoteServer</i> , const char * <i>name</i> , CORSERVER * <i>hServer</i> );	
<b>Description</b>	Gets the server handle corresponding to a specific name on a remote server Use this function to get from another Win32 system a handle to a server corresponding to an individual Win32 process (not listed in the Sapera Server database). You first need to create an alias for this server from its own process on the remote system.	
<b>Input</b>	<i>hRemoteServer</i>	Remote server handle
	<i>name</i>	Server name
<b>Output</b>	<i>hServer</i>	Server handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID and CORSTATUS_SERVER_NOT_FOUND	
<b>See Also</b>	erName	

---

## CorManGetRemoteServerChild

Get the child server handle from a remote parent server

<b>Prototype</b>	CORSTATUS <b>CorManGetRemoteServerChild</b> (CORSERVER <i>hServer</i> , UINT8 <i>nChild</i> , PCORSERVER <i>handle</i> )	
<b>Description</b>	This function obtains the child server handle via the parent server handle. Useful for boards with multiple processors. For example the Python board contains one parent server (Python_1) and four child processors (Python_1_C60.. Python_4_C60). This function allows you to obtain any child server handle without specifying the name of that specific child server.	
<b>Input</b>	<i>hServer</i>	Parent server handle
	<i>nChild</i>	Child server index (1..N) where N is the number of child servers on the parent board.
<b>Output</b>	<i>handle</i>	Child server handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID and CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorManGetRemoteServerParent	

---

## CorManGetRemoteServerParent

Get the parent server handle from a remote child server

<b>Prototype</b>	CORSTATUS <b>CorManGetRemoteServerParent</b> (CORSERVER <i>hServer</i> , PCORSERVER <i>handle</i> )	
<b>Description</b>	This function obtains the parent server handle via the handle of one of its child servers. Useful on boards with multiple processors. For example the Python board contains one parent server (Python_1) and four child processors (Python_1_C60.. Python_4_C60). This function allows you to obtain the parent server handle without specifying the name of the parent.	
<b>Input</b>	<i>hServer</i>	Child server handle
<b>Output</b>	<i>handle</i>	Parent server handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID and CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorManGetRemoteServerChild	

---

## CorManGetSaperaVersionInfo

Get Sapera LT version and license information

<b>Prototype</b>	CORSTATUS <b>CorManGetSaperaVersionInfo</b> (PCORMAN_SAPERA_VERSION_INFO <i>pVersionInfo</i> );
<b>Description</b>	Use this function to retrieve the current Sapera LT version number, and to identify whether it is a runtime, evaluation, or full SDK installation.
<b>Output</b>	<i>pVersionInfo</i> Version information structure. See CORMAN_SAPERA_VERSION_INFO structure definition.
<b>Return Value</b>	CORSTATUS_OK, CORSTATUS_ARG_INVALID

---

## CorManGetServerByIndex

Get server handle by index

<b>Prototype</b>	CORSTATUS <b>CorManGetServerByIndex</b> (UINT32 <i>index</i> , char * <i>name</i> , CORSERVER * <i>hServer</i> );
<b>Description</b>	Use this function to retrieve handles for servers listed in the Sapera Server database.
<b>Input</b>	<i>index</i> Specifies which server to get. Valid values are in the range [0... <i>count</i> -1], where <i>count</i> is the value returned by CorManGetServerCount.
<b>Output</b>	<i>name</i> Server name Server names are limited to 30 characters. If this argument is NULL, the server name won't be returned. <i>hServer</i> Server handle. If this argument is NULL, the handle won't be returned, which is useful if only the server name is needed.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_SERVER_NOT_FOUND
<b>Notes</b>	Use the Sapera configuration program to obtain a list of all available servers in your system and their names.
<b>See Also</b>	CorManGetServerCount, CorManGetServerByName and CorManReleaseServer

---

## CorManGetServerByName

Get server handle from its name

<b>Prototype</b>	CORSTATUS <b>CorManGetServerByName</b> (const char * <i>name</i> , CORSERVER * <i>server</i> );
<b>Description</b>	Gets server handle from its name.
<b>Input</b>	<i>name</i> Server name
<b>Output</b>	<i>server</i> Server handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID, CORSTATUS_SERVER_NOT_FOUND
<b>Notes</b>	Use the Sapera configuration program to obtain a list of all available servers in your system and their names.  Use this function to retrieve handles both for servers listed in the Sapera Server database and for those corresponding to individual processes. For the latter, use an alias you created previously for this server from its own process.
<b>See Also</b>	CorManGetServerByIndex erName CorManReleaseServer

---

## CorManGetServerCount

Get the number of available server

<b>Prototype</b>	CORSTATUS <b>CorManGetServerCount</b> (UINT32 <i>*count</i> );
<b>Description</b>	Gets the number of available servers.
<b>Input</b>	None
<b>Output</b>	<i>count</i> Number of available servers
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_OK
<b>Notes</b>	Use the Spera configuration program to obtain a list of all available servers in your system. This function returns the number of servers currently listed in the Spera Server database, it does not include those associated to individual Win32 processes.
<b>See Also</b>	CorManGetServerByIndex

---

## CorManGetServerSerialNumber

Gets the serial number for the specified server.

<b>Prototype</b>	CORSTATUS <b>CorManGetServerSerialNumber</b> (CORSERVER <i>hServer</i> , PSTR <i>serial</i> );
<b>Description</b>	Gets the serial number for the specified Spera Server. This number is assigned by Teledyne DALSA and programmed into the EEPROM of the board associated with the server.
<b>Input</b>	<i>hServer</i> Handle to the server.
<b>Output</b>	<i>serial</i> Character string that receives the resulting information in the format seen within the board's Viewer window. The first letter is either an "S" or an "H" followed by seven numbers, for example, 'S1234567'. Make certain that the string is long enough for the serial number plus the terminating NULL character.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>serial</i> is NULL) CORSTATUS_ARG_INVALID
<b>Notes</b>	There is no serial number associated with the System server. This function is only supported for frame grabbers and older Genie cameras (not Genie-TS). When using other camera servers (GigE-Vision or GenCP), you need a valid CorAcqDevice object from which the serial number can be retrieved through a named feature.
<b>See Also</b>	CorManGetServerByIndex and CorManGetServerByName

---

## CorManGetStatusText

Get text strings for "ID" and "info" fields of a given status value

<b>Prototype</b>	CORSTATUS <b>CorManGetStatusText</b> (CORSTATUS <i>status</i> , char <i>*idBuf</i> , UINT32 <i>idBufSize</i> , char <i>*infoBuf</i> , UINT32 <i>infoBufSize</i> );
<b>Description</b>	Gets text strings for "ID" and "info" fields of a given status value.
<b>Input</b>	<i>Status</i> Status value <i>idBufSize</i> ID buffer size <i>infoBufSize</i> Information buffer size
<b>Output</b>	<i>idBuf</i> ID string <i>infoBuf</i> Information string
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE

---

## CorManGetStatusTextEx

Get text strings for all the fields of a given status value

<b>Prototype</b>	CORSTATUS <b>CorManGetStatusTextEx</b> (CORSTATUS <i>status</i> , char * <i>idBuf</i> , UINT32 <i>idBufSize</i> , char * <i>infoBuf</i> , UINT32 <i>infoBufSize</i> , char * <i>levelBuf</i> , UINT32 <i>levelBufSize</i> , char * <i>moduleBuf</i> , UINT32 <i>moduleBufSize</i> );	
<b>Description</b>	Gets text strings for all the fields (ID, Info, Level, and Module) of a given status value.	
<b>Input</b>	<i>status</i>	Status value
	<i>idBufSize</i>	ID buffer size
	<i>infoBufSize</i>	Information buffer size
	<i>levelBufSize</i>	Level buffer size
	<i>moduleBufSize</i>	Module buffer size
<b>Output</b>	<i>idBuf</i>	ID string
	<i>infoBuf</i>	Information string
	<i>levelBuf</i>	Level string
	<i>moduleBuf</i>	Module string
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE	

---

## CorManGetStringFromFormat

Get a text description of a Sopera data format

<b>Prototype</b>	BOOL <b>CorManGetSringFromFormat</b> (UINT32 <i>format</i> , char * <i>szFormat</i> );	
<b>Description</b>	Get an identification string for the Sopera data format, for example, 'RGB888'	
<b>Input</b>	<i>format</i>	Sopera data format
<b>Output</b>	<i>szFormat</i>	String description, set to '(unknown)' if the format is unrecognized
<b>Return Value</b>	TRUE if a non-NULL string argument is specified , FALSE otherwise	

---

## CorManGetTimeout

Get communication timeout

<b>Prototype</b>	UINT32 <b>CorManGetTimeout</b> ();	
<b>Description</b>	Gets communication timeout.	
<b>Input</b>	None	
<b>Output</b>	None	
<b>Return Value</b>	Communication timeout in milliseconds.	



---

## CorManIsBufferTypeSupported

Identifies buffer types supported by an acquisition server

<b>Prototype</b>	CORSTATUS <b>CorManIsBufferTypeSupported</b> (CORSERVER <i>hServer</i> , UINT32 <i>bufType</i> , PUINT32 <i>isSupported</i> );	
<b>Description</b>	Checks if an acquisition server supports data transfers to a specific buffer type	
<b>Input</b>	<i>hServer</i>	Handle of Sapera LT acquisition server.
	<i>bufType</i>	Type of buffer to check, see CorBufferNew for a list of possible values
<b>Output</b>	<i>isSupported</i>	TRUE if the buffer type is supported, FALSE otherwise
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_NOT_IMPLEMENTED	
<b>Notes</b>	For most acquisition hardware, the return value is CORSTATUS_NOT_IMPLEMENTED, so it is not possible to determine if the buffer type is supported. In this case, an error will be returned by the CorXferConnect (or CorXferConnectEx) function when trying to set up a transfer to an unsupported buffer type.	
<b>See Also</b>	CorBufferNew, CorXferConnect, CorXferConnectEx	

---

## CorManIsLocalHandle

Check for a local handle

<b>Prototype</b>	BOOLEAN <b>CorManIsLocalHandle</b> (CORHANDLE <i>handle</i> );	
<b>Description</b>	Checks for a handle belonging to the local server.	
<b>Input</b>	<i>handle</i>	Sapera handle
<b>Output</b>	None	
<b>Return Value</b>	TRUE if handle is a local handle, FALSE otherwise	

---

## CorManIsServerAccessible

Checks if a server is accessible in the server database

<b>Prototype</b>	BOOLEAN <b>CorManIsServerAccessible</b> (UINT32 <i>index</i> );	
<b>Description</b>	<p>Checks if the resources belonging to a server are currently accessible. Although existing handles for these resources are still valid when their server becomes inaccessible, they must be left alone or released (for example, CorAcqDeviceRelease).</p> <p>When a Sapera application starts, all detected servers are automatically accessible. However, some Sapera camera devices (GigE-Vision and GenCP) can be connected and disconnected while a Sapera application is running. When such a device is connected for the first time, its server is automatically accessible. When the device is later disconnected, the server becomes inaccessible. If it is reconnected again, the server is once again accessible.</p> <p>Accessibility of servers can also be determined by registering callbacks for server related events using CorManRegisterCallbackEx.</p> <p>Note that you should not use this function for devices which are always connected (for example, frame grabbers), since the return value may not correspond to the actual resource accessibility for the corresponding server.</p>	
<b>Input</b>	<i>index</i>	Server index
<b>Output</b>	None	
<b>Return Value</b>	TRUE if server is accessible, FALSE otherwise	
<b>See Also</b>	CorManRegisterCallbackEx	

---

## CorManIsSystemHandle

Check for a system handle

<b>Prototype</b>	BOOLEAN <b>CorManIsSystemHandle</b> (CORHANDLE <i>handle</i> );
<b>Description</b>	Checks for a handle belonging to the 'System' server.
<b>Input</b>	<i>handle</i> SAPERA handle
<b>Output</b>	None
<b>Return Value</b>	TRUE if handle is a System handle, FALSE otherwise

---

## CorManLogMessage

Appends a “printf-like” user string to the Sapera Log Viewer output

<b>Prototype</b>	CORSTATUS <b>CorManLogMessage</b> (UINT32 <i>logtype</i> , PCSTR <i>msg</i> , PCSTR <i>file</i> , UINT32 <i>line</i> )
<b>Description</b>	This function allows the appended user string to implement formatting as available with the <i>printf</i> function so as to display any data type.
<b>Input</b>	<i>logtype</i> Error level: CORLOG_TYPEID_ERR (Normal error) CORLOG_TYPEID_FAT (Fatal error) CORLOG_TYPEID_WRN        (Warning) CORLOG_TYPEID_INF (Information)  <i>msg</i> A “printf-like” string containing the message to display. <i>file</i> String containing the file name in which the error occurred. The macro <code>__FILE__</code> can be used to specify the current file.  <i>line</i> Line number where the error occurred. The macro <code>__LINE__</code> can be used to specify the current line.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK and CORSTATUS_ARG_NULL

---

## CorManLogStatus

Appends a predefined status string to the Sapera Log Viewer output

<b>Prototype</b>	CORSTATUS <b>CorManLogStatus</b> (CORSTATUS <i>status</i> , PCSTR <i>file</i> , UINT32 <i>line</i> )
<b>Description</b>	The appended string is composed with three different status fields. This function does not allow custom formatting. A custom message can be appended by extracting the required status fields with <i>CorManGetStatusTextEx</i> , and then formatted using <i>CorManLogMessage</i> .
<b>Input</b>	<i>status</i> Error status returned by any Sapera function. <i>file</i> String containing the file name in which the error occurred. The macro <code>__FILE__</code> can be used to specify the current file.  <i>line</i> Line number where the error occurred. The macro <code>__LINE__</code> can be used to specify the current line.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK and CORSTATUS_ARG_NULL
<b>See Also</b>	CorManGetStatusTextEx

---

## CorManMapBuffer

Map a contiguous memory block in current process address space

<b>Prototype</b>	CORSTATUS <b>CorManMapBuffer</b> (UINT32 <i>physAddr</i> , UINT32 <i>size</i> , void ** <i>virtualAddr</i> );	
<b>Description</b>	Maps a contiguous memory block in current process address space	
<b>Input</b>	<i>physAddr</i>	Physical address of a contiguous memory block
	<i>size</i>	Contiguous memory block size in bytes
<b>Output</b>	<i>virtualAddr</i>	Virtual address of the contiguous memory block
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_NO_MEMORY	
<b>Note</b>	To unmap a previously mapped contiguous memory block use CorManUnmapBuffer.	
<b>See Also</b>	CorManUnmapBuffer	

---

## CorManOpen

Initializes the Sapera standard API

<b>Prototype</b>	CORSTATUS <b>CorManOpen</b> (void);	
<b>Description</b>	Initiates access to the standard C library. This must be the first Sapera call in an application program.	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INSUFFICIENT_RESOURCES	
<b>Notes</b>	This function must not be called from the DllMain function of a Windows DLL	
<b>See Also</b>	CorManClose	

---

## CorManRegisterCallback

Register a callback function to be called when receiving a user command

<b>Prototype</b>	CORSTATUS <b>CorManRegisterCallback</b> (CORSERVER <i>hServer</i> , PCORMANCALLBACK <i>callback</i> );	
<b>Description</b>	Registers a callback function to be called when receiving a user command	
<b>Input</b>	<i>hServer</i>	Server handle.
	<i>callback</i>	Callback function to call
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>Note</b>	The callback function must be defined as: CORSTATUS CCONV callbackFct( UINT32 cmd, void *inData, UINT32 inDataSize, void *outData, UINT32 outDataSize);	
<b>See Also</b>	CorManUnregisterCallback and CorManUserCmd	

---

## CorManRegisterCallbackEx

Register a callback function for server related events

**Prototype**      `CORSTATUS CorManRegisterCallbackEx(UINT32 eventType, PCOREVENTINFOCALLBACK callback, void *context);`

**Description**      Registers a callback function for server related events. The callback function provides information on the corresponding event (in the *COREVENTINFO* handle). Refer to the *EventInfo* module for more detail on the available information. The context pointer is also returned by the callback function allowing you to exchange user information between the callback and your application context.

Note that server related events are only available when dealing with Sapera camera devices (GigE-Vision and GenCP), that can be connected and disconnected while a Sapera application is running.

**Input**              *eventType*      Type of event to register. The callback function will be called when the specified event(s) occur. The values may be ORed if more than one event is desired.

The CORMAN\_VAL\_EVENT\_TYPE\_SERVER\_NEW event occurs when a new device is connected while a Sapera application is already running.

The CORMAN\_VAL\_EVENT\_TYPE\_SERVER\_DISCONNECTED event occurs when the device corresponding to an existing server is disconnected (replaces CORMAN\_VAL\_EVENT\_TYPE\_SERVER\_NOT\_ACCESSIBLE, which is now deprecated).

The CORMAN\_VAL\_EVENT\_TYPE\_SERVER\_CONNECTED event occurs when the device corresponding to an existing, unaccessible server is reconnected (replaces CORMAN\_VAL\_EVENT\_TYPE\_SERVER\_ACCESSIBLE, which is now deprecated).

The CORMAN\_VAL\_EVENT\_TYPE\_SERVER\_DATABASE\_FULL event occurs when there is no room left in the Sapera server database for a new device that has just been connected.

*callback*              Address of a user callback function of the following form:

```
CORSTATUS CCONV MyCallback(void *context, COREVENTINFO hEventInfo)
{
}
```

*context*              Pointer to user storage (that is, variable, structure, buffer, etc). Can be NULL.

**Output**              None              In the callback function, obtain the event type that triggered the callback by reading COREVENTINFO\_PRM\_EVENT\_TYPE.

For all events except the last, you can obtain a handle to the server by calling *CorManGetServerByIndex* using the server index specified by COREVENTINFO\_PRM\_SERVER\_INDEX.

**Return Value**      CORSTATUS\_OK  
CORSTATUS\_ARG\_NULL (if *callback* is NULL), CORSTATUS\_NOT\_AVAILABLE,  
CORSTATUS\_RESOURCE\_IN\_USE, CORSTATUS\_TIMEOUT

**Notes**

**See Also**              *CorManIsServerAccessible*, *CorManRegisterCallbackEx*

---

## CorManRegisterHandle

Adds a handle to the local handle database to allow other servers to access it.

<b>Prototype</b>	CORSTATUS <b>CorManRegisterHandle</b> (CORHANDLE <i>handle</i> , PSTR <i>name</i> , PUINT32 <i>pIndex</i> );	
<b>Description</b>	By registering a handle using this function you allow all other servers to get this handle through CorManGetHandleByIndex or CorManGetHandleByName.	
<b>Input</b>	<i>handle</i>	handle to register.
	<i>name</i>	Name to give the handle in the database. If NULL, a default name "Handle_X" is given, where "X" corresponds to the index returned by <i>pIndex</i> (for example, Handle_0, Handle_1, ...).
<b>Output</b>	<i>pIndex</i>	Index in the handle database where the handle is added. Can be NULL.
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorManUnregisterHandle, CorManGetHandleByIndex and CorManGetHandleByName	

---

## CorManReleaseHandle

Releases a handle obtained from *CorManGetHandleByName* or *CorManGetHandleByIndex*.

<b>Prototype</b>	CORSTATUS <b>CorManReleaseHandle</b> (CORHANDLE <i>handle</i> );	
<b>Description</b>	Releases a handle obtained from <i>CorManGetHandleByName</i> or <i>CorManGetHandleByIndex</i> .	
<b>Input</b>	<i>handle</i>	Handle to release.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorManGetHandleByIndex and CorManGetHandleByName	

---

## CorManReleaseServer

Release server handle

<b>Prototype</b>	CORSTATUS <b>CorManReleaseServer</b> (CORSERVER <i>hServer</i> );	
<b>Description</b>	Releases server handle.	
<b>Input</b>	<i>hServer</i>	Server handle.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorManGetLocalServer, CorManGetRemoteServerByName, CorManGetServerByIndex and CorManGetServerByName	

---

## CorManResetServer

Resets server (hardware reset)

<b>Prototype</b>	CORSTATUS <b>CorManResetServer</b> (CORSERVER <i>hServer</i> );
<b>Description</b>	Performs a hardware reset on a server.
<b>Input</b>	<i>hServer</i> Server handle.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>Notes</b>	After calling this function, all resources from the server cannot be used anymore; they must be released first.

---

## CorManSetLocalServerName

Set local server name

<b>Prototype</b>	CORSTATUS <b>CorManSetLocalServerName</b> ( const char * <i>serverName</i> );
<b>Description</b>	Sets a new name for the server corresponding to current process
<b>Input</b>	<i>serverName</i> New name for local server
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( <i>if serverName is NULL</i> ) CORSTATUS_RESOURCE_LOCKED
<b>Note</b>	Defines an alias for the server corresponding to the current process, so that its handle can be retrieved from a remote server.
<b>See Also</b>	CorManGetLocalServer and CorManGetRemoteServerByName

---

## CorManSoftResetServer

Resets server (software reset)

<b>Prototype</b>	CORSTATUS <b>CorManSoftResetServer</b> (CORSERVER <i>hServer</i> );
<b>Description</b>	Performs a software reset on a server.
<b>Input</b>	<i>hServer</i> Server handle.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>Notes</b>	After calling this function, all resources from the server cannot be used anymore; they must be released first.

---

## CorManSetTimeout

Set communication timeout

<b>Prototype</b>	void <b>CorManSetTimeout</b> (UINT32 <i>timeOut</i> );
<b>Description</b>	Sets communication timeout.
<b>Input</b>	<i>timeOut</i> Communication timeout in milliseconds.
<b>Output</b>	None
<b>Return Value</b>	(none; function has void return type)

---

## CorManUnmapBuffer

Unmap a contiguous memory block in current process address space

<b>Prototype</b>	CORSTATUS <b>CorManUnmapBuffer</b> ( void * <i>virtualAddr</i> );
<b>Description</b>	Unmaps a contiguous memory block in current process address space
<b>Input</b>	<i>virtualAddr</i> Previously mapped virtual address to be unmapped.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( <i>if virtualAddr is NULL</i> )
<b>See Also</b>	CorManMapBuffer

---

## CorManUnregisterCallback

Unregister the callback function to be called when receiving a user command

<b>Prototype</b>	CORSTATUS <b>CorManUnregisterCallback</b> (CORSERVER <i>hServer</i> );
<b>Description</b>	Unregisters the callback function to be called when receiving a user command
<b>Input</b>	<i>hServer</i> Server handle.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorManRegisterCallback and CorManUserCmd

---

## CorManUnregisterCallbackEx

Unregister the callback function for server related events

<b>Prototype</b>	CORSTATUS <b>CorManUnregisterCallbackEx</b> (void);
<b>Description</b>	Unregisters the callback function for server related events.
<b>Input</b>	None
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_TIMEOUT
<b>See Also</b>	CorManRegisterCallbackEx

---

## CorManUnregisterHandle

Removes a handle from the local handle database

<b>Prototype</b>	CORSTATUS <b>CorManUnregisterHandle</b> (CORHANDLE <i>handle</i> );
<b>Description</b>	Removes a handle from the local handle database. This function must be used to remove a handle previously added by <i>CorManRegisterHandle</i> .
<b>Input</b>	<i>handle</i> Handle to unregister.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorManRegisterHandle

---

## CorManUserCmd

Send a user command to a remote server

<b>Prototype</b>	CORSTATUS <b>CorManUserCmd</b> (CORSERVER <i>hServer</i> , UINT32 <i>cmd</i> , void * <i>inData</i> , UINT32 <i>inDataSize</i> , void * <i>outData</i> , UINT32 <i>outDataSize</i> );	
<b>Description</b>	Sends a user command to a server. To receive a user command, use CorManRegisterCallback to register a callback function to be called when receiving a user command from a server. To unregister the callback function use CorManUnregisterCallback.	
<b>Input</b>	<i>hServer</i>	Server handle.
	<i>cmd</i>	User command number ( 0 .. 65536).
	<i>inData</i>	Input data.
	<i>inDataSize</i>	Input data size in bytes.
	<i>outData</i>	Output data.
	<i>outDataSize</i>	Output data size in bytes.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE	
<b>Note</b>	<i>inData</i> allows data to be sent along with the user command to the registered callback function; <i>outData</i> allows data to be received resulting from the execution of the user command. Both <i>inData</i> and <i>outData</i> can be specified as <i>NULL</i> .	
<b>See Also</b>	CorManRegisterCallback CorManUnregisterCallback	

---

## CorManWaitForServerReady

Wait until a given server is ready

<b>Prototype</b>	CORSTATUS <b>CorManWaitForServerReady</b> (CORSERVER <i>hServer</i> , UINT32 <i>timeOut</i> );	
<b>Description</b>	Waits until a given server is ready. The function returns CORSTATUS_OK as soon as the server is ready, or with CORSTATUS_TIMEOUT if the <i>timeOut</i> seconds have elapsed.	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>timeOut</i>	Maximum time (in seconds) to wait
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_TIMEOUT	
<b>See Also</b>	CorManGetServerByIndex and CorManGetServerByName	

---

## CorManWriteFile

Returns the file transfer progress

<b>Prototype</b>	CORSTATUS <b>CorManWriteFile</b> (CORSERVER <i>hServer</i> , PCSTR <i>localFileName</i> UINT32 <i>deviceFileIndex</i> );	
<b>Description</b>	Returns the file transfer progress, as a percentage of the file size, when transferring a file to non-volatile memory on a device. See the acquisition device User's Manual for the list of supported files.	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>localFileName</i>	Name of the device file. See the acquisition device User's Manual for the list of supported files.
	<i>deviceFileIndex</i>	Index of the file. All indices in the range from 0 to the value returned by the GetFileCount method, minus 1, are valid.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
<b>See Also</b>	CorManGetServerByIndex and CorManGetServerByName	



---

# Transfer Module

The Transfer Module is responsible for moving data between various sources and destinations.

## Capabilities

ID	Capability
0x00	<i>Reserved</i>
0x01	CORXFER_CAP_EVENT_TYPE
0x02	CORXFER_CAP_CROP_HORZ
0x03	CORXFER_CAP_CROP_LEFT_MIN
0x04	CORXFER_CAP_CROP_LEFT_MAX
0x05	CORXFER_CAP_CROP_LEFT_MULT
0x06	CORXFER_CAP_CROP_VERT
0x07	CORXFER_CAP_CROP_TOP_MIN
0x08	CORXFER_CAP_CROP_TOP_MAX
0x09	CORXFER_CAP_CROP_TOP_MULT
0x0a	CORXFER_CAP_CROP_WIDTH_MIN
0x0b	CORXFER_CAP_CROP_WIDTH_MAX
0x0c	CORXFER_CAP_CROP_WIDTH_MULT
0x0d	CORXFER_CAP_CROP_HEIGHT_MIN
0x0e	CORXFER_CAP_CROP_HEIGHT_MAX
0x0f	CORXFER_CAP_CROP_HEIGHT_MULT
0x10	CORXFER_CAP_SCALE_HORZ_METHOD
0x11	CORXFER_CAP_SCALE_HORZ_MIN
0x12	CORXFER_CAP_SCALE_HORZ_MAX
0x13	CORXFER_CAP_SCALE_HORZ_MULT
0x14	CORXFER_CAP_SCALE_HORZ_MIN_FACTOR
0x15	CORXFER_CAP_SCALE_HORZ_MAX_FACTOR
0x16	CORXFER_CAP_SCALE_VERT_METHOD
0x17	CORXFER_CAP_SCALE_VERT_MIN
0x18	CORXFER_CAP_SCALE_VERT_MAX
0x19	CORXFER_CAP_SCALE_VERT_MULT
0x1a	CORXFER_CAP_SCALE_VERT_MIN_FACTOR
0x1b	CORXFER_CAP_SCALE_VERT_MAX_FACTOR
0x1c	CORXFER_CAP_COUNTER_STAMP_EVENT_TYPE
0x1d	CORXFER_CAP_MAX_XFER_SIZE
0x1e	CORXFER_CAP_SCALE_HORZ
0x1f	CORXFER_CAP_SCALE_VERT
0x20	CORXFER_CAP_FLIP
0x21	CORXFER_CAP_NB_INT_BUFFERS
0x22	CORXFER_CAP_EVENT_COUNT_SOURCE
0x23	CORXFER_CAP_MAX_FRAME_COUNT
	<i>Reserved</i>
0x25	CORXFER_CAP_COUNTER_STAMP_AVAILABLE
0x26	CORXFER_CAP_COUNTER_STAMP_TIME_BASE
0x27	CORXFER_CAP_COUNTER_STAMP_MAX

0x28	CORXFER_CAP_CYCLE_MODE
0x29	CORXFER_CAP_FLATFIELD
0x2d	CORXFER_CAP_PROCESSING_MODE
0x30	CORXFER_CAP_BUFFER_TIMESTAMP_MODULE_ACQ
0x31	CORXFER_CAP_BUFFER_TIMESTAMP_EVENT_ACQ
0x32	CORXFER_CAP_BUFFER_TIMESTAMP_MODULE_XFER
0x33	CORXFER_CAP_BUFFER_TIMESTAMP_EVENT_XFER
0x34	CORXFER_CAP_LINE_MERGING
0x35	CORXFER_CAP_EVENT_TYPE_EX
0x36	CORXFER_CAP_LEVEL_EVENT_TYPE

---

### **CORXFER\_CAP\_BUFFER\_TIMESTAMP\_EVENT\_ACQ**

<b>Description</b>	Available events from the acquisition module
<b>Type</b>	UINT32
<b>Values</b>	CORACQ_VAL_EVENT_TYPE_EXTERNAL_TRIGGER (0x01000000) CORACQ_VAL_EVENT_TYPE_START_OF_FRAME (0x00080000) CORACQ_VAL_EVENT_TYPE_END_OF_FRAME (0x00800000).
<b>Note</b>	See CORXFER_PRM_BUFFER_TIMESTAMP_EVENT. The returned value is the ORed combination of the valid values

---

### **CORXFER\_CAP\_BUFFER\_TIMESTAMP\_MODULE\_ACQ**

<b>Description</b>	Specifies if the acquisition module supports host buffer timestamps.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, host timestamp is available. FALSE, host timestamp is not available.
<b>Note</b>	See CORXFER_PRM_BUFFER_TIMESTAMP_EVENT and CORBUFFER_PRM_.

---

### **CORXFER\_CAP\_BUFFER\_TIMESTAMP\_EVENT\_XFER**

<b>Description</b>	Available events from the transfer module.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_EVENT_TYPE_START_OF_FRAME (0x00080000) CORXFER_VAL_EVENT_TYPE_END_OF_FRAME (0x00800000).
<b>Note</b>	See CORXFER_PRM_BUFFER_TIMESTAMP_EVENT and CORBUFFER_PRM_. The returned value is the ORed combination of the valid values.

---

### **CORXFER\_CAP\_BUFFER\_TIMESTAMP\_MODULE\_XFER**

<b>Description</b>	Specifies if the transfer module supports host buffer timestamps.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, host timestamp is available. FALSE, host timestamp is not available.
<b>Note</b>	See CORXFER_PRM_BUFFER_TIMESTAMP_EVENT and CORBUFFER_PRM_.

---

**CORXFER\_CAP\_COUNTER\_STAMP\_AVAILABLE**

<b>Description</b>	Specifies if the transfer resource supports a counter stamp.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, Counter stamp is available. FALSE, Counter stamp is not available.

---

**CORXFER\_CAP\_COUNTER\_STAMP\_MAX**

<b>Description</b>	Specifies the maximum value for the counter stamp
<b>Type</b>	UINT32
<b>Values</b>	
<b>Note</b>	Only valid if CORXFER_CAP_COUNTER_STAMP_AVAILABLE is TRUE

---

**CORXFER\_CAP\_COUNTER\_STAMP\_TIME\_BASE**

<b>Description</b>	Specifies the counter stamp time base values available
<b>Type</b>	UINT32
<b>Values</b>	See CORXFER_PRM_COUNTER_STAMP_BASE..
<b>Note</b>	The returned value is the ORed combination of the valid values. Only valid if CORXFER_CAP_COUNTER_STAMP_AVAILABLE is TRUE.

---

**CORXFER\_CAP\_COUNTER\_STAMP\_EVENT\_TYPE**

<b>Description</b>	Specifies the event type(s) that will perform a counter stamp of the transfer destination.
<b>Type</b>	UINT32
<b>Values</b>	See CORXFER_PRM_EVENT_TYPE.
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

**CORXFER\_CAP\_CROP\_HEIGHT\_MAX**

<b>Description</b>	Specifies the maximum supported cropping height value (in lines) of the transferred data.
<b>Type</b>	UINT32

---

**CORXFER\_CAP\_CROP\_HEIGHT\_MIN**

<b>Description</b>	Specifies the minimum supported cropping height value (in lines) of the transferred data.
<b>Type</b>	UINT32

---

**CORXFER\_CAP\_CROP\_HEIGHT\_MULT**

<b>Description</b>	Specifies the supported cropping height granularity (in lines) of the transferred data.
<b>Type</b>	UINT32

---

**CORXFER\_CAP\_CROP\_HORZ**

<b>Description</b>	Specifies if the transfer device supports horizontal cropping of the transferred data.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, Horizontal cropping is supported. FALSE, Horizontal cropping is not supported.

---

**CORXFER\_CAP\_CROP\_LEFT\_MAX**

**Description** Specifies the maximum supported left side cropping value (in pixels) of the transferred data.  
**Type** UINT32

---

**CORXFER\_CAP\_CROP\_LEFT\_MIN**

**Description** Specifies the minimum supported left side cropping value (in pixels) of the transferred data.  
**Type** UINT32

---

**CORXFER\_CAP\_CROP\_LEFT\_MULT**

**Description** Specifies the supported left side cropping granularity (in pixels) of the transferred data.  
**Type** UINT32

---

**CORXFER\_CAP\_CROP\_TOP\_MAX**

**Description** Specifies the maximum supported cropping value (in lines) for the top of the transferred data.  
**Type** UINT32

---

**CORXFER\_CAP\_CROP\_TOP\_MIN**

**Description** Specifies the minimum supported cropping value (in lines) for the top of the transferred data.  
**Type** UINT32

---

**CORXFER\_CAP\_CROP\_TOP\_MULT**

**Description** Specifies the supported cropping granularity (in lines) for the top of the transferred data.  
**Type** UINT32

---

**CORXFER\_CAP\_CROP\_VERT**

**Description** Specifies if the transfer device supports vertical cropping of the transferred data.  
**Type** UINT32  
**Values** TRUE, Vertical cropping is supported.  
FALSE, Vertical cropping is not supported.

---

**CORXFER\_CAP\_CROP\_WIDTH\_MAX**

**Description** Specifies the maximum supported cropping width value (in pixels) of the transferred data.  
**Type** UINT32

---

**CORXFER\_CAP\_CROP\_WIDTH\_MIN**

**Description** Specifies the minimum supported width cropping value (in pixels) of the transferred data.  
**Type** UINT32

---

**CORXFER\_CAP\_CROP\_WIDTH\_MULT**

**Description** Specifies the supported cropping granularity (in pixels) for the width of the transferred data.  
**Type** UINT32

---

---

## CORXFER\_CAP\_CYCLE\_MODE

<b>Description</b>	Specifies the different cycle modes supported by the transfer module for the current transfer level.
<b>Type</b>	UINT32
<b>Values</b>	See CORXFER_PRM_CYCLE_MODE.
<b>Note</b>	Use the macro CORXFER_IS_CYCLE_MODE_SUPPORTED to test for the valid cycle mode.
<b>Example Code</b>	<pre>#define CORXFER_CAP_CYCLE_MODE CORXFER_CAP(40, 4)</pre>

```
// use this macro to check if a cycle mode is supported
// cap is the capability of the transfer level
// cycleMode is a CORXFER_VAL_CYCLE_MODE_XXXX value
#define CORXFER_IS_CYCLE_MODE_SUPPORTED(cap,cycleMode) (((cap)&(1 << ((cycleMode)
& 31))) != 0)
```

---

## CORXFER\_CAP\_EVENT\_COUNT\_SOURCE

<b>Description</b>	Specifies the possible handle types that can increase the event count for each call to the transfer callback function.
<b>Type</b>	UINT32
<b>Values</b>	See CORXFER_PRM_EVENT_TYPE.
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

## CORXFER\_CAP\_EVENT\_TYPE

<b>Description</b>	Specifies the event type(s) that can be registered.
<b>Type</b>	UINT32
<b>Values</b>	See CORXFER_PRM_EVENT_TYPE.
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

## CORXFER\_CAP\_EVENT\_TYPE\_EX

<b>Description</b>	Specifies the event type(s) that can be registered.
<b>Type</b>	UINT64
<b>Values</b>	See CORXFER_PRM_EVENT_TYPE.
<b>Note</b>	The returned value is the ORed combination of the valid values.  This is a 64-bit version of the CORXFER_CAP_EVENT_TYPE capability, where the 32 LSBs of the 2 capabilities are always the same.

---

## CORXFER\_CAP\_FLATFIELD

<b>Description</b>	Specifies the different flatfield modes supported by the transfer module.
<b>Type</b>	BOOL
<b>Values</b>	CORXFER_VAL_FLATFIELD_NOT_SUPPORTED (0x00000000) CORXFER_VAL_FLATFIELD_SUPPORTED (0x00000001) See CORXFER_PRM_FLATFIELD_NUMBER.

---

## CORXFER\_CAP\_FLIP

<b>Description</b>	Specifies the different flipping modes supported by the transfer module.
<b>Type</b>	UINT32
<b>Values</b>	See CORXFER_PRM_FLIP
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

## CORXFER\_CAP\_LEVEL\_EVENT\_TYPE

<b>Description</b>	Specifies the events available on a level.
<b>Type</b>	UINT64
<b>Values</b>	See CORXFER_PRM_EVENT_TYPE_EX`
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

## CORXFER\_CAP\_LINE\_MERGING

<b>Description</b>	Specifies the different line merging modes supported by the transfer module.
<b>Type</b>	BOOL
<b>Values</b>	CORXFER_VAL_LINE_MERGING_AUTO (0x00000000) CORXFER_VAL_LINE_MERGING_ON (0x00000001) CORXFER_VAL_LINE_MERGING_OFF (0x00000002) See CORXFER_PRM_LINE_MERGING.

---

## CORXFER\_CAP\_MAX\_FRAME\_COUNT

<b>Description</b>	Specifies the maximum number of frames that can be acquired in a sequential grab, that is, when calling the CorXferStart function with a count argument not equal to CORXFER_CONTINUOUS
<b>Type</b>	UINT32

---

## CORXFER\_CAP\_MAX\_XFER\_SIZE

<b>Description</b>	Specifies the maximum number of bytes the transfer device can transfer.
<b>Type</b>	UINT32

---

## CORXFER\_CAP\_NB\_INT\_BUFFERS

<b>Description</b>	Gets the internal buffer capability of the board. This is the creation mode of the internal buffers.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_NB_INT_BUFFERS_NONE (0x00000000), none available. CORXFER_VAL_NB_INT_BUFFERS_MANUAL (0x00000001), created by the application. The user must create the internal buffer by using a handle to the board, and then append the buffer to the Xfer module. The number of possible buffers is limited by the size of the frame grabber's internal buffer memory. CORXFER_VAL_NB_INT_BUFFERS_AUTO (0x00000002), automatically created. The internal buffers are not accessible by the user. When buffers are created automatically, use CORXFER_PRM_NB_INT_BUFFERS to set the number of internal buffers.

---

## **CORXFER\_CAP\_PROCESSING\_MODE**

<b>Description</b>	Gets the processing capability of the board.
<b>Type</b>	UINT32
<b>Values</b>	See CORXFER_PRM_PROCESSING_MODE.
<b>Note</b>	The processing behavior is specific to the board driver. See the board user's manual for more information about the processing.

---

## **CORXFER\_CAP\_SCALE\_HORZ**

<b>Description</b>	Specifies if the transfer device supports horizontal scaling.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, Horizontal scaling is available. FALSE, Horizontal scaling is not available.

---

## **CORXFER\_CAP\_SCALE\_HORZ\_MAX**

<b>Description</b>	Specifies the maximum number of pixels that can be output by the transfer resource.
<b>Type</b>	UINT32

---

## **CORXFER\_CAP\_SCALE\_HORZ\_MAX\_FACTOR**

<b>Description</b>	Specifies the maximum horizontal upscaling ratio supported by the transfer resource.
<b>Type</b>	UINT32
<b>Notes</b>	The ratio is equal to $\text{CORXFER\_CAP\_SCALE\_HORZ\_MAX\_FACTOR} / \text{CORXFER\_VAL\_SCALE\_FACTOR}$

---

## **CORXFER\_CAP\_SCALE\_HORZ\_METHOD**

<b>Description</b>	Specifies the different horizontal scaling methods supported by the transfer resource.
<b>Type</b>	UINT32
<b>Values</b>	See CORXFER_PRM_SCALE_HORZ_METHOD.
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

## **CORXFER\_CAP\_SCALE\_HORZ\_MIN**

<b>Description</b>	Specifies the minimum number of pixels that can be output by the transfer resource.
<b>Type</b>	UINT32

---

## **CORXFER\_CAP\_SCALE\_HORZ\_MIN\_FACTOR**

<b>Description</b>	Specifies the minimum horizontal downscaling ratio supported by the transfer resource.
<b>Type</b>	UINT32
<b>Note</b>	The ratio is equal to $1 / (\text{CORXFER\_CAP\_SCALE\_HORZ\_MIN\_FACTOR} / \text{CORXFER\_VAL\_SCALE\_FACTOR})$ .

---

## **CORXFER\_CAP\_SCALE\_HORZ\_MULT**

<b>Description</b>	Specifies the granularity (in pixels) that can be output by the transfer resource.
<b>Type</b>	UINT32

---

**CORXFER\_CAP\_SCALE\_VERT**

<b>Description</b>	Specifies if the transfer resource supports vertical scaling.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, Vertical scaling is available. FALSE, Vertical scaling is not available.

---

**CORXFER\_CAP\_SCALE\_VERT\_MAX**

<b>Description</b>	Specifies the maximum number of lines that can be output by the transfer resource.
<b>Type</b>	UINT32

---

**CORXFER\_CAP\_SCALE\_VERT\_MAX\_FACTOR**

<b>Description</b>	Specifies the maximum vertical upscaling ratio supported by the transfer resource.
<b>Type</b>	UINT32
<b>Note</b>	The ratio is equal to: $\text{CORXFER\_CAP\_SCALE\_VERT\_MAX\_FACTOR} / \text{CORXFER\_VAL\_SCALE\_FACTOR}$ .

---

**CORXFER\_CAP\_SCALE\_VERT\_METHOD**

<b>Description</b>	Specifies the different vertical scaling methods supported by the transfer resource.
<b>Type</b>	UINT32
<b>Values</b>	See CORXFER_PRM_SCALE_VERT_METHOD.
<b>Note</b>	The returned value is the ORed combination of the valid values.

---

**CORXFER\_CAP\_SCALE\_VERT\_MIN**

<b>Description</b>	Specifies the minimum number of lines that can be output by the transfer resource.
<b>Type</b>	UINT32

---

**CORXFER\_CAP\_SCALE\_VERT\_MIN\_FACTOR**

<b>Description</b>	Specifies the minimum vertical downscaling ratio supported by the transfer resource.
<b>Type</b>	UINT32
<b>Note</b>	The ratio is equal to: $1 / (\text{CORXFER\_CAP\_SCALE\_VERT\_MIN\_FACTOR} / \text{CORXFER\_VAL\_SCALE\_FACTOR})$ .

---

**CORXFER\_CAP\_SCALE\_VERT\_MULT**

<b>Description</b>	Specifies the vertical granularity (in lines) that can be output by the transfer resource.
<b>Type</b>	UINT32



## Parameters

ID	Parameter	Attribute
0x00	<i>Reserved</i>	-----
0x01	<i>Reserved</i>	-----
0x02	CORXFER_PRM_CROP_LEFT	Read/Write
0x03	CORXFER_PRM_CROP_TOP	Read/Write
0x04	CORXFER_PRM_CROP_WIDTH	Read/Write
0x05	CORXFER_PRM_CROP_HEIGHT	Read/Write
0x06	CORXFER_PRM_SCALE_HORZ	Read/Write
0x07	CORXFER_PRM_SCALE_VERT	Read/Write
0x08	CORXFER_PRM_SCALE_HORZ_METHOD	Read/Write
0x09	CORXFER_PRM_SCALE_VERT_METHOD	Read/Write
0x0a	CORXFER_PRM_EVENT_TYPE	Read Only
0x0b	CORXFER_PRM_EVENT_COUNT	Read Only
0x0c	CORXFER_PRM_START_MODE	Read/Write
0x0d	CORXFER_PRM_TIMEOUT	Read/Write
0x0e	CORXFER_PRM_CYCLE_MODE	Read/Write
0x0f	CORXFER_PRM_EVENT_SERVER	Read Only
0x10	CORXFER_PRM_EVENT_CALLBACK	Read Only
0x11	CORXFER_PRM_EVENT_CONTEXT	Read Only
0x12	CORXFER_PRM_FLIP	Read/Write
0x13	CORXFER_PRM_NB_INT_BUFFERS	Read/Write
0x14	CORXFER_PRM_EVENT_COUNT_SOURCE	Read/Write
0x15	<i>Reserved</i>	
0x16	CORXFER_PRM_COUNTER_STAMP_BASE	Read/Write
0x17	CORXFER_PRM_FLATFIELD_NUMBER	Read/Write
0x1b	CORXFER_PRM_PROCESSING_MODE	Read/Write
0x1e	CORXFER_PRM_BUFFER_TIMESTAMP_MODULE	Read/Write
0x1f	CORXFER_PRM_BUFFER_TIMESTAMP_EVENT	Read/Write
0x20	CORXFER_PRM_LINE_MERGING	Read/Write
0x21	CORXFER_PRM_EVENT_TYPE_EX	Read/Write
0x22	CORXFER_PRM_LEVEL_EVENT_CALLBACK	Read Only
0x23	CORXFER_PRM_LEVEL_EVENT_CONTEXT	Read Only
0x24	CORXFER_PRM_LEVEL_EVENT_COUNT	Read Only
0x25	CORXFER_PRM_LEVEL_EVENT_SERVER	Read Only
0x26	CORXFER_PRM_LEVEL_EVENT_TYPE	Read/Write

### CORXFER\_PRM\_BUFFER\_TIMESTAMP\_MODULE

<b>Description</b>	Selects from which module an event will set the buffer parameter CORBUFFER_PRM_.
<b>Type</b>	UINT32
<b>Values</b>	<p>CORXFER_VAL_BUFFER_TIMESTAMP_MODULE_XFER (0x00000013), the timestamp event comes from the xfer module</p> <p>CORXFER_VAL_BUFFER_TIMESTAMP_MODULE_ACQ (0x00000001), the timestamp event comes from the acquisition module</p>
<b>Note</b>	The parameter must be set before calling CorXferConnect

---

## CORXFER\_PRM\_BUFFER\_TIMESTAMP\_EVENT

<b>Description</b>	Selects the event that will set the buffer parameter CORBUFFER_PRM_.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_EVENT_TYPE_START_OF_FRAME (0x00080000) <sup>1</sup> CORXFER_VAL_EVENT_TYPE_END_OF_FRAME (0x00800000) CORACO_VAL_EVENT_TYPE_EXTERNAL_TRIGGER (0x01000000) <sup>2</sup> CORACO_VAL_EVENT_TYPE_START_OF_FRAME (0x00080000) <sup>2</sup> CORACO_VAL_EVENT_TYPE_END_OF_FRAME (0x00800000)
<b>Note</b>	1. Only if CORXFER_PRM_BUFFER_TIMESTAMP_MODULE is equal to CORXFER_VAL_BUFFER_TIMESTAMP_MODULE_XFER 2. Only if CORXFER_PRM_BUFFER_TIMESTAMP_MODULE is equal to CORXFER_VAL_BUFFER_TIMESTAMP_MODULE_ACQ See CORXFER_PRM_BUFFER_TIMESTAMP_MODULE, CORBUFFER_PRM_HOST_COUNTER_STAMP. The parameter must be set before calling CorXferConnect.

---

## CORXFER\_PRM\_COUNTER\_STAMP\_BASE

<b>Description</b>	Sets the counter stamp time base.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_TIME_BASE_US (0x00000001), the time base is in micro-seconds CORXFER_VAL_TIME_BASE_MS (0x00000002), the time base is in milli-seconds CORXFER_VAL_TIME_BASE_LINE_TRIGGER (0x00000004), the time base is in external line trigger or shaft encoder pulse counts after drop and multiply factors. CORXFER_VAL_TIME_BASE_LINE (0x00000008), the time base is in line valid CORXFER_VAL_TIME_BASE_FRAME (0x00000010), the time base is in frame valid or VS CORXFER_VAL_TIME_BASE_EXT_FRAME_TRIGGER (0x00000020), the time base is in external trigger counts CORXFER_VAL_TIME_BASE_SHAFT_ENCODER (0x00000040), the time base is the shaft encoder input (before drop or/and multiply factors).
<b>Note</b>	Only valid if CORXFER_CAP_COUNTER_STAMP_AVAILABLE is TRUE. See CORXFER_CAP_COUNTER_STAMP_TIME_BASE.

---

## CORXFER\_PRM\_CROP\_HEIGHT

<b>Description</b>	Cropped height of the transferred data (in lines).
<b>Type</b>	UINT32

---

## CORXFER\_PRM\_CROP\_LEFT

<b>Description</b>	Number of pixels to crop from the left side of the transferred data.
<b>Type</b>	UINT32

---

## CORXFER\_PRM\_CROP\_TOP

<b>Description</b>	Number of lines to crop from the top of the transferred data.
<b>Type</b>	UINT32

---

## CORXFER\_PRM\_CROP\_WIDTH

<b>Description</b>	Cropped width of the transferred data (in pixels).
<b>Type</b>	UINT32

---

## CORXFER\_PRM\_CYCLE\_MODE

<b>Description</b>	Sets the mode used by the transfer device to specify which buffer gets the next data transfer.
<b>Type</b>	UINT32
<b>Values</b>	<p>The available modes differ by the way in which they specify which buffer gets the next data transfer.</p> <p>The empty state refers to the case where buffer data has been completely processed and may be overwritten. It is set by application code as soon as it has finished processing buffer data.</p> <p>The full state refers to the case where buffer data has not been processed since its latest data transfer. It is set by the transfer device as soon as a data transfer has completed.</p> <p>The current buffer is the one in which the latest data transfer occurred.</p> <p>The next buffer is the one immediately after the current buffer, with wraparound to the first buffer at the end of the list.</p> <p>The trash buffer is defined as the last buffer in the list for the WITH_TRASH modes only. Its state is always considered to be empty by the transfer device.</p> <p>CORXFER_VAL_CYCLE_MODE_ASYNCHRONOUS (0x00000000), Always transfer to the next buffer regardless of its state.</p> <p>CORXFER_VAL_CYCLE_MODE_SYNCHRONOUS (0x00000001), If next buffer is empty, then transfer to next buffer, otherwise, transfer to current buffer.</p> <p>CORXFER_VAL_CYCLE_MODE_SYNCHRONOUS_WITH_TRASH (0x00000002), If next buffer is empty, then transfer to the next buffer, otherwise, transfer to the trash buffer. Repeat transferring to the trash buffer as long as the next buffer is full.</p> <p>CORXFER_VAL_CYCLE_MODE_OFF (0x00000003), Always transfer to the current buffer.</p> <p>CORXFER_VAL_CYCLE_MODE_NEXT_EMPTY (0x00000004), If next buffer is empty, then transfer to next buffer, otherwise, transfer to next empty buffer in the list. If all buffers are full, then transfer to current buffer.</p> <p>CORXFER_VAL_CYCLE_MODE_SYNCHRONOUS_NEXT_EMPTY_WITH_TRASH (0x00000005), If next buffer is empty, then transfer to next buffer, otherwise, transfer to next empty buffer in the list. If all buffers are full, then transfer to trash buffer. Repeat transferring to the trash buffer as long as there is no empty buffer in the list.</p>
<b>See Also</b>	CORBUFFER_PRM_STATE

---

## CORXFER\_PRM\_EVENT\_CALLBACK

<b>Description</b>	Callback registered using the function CorXferRegisterCallback for the current item selected.
<b>Type</b>	PCORCALLBACK
<b>Values</b>	Pointer to the callback function registered.
<b>Note</b>	This parameter is read-only.

---

## CORXFER\_PRM\_EVENT\_CONTEXT

<b>Description</b>	Context pointer registered using the function CorXferRegisterCallback for the current item selected..
<b>Type</b>	void *
<b>Values</b>	Pointer to the context.
<b>Note</b>	This parameter is read-only.

---

## **CORXFER\_PRM\_EVENT\_COUNT**

<b>Description</b>	Number of events that have occurred for the current item selected since a callback function was registered using the CorXferRegisterCallback function.
<b>Type</b>	UINT32
<b>Note</b>	This parameter is read-only.

---

## **CORXFER\_PRM\_EVENT\_COUNT\_SOURCE**

<b>Description</b>	Handle type that increases the event count for each call to the transfer callback function.
<b>Type</b>	UINT32
<b>Values</b>	<p>CORXFER_VAL_EVENT_COUNT_SOURCE_DST (0x00000001) The event count is associated with the destination handle, which is usually a buffer. This means that all buffers in a list have their own event count.</p> <p>CORXFER_VAL_EVENT_COUNT_SOURCE_SRC (0x00000002) The event count is associated with the source handle which is usually an acquisition device. This means that the count increases at each acquired frame.</p>

---

## **CORXFER\_PRM\_EVENT\_SERVER**

<b>Description</b>	Server to which an event notification through a callback function will be made.
<b>Type</b>	CORSERVER
<b>Values</b>	Server handle.
<b>Note</b>	This parameter is read-only.

---

## CORXFER\_PRM\_EVENT\_TYPE

<b>Description</b>	Event to be signaled while a transfer is in progress.
<b>Type</b>	UINT32
<b>Values</b>	<p>CORXFER_VAL_EVENT_TYPE_START_OF_FIELD (0x00010000) Call the callback function at the start of an odd or even field.</p> <p>CORXFER_VAL_EVENT_TYPE_START_OF_ODD (0x00200000) Call the callback function at the start of an odd field.</p> <p>CORXFER_VAL_EVENT_TYPE_START_OF_EVEN (0x00040000) Call the callback function at the start of an even field.</p> <p>CORXFER_VAL_EVENT_TYPE_START_OF_FRAME (0x00080000) Call the callback at the start of a frame.</p> <p>CORXFER_VAL_EVENT_TYPE_END_OF_FIELD (0x00100000) Call the callback function at the end of an odd or even field.</p> <p>CORXFER_VAL_EVENT_TYPE_END_OF_ODD (0x00200000) Call the callback function at the end of an odd field.</p> <p>CORXFER_VAL_EVENT_TYPE_END_OF_EVEN (0x00400000) Call the callback function at the end of an even field.</p> <p>CORXFER_VAL_EVENT_TYPE_END_OF_FRAME (0x00800000) Call the callback function at the end of a frame.</p> <p>CORXFER_VAL_EVENT_TYPE_END_OF_LINE (0x01000000) Call the callback function at end of line <i>n</i>.</p> <p>CORXFER_VAL_EVENT_TYPE_END_OF_NLINES (0x02000000) Call the callback function at end of <i>n</i> lines.</p> <p>CORXFER_VAL_EVENT_TYPE_END_OF_TRANSFER (0x04000000) Call the callback function at the end of a transfer.</p> <p>CORXFER_VAL_EVENT_TYPE_LINE_UNDERRUN (0x08000000) Call the callback function if during a transfer the number of active pixels per line received from a video source is smaller than requested.</p> <p>CORXFER_VAL_EVENT_TYPE_FIELD_UNDERRUN (0x10000000) Call the callback function if during a transfer the number of active lines per field received from a video source is smaller than requested.</p>
<b>Note</b>	The values may be ORed if more than one event is desired.

---

## CORXFER\_PRM\_EVENT\_TYPE\_EX

<b>Description</b>	Event to be signaled while a transfer is in progress.
<b>Type</b>	UINT64
<b>Values</b>	See CORXFER_PRM_EVENT_TYPE.
<b>Note</b>	<p>The values may be ORed if more than one event is desired.</p> <p>This is a 64-bit version of the CORACO_PRM_EVENT_TYPE parameter, the 32 LSBs of the 2 capabilities are always the same.</p> <p>Currently, values are the same as CORXFER_PRM_EVENT_TYPE. This 64-bit function provides for future expansion beyond the limits of the 32-bit CORXFER_PRM_EVENT_TYPE.</p>

---

## CORXFER\_PRM\_FLATFIELD\_NUMBER

<b>Description</b>	The flatfield number used for the current source and destination.
<b>Type</b>	UINT32

---

## **CORXFER\_PRM\_FLIP**

<b>Description</b>	The transfer module Flipping Mode control.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_FLIP_OFF (0x00000000), Will not flip incoming lines and frames. CORXFER_VAL_FLIP_HORZ (0x00000001), Will flip incoming lines for the current destination buffer; that is the rightmost pixels become the leftmost pixels. CORXFER_VAL_FLIP_VERT (0x00000002), Will flip incoming frames for the current destination buffer; that is the bottom lines become the top lines.
<b>Limits</b>	This value must match one of the supported capabilities of the transfer module given by CORXFER_CAP_FLIP

---

## **CORXFER\_PRM\_LEVEL\_EVENT\_CALLBACK**

<b>Description</b>	Callback registered using the function CorXferRegisterCallbackEx for the level of the currently selected item.
<b>Type</b>	PCOREVENTINFOCALLBACK
<b>Values</b>	Pointer to the callback function registered.
<b>Note</b>	This parameter is read-only.

---

## **CORXFER\_PRM\_LEVEL\_EVENT\_CONTEXT**

<b>Description</b>	Context pointer registered using the function CorXferRegisterCallbackEx for the level of the currently selected item.
<b>Type</b>	void *
<b>Values</b>	Pointer to the context.
<b>Note</b>	This parameter is read-only.

---

## **CORXFER\_PRM\_LEVEL\_EVENT\_COUNT**

<b>Description</b>	Number of events that have occurred for the level of the currently selected item since a callback function was registered using the CorXferRegisterCallbackEx function.
<b>Type</b>	UINT64
<b>Note</b>	This parameter is read-only.

---

## **CORXFER\_PRM\_LEVEL\_EVENT\_SERVER**

<b>Description</b>	Server to which an event notification through a callback function will be made based on the level of the currently selected item.
<b>Type</b>	CORSERVER
<b>Values</b>	Server handle.
<b>Note</b>	This parameter is read-only.

---

## CORXFER\_PRM\_LEVEL\_EVENT\_TYPE

<b>Description</b>	Event to be signaled while a transfer is in progress based on the currently selected level..
<b>Type</b>	UINT64
<b>Values</b>	See CORXFER_PRM_EVENT_TYPE_EX.
<b>Note</b>	The values may be ORed if more than one event is required.

---

## CORXFER\_PRM\_LINE\_MERGING

<b>Description</b>	Sets the enable state of line merging. When supported by hardware, line merging allows multiple lines to be concatenated and considered as a single line (typically used in 8 or 10 tap formats) to increase the maximum throughput. By default, this feature is enabled. If processing requires that only single lines be output, this feature can be disabled.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_LINE_MERGING_AUTO (0x00000000), Automatically enables line merging if supported. CORXFER_VAL_LINE_MERGING_ON (0x00000001), Enable line merging. CORXFER_VAL_LINE_MERGING_OFF (0x00000002), Disable line merging.
<b>Limits</b>	This value must match one of the supported capabilities of the transfer module given by CORXFER_CAP_LINE_MERGING

---

## CORXFER\_PRM\_NB\_INT\_BUFFERS

<b>Description</b>	Sets the number of internal buffers on the frame grabber that will be used when acquiring images.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_NB_INT_BUFFERS_NONE (0x00000000), none available. CORXFER_VAL_NB_INT_BUFFERS_MANUAL (0x00000001), created by the application. The user must create the internal buffer by using a handle to the board, and then append the buffer to the Xfer module. CORXFER_VAL_NB_INT_BUFFERS_AUTO (0x00000002), automatically created. The internal buffers are not accessible by the user.

---

## CORXFER\_PRM\_PROCESSING\_MODE

<b>Description</b>	Sets the processing mode of the board.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_PROCESSING_MODE_NONE (0x00000000)= not available. CORXFER_VAL_PROCESSING_MODE_1 (0x00000001) = processing mode 1 (board specific) CORXFER_VAL_PROCESSING_MODE_2 (0x00000002) = processing mode 2 (board specific) CORXFER_VAL_PROCESSING_MODE_3 (0x00000004) = processing mode 3 (board specific) CORXFER_VAL_PROCESSING_MODE_DLUT (0x00000008) = processing mode 4 (board specific)
<b>Note</b>	A processing mode can only be set before calling CorXferConnect

---

## CORXFER\_PRM\_SCALE\_HORZ

<b>Description</b>	Number of pixels per line to be output by the transfer.
<b>Type</b>	UINT32

---

## CORXFER\_PRM\_SCALE\_HORZ\_METHOD

<b>Description</b>	Horizontal scaling method.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_SCALE_DISABLE (0x00000000), Disable horizontal scaling. CORXFER_VAL_SCALE_SIMPLE (0x00000001), Horizontal scaling drops pixels. CORXFER_VAL_SCALE_INTERPOLATION (0x00000003), Horizontal scaling interpolates pixels. CORXFER_VAL_SCALE_POW2 (0x00000004), Horizontal scaling factor must be a power of 2.

---

## CORXFER\_PRM\_SCALE\_VERT

<b>Description</b>	Number of lines per frame to be output by the transfer.
<b>Type</b>	UINT32

---

## CORXFER\_PRM\_SCALE\_VERT\_METHOD

<b>Description</b>	Vertical scaling method.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_SCALE_DISABLE (0x00000001), Disable vertical scaling. CORXFER_VAL_SCALE_SIMPLE (0x00000002), Vertical scaling drops lines. CORXFER_VAL_SCALE_INTERPOLATION (0x00000003), Vertical scaling interpolates lines. CORXFER_VAL_SCALE_POW2 (0x00000004), Vertical scaling factor must be a power of 2.

---

## CORXFER\_PRM\_START\_MODE

<b>Description</b>	Controls the behavior of CorXferStart function when called.
<b>Type</b>	UINT32
<b>Values</b>	CORXFER_VAL_START_MODE_ASYNCHRONOUS (0x00000000) When starting a transfer, CorXferStart returns immediately without waiting for the transfer to begin.  CORXFER_VAL_START_MODE_SYNCHRONOUS (0x00000001) When starting a single frame transfer, CorXferStart returns only when the transfer has been completed.  CORXFER_VAL_START_MODE_HALF_ASYNCHRONOUS (0x00000002) If a transfer is currently in progress when starting a new single frame transfer, CorXferStart will wait for the first transfer to finish and then start the transfer. It then returns immediately.  CORXFER_VAL_START_MODE_SEQUENTIAL (0x00000003) If a multi-level transfer is defined (that is, acquisition to on-board memory to host memory), the transfer process will wait until all frames in the sequence are in the on-board memory before sending them to the host memory.
<b>Note</b>	This parameter has no effect when starting a transfer in continuous mode.



---

## CORXFER\_PRM\_TIMEOUT

**Description** Specifies the maximum number of milliseconds to wait for a transfer to finish.

**Type** UINT32

## CORXFER\_DESC Structure Definition

```
// CORXFER_DESC Structure Definition

typedef struct
{
    UINT32 frame; //has the following values:
    //CORXFER_VAL_FRAME_INTERLACED
    //CORXFER_VAL_FRAME_NON_INTERLACED

    UINT32 fieldOrder; //has the following values if frame is interlaced:
    //CORXFER_VAL_FIELD_ORDER_ODD_EVEN
    //CORXFER_VAL_FIELD_ORDER_EVEN_ODD
    //CORXFER_VAL_FIELD_ORDER_ANY_ORDER
    UINT32 widthByte; //line width of the frame in bytes
    UINT32 height; //frame height in lines
    UINT32 incByte; //the stride between two lines in bytes
    //(even if the frame is interlaced,
    //incByte should usually be equal to widthByte)
} CORXFER_DESC, *PCORXFER_DESC; //any parameter with a value of 0 is ignored

//the source is then interrogated to retrieve the
//corresponding information when possible)
```

## Functions

Function	Description
CorXferAbort	<i>Aborts transfer asynchronously for a transfer resource</i>
CorXferAppend	<i>Appends item to the transfer description list of a transfer resource. Source and destination resource have a single port.</i>
CorXferAppendEx	<i>Appends item to the transfer description list of a transfer resource. Source and destination resource can have more than one port.</i>
CorXferConnect	<i>Builds the transfer description list and locks resources of a transfer resource</i>
CorXferConnectEx	<i>Builds the transfer description list and locks resources of a transfer resource (with a timeout)</i>
CorXferDisconnect	<i>Frees resources used by a transfer resource</i>
CorXferFree	<i>Frees handle to a transfer resource</i>
CorXferGetCap	<i>Gets transfer capability value from a transfer resource</i>
CorXferGetPrm	<i>Gets transfer parameter value from a transfer resource</i>
CorXferNew	<i>Creates in the specified server's memory a new transfer resource handle. Source and destination resource have a single port.</i>
CorXferNewEx	<i>Creates in the specified server's memory a new transfer resource handle. Source and destination resource can have more than one port.</i>
CorXferRegisterCallback	<i>Registers callback function for a transfer resource</i>
CorXferRegisterCallbackEx	<i>Registers callback function for a transfer resource. This extended version supports newer event types (64-bit) and additional information.</i>
CorXferReset	<i>Resets a transfer resource</i>
CorXferResetModule	<i>Resets the resources associated with the server's transfer device(s)</i>
CorXferSelect	<i>Selects an item as the current item of a transfer resource. Source and destination resource have a single port.</i>
CorXferSelectEx	<i>Selects an item as the current item of a transfer resource. Source and destination resource can have more than one port.</i>
CorXferSetPrm	<i>Sets a simple transfer parameter of a transfer resource</i>
CorXferSetPrmEx	<i>Sets a complex transfer parameter of a transfer resource</i>
CorXferStart	<i>Starts transfer for a transfer resource</i>
CorXferStop	<i>Stops transfer synchronously for a transfer resource</i>
CorXferUnregisterCallback	<i>Unregisters callback function for a transfer resource</i>
	<i>Unregisters callback function for a transfer resource</i>
CorXferWait	<i>Waits until end of transfer or until timeout for a transfer resource</i>

---

### CorXferAbort

Stop transfer asynchronously for a transfer resource

**Prototype**      `CORSTATUS CorXferAbort(CORXFER hXfer);`

**Description**      Stops transfer asynchronously for a transfer resource.  
On return, transfer is finished but part of the last transferred frame may be corrupted.

**Input**              *hXfer*              Transfer resource handle

**Output**             None

**Return Value**    `CORSTATUS_OK`  
`CORSTATUS_INVALID_HANDLE` and `CORSTATUS_XFER_NOT_CONNECTED`

---

## CorXferAppend

Append item to the transfer description list of a transfer resource

**Prototype**      `CORSTATUS CorXferAppend(CORXFER hXfer, CORHANDLE hSrc, CORHANDLE hDst, CORXFER_DESC *pDesc);`

**Description**      Appends item to the transfer description list of a transfer resource. The new appended item (*hSrc*, *hDst*) becomes the current item. If the source and/or the destination resource have more than one port, port number 0 will be used.

**Input**            *hXfer*              Transfer resource handle  
                     *hSrc*              Resource handle (source)  
                     *hDst*              Resource handle (destination)  
                     *pDesc*              Transfer description structure. See CORXFER\_DESC Structure Definition.

**Output**            None

**Return Value**    `CORSTATUS_OK`  
                     `CORSTATUS_INCOMPATIBLE_BUFFER`, `CORSTATUS_INVALID_HANDLE`  
                     `CORSTATUS_NO_MEMORY`, `CORSTATUS_ROUTING_NOT_IMPLEMENTED` and  
                     `CORSTATUS_XFER_CANT_CYCLE`

**Note**              If *pDesc* is specified as NULL, automatic source format detection will be used to provide all the information needed to specify the transfer.

When transferring to a buffer resource, the specified buffer must have been created using the `CORBUFFER_VAL_TYPE_CONTIGUOUS` or `CORBUFFER_VAL_TYPE_SCATTER_GATHER` type. Otherwise, `CORSTATUS_INCOMPATIBLE_BUFFER` is returned.

If there is not enough local memory to add the (*hSrc*, *hDst*) items to the transfer description list, `CORSTATUS_NO_MEMORY` is returned.

If there is no available transfer path for the newly added (*hSrc*, *hDst*) item, `CORSTATUS_ROUTING_NOT_IMPLEMENTED` is returned.

If for the newly added (*hSrc*, *hDst*) item in the transfer description list, the *hDst* resource location has already been added and the transfer resource does not support cycle transfer for this type of resource, `CORSTATUS_XFER_CANT_CYCLE` is returned.

**See also**            `CorXferAppendEx`

---

## CorXferAppendEx

Append item to the transfer description list of a transfer resource

**Prototype**      `CORSTATUS CorXferAppendEx(CORXFER hXfer, CORHANDLE hSrc, UINT32 srcPort, CORHANDLE hDst, UINT32 dstPort, CORXFER_DESC *pDesc);`

**Description**      Appends item to the transfer description list of a transfer resource. Source and destination resource can have more than one port. The new appended item (*hSrc*, *hDst*) becomes the current item.

**Input**            *hXfer*            Transfer resource handle  
                  *hSrc*            Resource handle (source)  
                  *srcPort*        Source port number  
                  *hDst*            Resource handle (destination)  
                  *dstPort*        Destination port number  
                  *pDesc*        Transfer description structure. See CORXFER\_DESC Structure Definition.

**Output**            None

**Return Value**    `CORSTATUS_OK`  
                  `CORSTATUS_INCOMPATIBLE_BUFFER`, `CORSTATUS_INVALID_HANDLE`  
                  `CORSTATUS_NO_MEMORY`, `CORSTATUS_ROUTING_NOT_IMPLEMENTED` and  
                  `CORSTATUS_XFER_CANT_CYCLE`

**Note**            If *pDesc* is specified as NULL, automatic source format detection will be used to provide all the information needed to specify the transfer.

When transferring to a buffer resource, the specified buffer must have been created using the `CORBUFFER_VAL_TYPE_CONTIGUOUS` or `CORBUFFER_VAL_TYPE_SCATTER_GATHER` type. Otherwise, `CORSTATUS_INCOMPATIBLE_BUFFER` is returned.

If there is not enough local memory to add the (*hSrc*, *hDst*) items to the transfer description list, `CORSTATUS_NO_MEMORY` is returned.

If there is no available transfer path for the newly added (*hSrc*, *hDst*) item, `CORSTATUS_ROUTING_NOT_IMPLEMENTED` is returned.

If for the newly added (*hSrc*, *hDst*) item in the transfer description list, the *hDst* resource location has already been added and the transfer resource does not support cycle transfer for this type of resource, `CORSTATUS_XFER_CANT_CYCLE` is returned.

---

## CorXferConnect

Build the transfer description list and locks resources of a transfer resource

**Prototype**      `CORSTATUS CorXferConnect(CORXFER hXfer);`

**Description**      Builds the transfer description list and locks resources for a transfer resource

**Input**            *hXfer*            Transfer resource handle

**Output**           None

**Return Value**    `CORSTATUS_OK`  
`CORSTATUS_INCOMPATIBLE_SIZE`, `CORSTATUS_INVALID_HANDLE`,  
`CORSTATUS_NO_MEMORY`, `CORSTATUS_RESOURCE_IN_USE`,  
`CORSTATUS_ROUTING_IN_USE`, `CORSTATUS_XFER_EMPTY_LIST` and  
`CORSTATUS_XFER_MAX_SIZE`

**Note**            If there are resources already in use that are needed to build the transfer description list, `CORSTATUS_RESOURCE_IN_USE` is returned.

                  If for any one of the (hSrc, hDst) items in the transfer description list, the size of the source resource is larger than the size of the destination resource, `CORSTATUS_INCOMPATIBLE_SIZE` is returned.

                  If for any one of the (hSrc, hDst) items in the transfer description list, the size in bytes of the source resource is larger than the `CORXFER_CAP_MAX_XFER_SIZE` capability, `CORSTATUS_XFER_MAX_SIZE` is returned.

                  If the transfer description list is empty, `CORSTATUS_XFER_EMPTY_LIST` is returned.

                  If there is a routing already in use that is needed to build the transfer description list, `CORSTATUS_ROUTING_IN_USE` is returned.

                  If there is not enough local memory to build the local representation of the transfer description list, `CORSTATUS_NO_MEMORY` is returned.

**See Also**        `CorXferDisconnect`

---

## CorXferConnectEx

Build the transfer description list and locks resources of a transfer resource (with a timeout)

<b>Prototype</b>	CORSTATUS <b>CorXferConnectEx</b> (CORXFER <i>hXfer</i> , UINT32 <i>timeout</i> );
<b>Description</b>	Builds the transfer description list and locks resources for a transfer resource
<b>Input</b>	<i>hXfer</i> Transfer resource handle <i>timeout</i> Maximum time to wait (in milliseconds)
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INCOMPATIBLE_SIZE, CORSTATUS_INVALID_HANDLE, CORSTATUS_NO_MEMORY, CORSTATUS_RESOURCE_IN_USE, CORSTATUS_ROUTING_IN_USE, CORSTATUS_XFER_EMPTY_LIST and CORSTATUS_XFER_MAX_SIZE
<b>Note</b>	<p>If there are resources already in use that are needed to build the transfer description list, CORSTATUS_RESOURCE_IN_USE is returned.</p> <p>If for any one of the (hSrc, hDst) items in the transfer description list, the size of the source resource is larger than the size of the destination resource, CORSTATUS_INCOMPATIBLE_SIZE is returned.</p> <p>If for any one of the (hSrc, hDst) items in the transfer description list, the size in bytes of the source resource is larger than the CORXFER_CAP_MAX_XFER_SIZE capability, CORSTATUS_XFER_MAX_SIZE is returned.</p> <p>If the transfer description list is empty, CORSTATUS_XFER_EMPTY_LIST is returned.</p> <p>If there is a routing already in use that is needed to build the transfer description list, CORSTATUS_ROUTING_IN_USE is returned.</p> <p>If there is not enough local memory to build the local representation of the transfer description list, CORSTATUS_NO_MEMORY is returned.</p> <p>The time required by CorXferConnect can be high when the amount of memory taken by the buffer resources is very large, and can even exceed the Sapera LT communication timeout value (obtained by calling CorManGetTimeout). In this case, the call to CorXferConnect returns CORSTATUS_TIMEOUT. The <i>timeout</i> argument can then be used to specify a larger amount of time. The largest of this value and of the communication timeout value is then used internally by CorXferConnect.</p>
<b>See Also</b>	CorXferConnect, CorXferDisconnect, CorManGetTimeout, CorManSetTimeout

---

## CorXferDisconnect

Free resources used by a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferDisconnect</b> (CORXFER <i>hXfer</i> );
<b>Description</b>	Frees resources used by a transfer resource.
<b>Input</b>	<i>hXfer</i> Transfer resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorXferConnect

---

## CorXferFree

Free handle to a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferFree</b> (CORXFER <i>hXfer</i> );
<b>Description</b>	Frees handle to a transfer resource
<b>Input</b>	<i>hXfer</i> Transfer resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE and CORSTATUS_RESOURCE_IN_USE
<b>See Also</b>	CorXferNew

---

## CorXferGetCap

Get transfer capability value from a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferGetCap</b> (CORXFER <i>hXfer</i> , UINT32 <i>cap</i> , void * <i>value</i> );
<b>Description</b>	Gets transfer capability value for the current item of a transfer resource.
<b>Input</b>	<i>hXfer</i> Transfer resource handle <i>cap</i> Transfer device capability requested
<b>Output</b>	<i>value</i> Value of the capability
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>value</i> is NULL), CORSTATUS_CAP_INVALID and CORSTATUS_INVALID_HANDLE
<b>Note</b>	To select an item (hSrc, hDst) as the current item of a transfer resource, use CorXferSelect.
<b>See Also</b>	CorXferSetPrm, CorXferSetPrmEx and CorXferSelect

---

## CorXferGetPrm

Get transfer parameter value from a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferGetPrm</b> (CORXFER <i>hXfer</i> , UINT32 <i>prm</i> , void * <i>value</i> );
<b>Description</b>	Gets transfer parameter value from a transfer resource.
<b>Input</b>	<i>hXfer</i> Transfer resource handle <i>prm</i> Transfer parameter requested
<b>Output</b>	<i>value</i> Current value of the parameter
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>value</i> is NULL), CORSTATUS_INVALID_HANDLE, CORSTATUS_PRM_INVALID and CORSTATUS_PRM_NOT_AVAILABLE
<b>Note</b>	To select an item (hSrc, hDst) as the current transfer resource item, use CorXferSelect.
<b>See Also</b>	CorXferSetPrm, CorXferSetPrmEx and CorXferSelect

---

## CorXferNew

Create in the specified server's memory a new transfer resource

**Prototype**      `CORSTATUS CorXferNew(CORSERVER hServer, CORHANDLE hSrc, CORHANDLE hDst, CORXFER_DESC *pDesc, CORXFER *hXfer);`

**Description**      Creates in the specified server's memory a new transfer resource. The new item (*hSrc*, *hDst*) becomes the current item. If the source and/or the destination resource have more than one port, port number 0 will be used.

**Input**            *hServer*      Server handle  
                  *hSrc*          Source of transfer  
                  *hDst*          Destination of transfer  
                  *pDesc*      Transfer description structure. See CORXFER\_DESC Structure Definition  
**Output**            *hXfer*          Transfer resource handle

**Return Value**    `CORSTATUS_OK`  
`CORSTATUS_ARG_INVALID`, `CORSTATUS_ARG_NULL` ( if *hXfer* is NULL), ,  
`CORSTATUS_INVALID_HANDLE`, `CORSTATUS_INCOMPATIBLE_BUFFER`,  
`CORSTATUS_INVALID_HANDLE`, `CORSTATUS_NO_MEMORY`,  
`CORSTATUS_ROUTING_NOT_IMPLEMENTED` and `CORSTATUS_XFER_CANT_CYCLE`

**Note**             If *pDesc* is specified as NULL, automatic source format detection will provide all the information needed to specify the transfer.

                  The specified buffer must be created using `CORBUFFER_VAL_TYPE_CONTIGUOUS` or `CORBUFFER_VAL_TYPE_SCATTER_GATHER` when transferring to a buffer resource. Otherwise, `CORSTATUS_INCOMPATIBLE_BUFFER` is returned.

                  If there is not enough local memory to add the *hSrc* and *hDst* items to the transfer description list, `CORSTATUS_NO_MEMORY` is returned.

                  If there is no available transfer path for the newly added *hSrc* and *hDst* items, `CORSTATUS_ROUTING_NOT_IMPLEMENTED` is returned.

                  For the newly added *hSrc* and *hDst* items in the transfer description list, if the *hDst* resource has been previously added and the transfer resource does not support cycle transfers, `CORSTATUS_XFER_CANT_CYCLE` is returned.

**See Also**        `CorXferFree`, `CorXferAppend` and `CorXferNewEx`



---

## CorXferNewEx

Create in the specified server's memory a new transfer resource

**Prototype**      `CORSTATUS CorXferNewEx(CORSERVER hServer, CORHANDLE hSrc, UINT32 srcPort, CORHANDLE hDst, UINT32 dstPort, CORXFER_DESC *pDesc, CORXFER *hXfer);`

**Description**      Creates in the specified server's memory a new transfer resource. Source and destination resource can have more than one port. The new items *hSrc* and *hDst* are now the current items.

<b>Input</b>	<i>hServer</i>	Server handle
	<i>hSrc</i>	Source of transfer
	<i>srcPort</i>	Source port number
	<i>hDst</i>	Destination of transfer
	<i>dstPort</i>	Destination port number
	<i>pDesc</i>	Transfer description structure. See CORXFER_DESC Structure Definition
<b>Output</b>	<i>hXfer</i>	Transfer resource handle

**Return Value**      `CORSTATUS_OK`  
`CORSTATUS_ARG_INVALID`, `CORSTATUS_ARG_NULL` ( if *hXfer* is NULL ),  
`CORSTATUS_INCOMPATIBLE_BUFFER`, `CORSTATUS_INVALID_HANDLE`,  
`CORSTATUS_NO_MEMORY`, `CORSTATUS_ROUTING_NOT_IMPLEMENTED` and  
`CORSTATUS_XFER_CANT_CYCLE`

**Note**      If *pDesc* is specified as NULL, automatic source format detection will provide all the information needed to specify the transfer.

The specified buffer must have been created using `CORBUFFER_VAL_TYPE_CONTIGUOUS` or `CORBUFFER_VAL_TYPE_SCATTER_GATHER` when transferring to a buffer resource. Otherwise, `CORSTATUS_INCOMPATIBLE_BUFFER` is returned.

If there is not enough local memory to add the *hSrc* and *hDst* items to the transfer description list, `CORSTATUS_NO_MEMORY` is returned.

If there is no available transfer path for the newly added *hSrc* and *hDst* items, `CORSTATUS_ROUTING_NOT_IMPLEMENTED` is returned.

For the newly added *hSrc* and *hDst* items in the transfer description list, if the *hDst* resource has been previously added and the transfer resource does not support cycle transfer for this type of resource, `CORSTATUS_XFER_CANT_CYCLE` is returned.

**See Also**      `CorXferFree` and `CorXferAppendEx`

---

## CorXferRegisterCallback

Register callback function for a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferRegisterCallback</b> (CORXFER <i>hXfer</i> , UINT32 <i>eventType</i> , PCORCALLBACK <i>callbackFct</i> , void * <i>context</i> );	
<b>Description</b>	Registers callback function for the current item of a transfer resource.	
<b>Input</b>	<i>hXfer</i>	Transfer resource handle
	<i>eventType</i>	Type of event to register. The callback function will be called when the specified event(s) occur. See CORXFER_PRM_EVENT_TYPE.
	<i>callbackFct</i>	Callback function must be defined as follow: <i>CORSTATUS CCONV</i> <i>callback ( void *context, UINT32 eventType, UINT32 eventCount);</i>  When called, <i>context</i> contains the value specified at callback function registration; and <i>eventType</i> contains the event(s) that triggered the call to the callback function. The <i>eventCount</i> argument starts with a value of 1, and then is incremented either by the source or the destination handle for the transfer, as specified by the CORXFER_PRM_EVENT_COUNT_SOURCE parameter. This counter is reinitialized each time a new transfer is started by calling <i>CorXferStart</i> . In case the transfer resource can not keep up because there are too many events to be signaled, <i>eventCount</i> will take non-consecutive values, indicating that events have been lost.
		See the Data Types section for the PCORCALLBACK definition.
	<i>context</i>	Context pointer to be passed to the callback function when called
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>callbackFct</i> is NULL), CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_AVAILABLE and CORSTATUS_RESOURCE_IN_USE	
<b>Note</b>	The values may be ORed if more than one event is desired. To select an item (hSrc, hDst) as the current item of a transfer resource, use CorXferSelect. When used, CORXFER_VAL_EVENT_TYPE_END_OF_LINE must be ORed with an <i>unsigned</i> integer representing the line on which the callback function has to be called, while CORXFER_VAL_EVENT_TYPE_END_OF_NLINES must be ORed with an <i>unsigned</i> integer representing the number of lines after which the callback function has to be called.  Also note that the line number for which the callback function is called is not returned through its eventType argument; the corresponding bits are always set to 0.	
<b>See Also</b>	CorXferUnregisterCallback, CorXferSelect and CORXFER_PRM_EVENT_COUNT_SOURCE	

---

## CorXferRegisterCallbackEx

Register callback function for a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferRegisterCallbackEx</b> (CORXFER <i>hXfer</i> , UINT32 <i>xferElement</i> , UINT64 <i>eventType</i> , PCOREVENTINFOCALLBACK <i>callback</i> , void <i>*context</i> );	
<b>Description</b>	Registers callback function for the specified element of a transfer resource.	
<b>Input</b>	<i>hXfer</i>	Transfer resource handle
	<i>xferElement</i>	Indicates where to register the callback: on currently selected pair or level: CORXFER_VAL_ELEMENT_PAIR (0x00000000) CORXFER_VAL_ELEMENT_LEVEL (0x00000001)
	<i>eventType</i>	Type of event to register. See CORXFER_PRM_EVENT_TYPE_EX.
	<i>callback</i>	Callback function to register. The callback function provides information on the corresponding event (in the <i>COREVENTINFO</i> handle). Refer to the <i>EventInfo</i> module for more detail on the available information  CORSTATUS CCONV MyCallback(void <i>*context</i> , COREVENTINFO <i>hEventInfo</i> ) { } }.
<b>Output</b>	<i>context</i>	Context pointer passed to the callback function when called
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>callbackFct</i> is NULL), CORSTATUS_INVALID_HANDLE CORSTATUS_NOT_AVAILABLE and CORSTATUS_RESOURCE_IN_USE	
<b>Note</b>	The values may be ORed if more than one event is desired. To select an item ( <i>hSrc</i> , <i>hDst</i> ) as the current item of a transfer resource, use <i>CorXferSelect</i> . When used, CORXFER_VAL_EVENT_TYPE_END_OF_LINE must be ORed with an <i>unsigned</i> integer representing the line on which the callback function has to be called, while CORXFER_VAL_EVENT_TYPE_END_OF_NLINES must be ORed with an <i>unsigned</i> integer representing the number of lines after which the callback function has to be called.  Also note that the line number for which the callback function is called is not returned through its <i>eventType</i> argument; the corresponding bits are always set to 0.	
<b>See Also</b>	<i>CorXferUnregisterCallbackEx</i> , <i>CorXferSelect</i> and CORXFER_PRM_EVENT_COUNT_SOURCE	

---

## CorXferReset

Reset a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferReset</b> (CORXFER <i>hXfer</i> );	
<b>Description</b>	Deletes the existing transfer routing associated with the specified transfer resource.	
<b>Input</b>	<i>hXfer</i>	Transfer resource handle
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE, CORSTATUS_NOT_ACCESSIBLE, CORSTATUS_RESOURCE_IN_USE and CORSTATUS_XFER_NOT_CONNECTED	

---

## CorXferResetModule

Reset the resources associated with the server's transfer device(s)

<b>Prototype</b>	CORSTATUS <b>CorXferResetModule</b> (CORSERVER <i>hServer</i> );
<b>Description</b>	Resets the resources associated with the server's transfer device(s). It will release all resources (handle, memory) currently allocated. When using this function, make certain that no other application is currently using any transfer device resources. This function should be used with caution.
<b>Input</b>	<i>hServer</i> Server handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE

---

## CorXferSelect

Select an item as the current item of a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferSelect</b> (CORXFER <i>hXfer</i> , CORHANDLE <i>hSrc</i> , CORHANDLE <i>hDst</i> , UINT32 <i>index</i> );
<b>Description</b>	Selects an item as the current item of a transfer resource. If the source and/or the destination resource have more than one port, port number 0 will be used.
<b>Input</b>	<i>hXfer</i> Transfer resource handle <i>hSrc</i> Resource handle (source) <i>hDst</i> Resource handle (destination) <i>index</i> Specifies which item to select. Valid values are in the range [ 0...n-1], where n is the number of items having the same source and destinations. Usually index is 0.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE and CORSTATUS_RESOURCE_IN_USE
<b>See Also</b>	CorXferSelectEx, CorXferGetCap, CorXferGetPrm, CorXferSetPrm, CorXferRegisterCallback, CorXferSetPrmEx and CorXferUnregisterCallback

---

## CorXferSelectEx

Select an item as the current item of a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferSelectEx</b> (CORXFER <i>hXfer</i> , CORHANDLE <i>hSrc</i> , UINT32 <i>srcPort</i> , CORHANDLE <i>hDst</i> , UINT32 <i>dstPort</i> , UINT32 <i>index</i> );
<b>Description</b>	Selects an item as the current item of a transfer resource. Source and destination resource can have more than one port.
<b>Input</b>	<i>hXfer</i> Transfer resource handle <i>hSrc</i> Resource handle (source) <i>srcPort</i> Source port number <i>hDst</i> Resource handle (destination) <i>dstPort</i> Destination port number <i>index</i> Specifies which item to select. Valid values are in the range [ 0...n-1], where n is the number of items having the same source and destinations. Usually, index is 0.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE and CORSTATUS_RESOURCE_IN_USE
<b>See Also</b>	CorXferGetCap, CorXferGetPrm, CorXferSetPrm, CorXferRegisterCallback, CorXferSetPrmEx and CorXferUnregisterCallback

---

## CorXferSetPrm

Set a simple transfer parameter of a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferSetPrm</b> (CORXFER <i>hXfer</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );	
<b>Description</b>	Sets a simple transfer parameter for the current item of a transfer resource.	
<b>Input</b>	<i>hXfer</i>	Transfer resource handle
	<i>prm</i>	Transfer parameter to set
	<i>value</i>	New value of the parameter
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE, CORSTATUS_PRM_INVALID_VALUE, CORSTATUS_PRM_NOT_AVAILABLE and CORSTATUS_PRM_READ_ONLY	
<b>Note</b>	A simple parameter fits inside an UINT32. If the parameter is complex, use CorXferSetPrmEx. To select an item (hSrc, hDst) as the current item of a transfer resource, use CorXferSelect.	
<b>See Also</b>	CorXferSetPrm, CorXferSetPrmEx and CorXferSelect	

---

## CorXferSetPrmEx

Set a complex transfer parameter of a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferSetPrmEx</b> (CORXFER <i>hXfer</i> , UINT32 <i>prm</i> , const void * <i>value</i> );	
<b>Description</b>	Sets a complex transfer parameter for the current item of a transfer resource.	
<b>Input</b>	<i>hXfer</i>	Transfer resource handle
	<i>prm</i>	Transfer parameter to set
	<i>value</i>	New value of the parameter
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>value</i> is NULL) CORSTATUS_INVALID_HANDLE, CORSTATUS_PRM_INVALID_VALUE, CORSTATUS_PRM_NOT_AVAILABLE and CORSTATUS_PRM_READ_ONLY	
<b>Note</b>	A complex parameter is greater than an UINT32. If the parameter size is UINT32, either CorXferSetPrm or CorXferSetPrmEx can be used. To select an item (hSrc, hDst) as the current item of a transfer resource, use CorXferSelect.	
<b>See Also</b>	CorXferGetPrm, CorXferSetPrm and CorXferSelect	

---

## CorXferStart

Start transfer for a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferStart</b> (CORXFER <i>hXfer</i> , UINT32 <i>count</i> );
<b>Description</b>	Starts transfer for a transfer resource
<b>Input</b>	<i>hXfer</i> Transfer object handle <i>count</i> Numerical value within the range [1...CORXFER_CAP_MAX_FRAME_COUNT] or CORXFER_CONTINUOUS.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE, CORSTATUS_NOT_ACCESSIBLE, CORSTATUS_RESOURCE_IN_USE, CORSTATUS_XFER_NOT_CONNECTED, CORSTATUS_TIMEOUT and CORSTATUS_ARG_INVALID
<b>Note</b>	<p>Before calling CorXferStart, the transfer resource has to be connected to the hardware by calling CorXferConnect; otherwise, CORSTATUS_XFER_NOT_CONNECTED is returned.</p> <p>When calling CorXferStart, if a transfer is still in progress and the CORXFER_PRM_START_MODE parameter has been set to CORXFER_VAL_START_MODE_ASYNCHRONOUS, then CORSTATUS_RESOURCE_IN_USE is returned.</p> <p>When calling CorXferStart, if a transfer is still in progress and CORXFER_PRM_START_MODE parameter has been set to CORXFER_VAL_START_MODE_SYNCHRONOUS or CORXFER_VAL_START_MODE_HALF_ASYNCHRONOUS, then CORSTATUS_TIMEOUT is returned.</p> <p>For stopping a transfer started in continuous mode, CorXferStop must first be called to flag the end of the transfer, followed by a call to CorXferWait to wait for the actual end of transfer.</p> <p>If for any reason the source of the transfer does not provide enough data for the transfer to finish, CorXferAbort must be used to force an asynchronous end of transfer. In this situation, calling CorXferStop would have no effect.</p>
<b>See Also</b>	CorXferAbort and CorXferStop

---

## CorXferStop

Stop transfer synchronously for a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferStop</b> (CORXFER <i>hXfer</i> );
<b>Description</b>	Stops transfer synchronously for a transfer resource. Transfer will be stopped at the end of the current frame; therefore, last transferred frame is valid.
<b>Input</b>	<i>hXfer</i> Transfer resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID_VALUE, CORSTATUS_INVALID_HANDLE
<b>Note</b>	<p>Function call returns immediately, therefore current transfers can still be in progress. To detect the actual end of transfer, CorXferWait should be used.</p> <p>If for any reason the source of transfer does not provide enough data for the transfer to finish, CorXferAbort must be used to force an asynchronous end of transfer. In this situation, calling CorXferStop would have no effect.</p>
<b>See Also</b>	CorXferAbort, CorXferStart and CorXferWait

---

## CorXferUnregisterCallback

Unregister callback function for a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferUnregisterCallback</b> (CORXFER <i>hXfer</i> , PCORCALLBACK <i>callbackFct</i> );	
<b>Description</b>	Unregisters callback function for the current item of a transfer resource.	
<b>Input</b>	<i>hXfer</i>	Transfer resource handle
	<i>callbackFct</i>	Callback function to unregister. See the Data Types section for the PCORCALLBACK definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>Note</b>	To select an item (hSrc, hDst) as the current transfer resource, use CorXferSelect.	
<b>See Also</b>	CorXferRegisterCallback and CorXferSelect	

---

## CorXferUnregisterCallbackEx

Unregister callback function for a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferUnregisterCallbackEx</b> (CORXFER <i>hXfer</i> , UINT32 <i>xferElement</i> , PCOREVENTINFOCALLBACK <i>callbackFct</i> );	
<b>Description</b>	Unregisters callback function for the current item of a transfer resource.	
<b>Input</b>	<i>hXfer</i>	Transfer resource handle
	<i>xferElement</i>	Indicates where to unregister the callback: on currently selected pair or level (group):
	CORXFER_VAL_ELEMENT_PAIR	Unregisters the callback for the currently selected source/destination pair.
	CORXFER_VAL_ELEMENT_LEVEL	Unregisters the callback for the currently selected source and all its destination pairs.
	<i>callbackFct</i>	Callback function to unregister. See the Data Types section for the PCOREVENTINFOCALLBACK definition.
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>Note</b>	To select an item (hSrc, hDst) as the current transfer resource, use CorXferSelect.	
<b>See Also</b>	CorXferRegisterCallbackEx and CorXferSelect	

---

## CorXferWait

Wait until end of transfer or until timeout for a transfer resource

<b>Prototype</b>	CORSTATUS <b>CorXferWait</b> (CORXFER <i>hXfer</i> , UINT32 <i>timeout</i> );	
<b>Description</b>	Waits until end of transfer or until timeout for a transfer resource.	
<b>Input</b>	<i>hXfer</i>	Transfer resource handle
	<i>timeout</i>	Maximum time to wait (in ms)
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE, CORSTATUS_XFER_NOT_CONNECTED	
	CORSTATUS_TIMEOUT	
<b>Note</b>	If the transfer has not finished within the specified timeout interval, CORSTATUS_TIMEOUT is returned. The reason could be that the specified timeout interval was too small or that the transfer source didn't provided enough data for the transfer to finish. To asynchronously end the transfer, CorXferAbort function is used.	
<b>See Also</b>	CorXferStart	

---

## View Module

The View Module controls a viewing window within the display device.

### Capabilities

ID	Capability
0x00	<i>Reserved</i>
0x01	<i>Reserved</i>
0x02	CORVIEW_CAP_ZORDER
0x03	CORVIEW_CAP_FLIP
0x04	<i>Reserved</i>
0x05	CORVIEW_CAP_COLOR_SPACE_CONVERT
0x06	CORVIEW_CAP_ROTATE
0x07	CORVIEW_CAP_RANGE
0x08	<i>Reserved</i>
0x09	CORVIEW_CAP_ROI_SRC
0x0a	CORVIEW_CAP_ROI_DST
0x0b	CORVIEW_CAP_ZOOM_HORZ
0x0c	CORVIEW_CAP_ZOOM_HORZ_METHOD
0x0d	CORVIEW_CAP_ZOOM_HORZ_MIN
0x0e	CORVIEW_CAP_ZOOM_HORZ_MAX
0x0f	CORVIEW_CAP_ZOOM_HORZ_MULT
0x10	CORVIEW_CAP_ZOOM_HORZ_MIN_FACTOR
0x11	CORVIEW_CAP_ZOOM_HORZ_MAX_FACTOR
0x12	CORVIEW_CAP_ZOOM_VERT
0x13	CORVIEW_CAP_ZOOM_VERT_METHOD
0x14	CORVIEW_CAP_ZOOM_VERT_MIN
0x15	CORVIEW_CAP_ZOOM_VERT_MAX
0x16	CORVIEW_CAP_ZOOM_VERT_MULT
0x17	CORVIEW_CAP_ZOOM_VERT_MIN_FACTOR
0x18	CORVIEW_CAP_ZOOM_VERT_MAX_FACTOR
0x19	<i>Reserved</i>
0x1a	CORVIEW_CAP_LUT_ENABLE
0x1b	CORVIEW_CAP_LUT
0x1c	<i>Reserved</i>
0x1d	<i>Reserved</i>
0x1e	<i>Reserved</i>
0x1f	<i>Reserved</i>
0x20	CORVIEW_CAP_OVERLAY_MODE
0x21	CORVIEW_CAP_RANGE_MAX



---

## CORVIEW\_CAP\_COLOR\_SPACE\_CONVERT

<b>Description</b>	Specifies whether this view can convert video information from one color space to another (the buffer's color space to the display's color space) while it's being displayed.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, The video information can be converted. FALSE, The video information cannot be converted.

---

## CORVIEW\_CAP\_FLIP

<b>Description</b>	Specifies whether this view can be flipped during display.
<b>Type</b>	UINT32
<b>Values</b>	CORVIEW_VAL_FLIP_X: Can be flipped vertically. CORVIEW_VAL_FLIP_Y: Can be flipped horizontally.
<b>Note</b>	The values may be ORed when both are supported.
<b>See Also</b>	CORVIEW_PRM_FLIP_X and CORVIEW_PRM_FLIP_Y

---

## CORVIEW\_CAP\_LUT

<b>Description</b>	Specifies if an output LUT is available.
<b>Type</b>	UINT32
<b>Values</b>	TRUE: At least one LUT is available. FALSE: No LUT is available.
<b>See Also</b>	CORVIEW_PRM_LUT_MAX and CORVIEW_PRM_LUT_ENABLE

---

## CORVIEW\_CAP\_LUT\_ENABLE

<b>Description</b>	Specifies if an output LUT can be enabled/disabled.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, Output LUT can be enabled/disabled. FALSE, Output LUT cannot be enabled/disabled.

---

## CORVIEW\_CAP\_OVERLAY\_MODE

<b>Description</b>	Specifies the behavior of a view when the overlay is available.
<b>Type</b>	UINT32
<b>Values</b>	See CORVIEW_PRM_MODE.

---

## CORVIEW\_CAP\_RANGE

<b>Description</b>	Specifies whether a range within the pixel bit depth can be designated for viewing.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, The range can be designated for viewing. FALSE, The range cannot be designated for viewing.
<b>Note</b>	Useful when a buffer must be viewed on a display which is only capable of displaying at a lower bit depth than the buffer pixel depth.
<b>See Also</b>	CORVIEW_PRM_RANGE

---

## CORVIEW\_CAP\_RANGE\_MAX

<b>Description</b>	Specifies the maximum value allowed for CORVIEW_PRM_RANGE.
<b>Type</b>	UINT32
<b>Values</b>	The value corresponds to the maximum number of bits of the attached buffer ( <b>CorManGetPixelDepthMax</b> ) minus the view's bit depth.
<b>Note</b>	Useful when a buffer must be viewed on a display that is only capable of displaying at a lower bit depth than the buffer pixel depth.
<b>See Also</b>	CORVIEW_CAP_RANGE and CORVIEW_PRM_RANGE.

---

## CORVIEW\_CAP\_ROTATE

<b>Description</b>	Specifies whether this view can rotate the video information while it is being displayed.
<b>Type</b>	UINT32
<b>Values</b>	CORVIEW_VAL_ROTATE_ANY, Supports arbitrary integer angle rotation. CORVIEW_VAL_ROTATE_90, Supports rotation angles that are a multiple of 90 degrees.
<b>See Also</b>	CORVIEW_PRM_ROTATE

---

## CORVIEW\_CAP\_ROI\_DST

<b>Description</b>	Specifies whether a destination ROI can be defined on the associated display surface. If so, after the ROI is set up, the video information contained within the source ROI is displayed in the destination ROI. This video information is zoomed when necessary to fill the destination ROI.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, The destination ROI can be defined. FALSE, The destination ROI cannot be defined.
<b>Note</b>	Used to be CORVIEW_CAP_WIN_DST
<b>See Also</b>	CORVIEW_PRM_ROI_DST_HEIGHT, CORVIEW_PRM_ROI_DST_LEFT, CORVIEW_PRM_ROI_DST_TOP and CORVIEW_PRM_ROI_DST_WIDTH

---

## CORVIEW\_CAP\_ROI\_SRC

<b>Description</b>	Specifies whether a source ROI can be defined in the associated buffer. If so, after the ROI is set up, only the region delimited by the ROI is displayed.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, The source ROI can be defined. FALSE, The source ROI cannot be defined.
<b>Note</b>	Used to be CORVIEW_CAP_WIN_SRC
<b>See Also</b>	CORVIEW_PRM_ROI_SRC_HEIGHT, CORVIEW_PRM_ROI_SRC_LEFT, CORVIEW_PRM_ROI_SRC_TOP and CORVIEW_PRM_ROI_SRC_WIDTH

---

## CORVIEW\_CAP\_ZOOM\_HORZ

<b>Description</b>	Specifies whether the view supports horizontal zooming.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, The view supports horizontal zooming. FALSE, The view does not support horizontal zooming.
<b>Note</b>	View zoom applies only to a single view, not to the whole display surface.
<b>See Also</b>	CORVIEW_CAP_ZOOM_VERT

---

## **CORVIEW\_CAP\_ZOOM\_HORZ\_MAX**

<b>Description</b>	Maximum valid value (in pixels) for the horizontal zoom.
<b>Type</b>	UINT32
<b>Note</b>	An alternative to CORVIEW_CAP_ZOOM_HORZ_MAX_FACTOR. One and/or the other may be specified.

---

## **CORVIEW\_CAP\_ZOOM\_HORZ\_MAX\_FACTOR**

<b>Description</b>	Maximum horizontal zoom factor.
<b>Type</b>	UINT32
<b>Note</b>	A factor of 1000 is equivalent to a 1:1 zoom (no zoom). An alternative to CORVIEW_CAP_ZOOM_HORZ_MAX. One and/or the other may be specified.

---

## **CORVIEW\_CAP\_ZOOM\_HORZ\_METHOD**

<b>Description</b>	Horizontal zooming method implemented by the view.
<b>Type</b>	INT32
<b>Values</b>	CORVIEW_VAL_ZOOM_METHOD_SIMPLE Simple zoom using pixel dropping or replication. CORVIEW_VAL_ZOOM_METHOD_INTERPOLATION Interpolated zoom. CORVIEW_VAL_ZOOM_METHOD_POW2 Zoom by a power of 2 (for example, 2x, 4x, 8x, and so forth). CORVIEW_VAL_ZOOM_METHOD_INTEGER Zoom by an integer factor (for example, 2x, 3x, 4x, 5x, and so forth).
<b>Note</b>	The values may be ORed if more than one zoom method applies. View zoom applies to a single view, not the whole display surface.

---

## **CORVIEW\_CAP\_ZOOM\_HORZ\_MIN**

<b>Description</b>	Minimum valid value (in pixels) for the horizontal zoom.
<b>Type</b>	UINT32
<b>Note</b>	An alternative to CORVIEW_CAP_ZOOM_HORZ_MIN_FACTOR. One and/or the other may be specified.

---

## **CORVIEW\_CAP\_ZOOM\_HORZ\_MIN\_FACTOR**

<b>Description</b>	Minimum horizontal zoom factor.
<b>Type</b>	UINT32
<b>Note</b>	An alternative to CORVIEW_CAP_ZOOM_HORZ_MIN. A factor of 1000 is equivalent to a 1:1 zoom (no zoom).

---

## **CORVIEW\_CAP\_ZOOM\_HORZ\_MULT**

<b>Description</b>	Granularity (in pixels) for the horizontal zoom parameter.
<b>Type</b>	UINT32
<b>Note</b>	The horizontal zoom dimension must be a multiple of this value.

---

## **CORVIEW\_CAP\_ZOOM\_VERT**

<b>Description</b>	Specifies whether the view supports vertical zooming.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, The display supports vertical zooming. FALSE, The display does not support vertical zooming.
<b>Note</b>	View zoom applies only to a single view, not to the whole display surface.
<b>See Also</b>	CORVIEW_CAP_ZOOM_HORZ

---

## **CORVIEW\_CAP\_ZOOM\_VERT\_MAX**

<b>Description</b>	Maximum valid value (in pixels) for the vertical zoom.
<b>Type</b>	UINT32
<b>Note</b>	An alternative to CORVIEW_CAP_ZOOM_VERT_MAX_FACTOR.

---

## **CORVIEW\_CAP\_ZOOM\_VERT\_MAX\_FACTOR**

<b>Description</b>	Maximum vertical zoom factor.
<b>Type</b>	UINT32
<b>Note</b>	A factor of 1000 is equivalent to a 1:1 zoom (no zoom). An alternative to CORVIEW_CAP_ZOOM_VERT_MAX. One and/or the other may be specified.

---

## **CORVIEW\_CAP\_ZOOM\_VERT\_METHOD**

<b>Description</b>	Vertical zooming method implemented by the view.
<b>Type</b>	INT32
<b>Values</b>	See CORVIEW_PRM_ZOOM_HORZ_METHOD.
<b>Note</b>	The values may be ORed if more than one zoom method applies. View zoom applies to a single view, not the whole display surface.

---

## **CORVIEW\_CAP\_ZOOM\_VERT\_MIN**

<b>Description</b>	Minimum valid value (in pixels) for the vertical zoom.
<b>Type</b>	UINT32
<b>Note</b>	An alternative to CORVIEW_CAP_ZOOM_HORZ_MIN_FACTOR. One and/or the other may be specified.

---

## **CORVIEW\_CAP\_ZOOM\_VERT\_MIN\_FACTOR**

<b>Description</b>	Minimum vertical zoom factor.
<b>Type</b>	UINT32
<b>Note</b>	An alternative to CORVIEW_CAP_ZOOM_VERT_MIN. A factor of 1000 is equivalent to a 1:1 zoom (no zoom). One and/or the other may be specified.

---

## **CORVIEW\_CAP\_ZOOM\_VERT\_MULT**

<b>Description</b>	Granularity (in pixels) for the vertical zoom parameter.
<b>Type</b>	UINT32
<b>Note</b>	The vertical zoom dimension must be a multiple of this value.

---

## **CORVIEW\_CAP\_ZORDER**

<b>Description</b>	Specifies whether this view can be Z-ordered (have its relative position in the Z-plane specified) on the display associated with it.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, The view can be Z-ordered. FALSE, The view cannot be Z-ordered.
<b>See Also</b>	CORVIEW_PRM_ZORDER

## Parameters

ID	Parameter	Attribute
0x00	<i>Reserved</i>	
0x01	CORVIEW_PRM_KEYER_COLOR_RED	Read/Write
0x02	CORVIEW_PRM_KEYER_COLOR_GREEN	Read/Write
0x03	CORVIEW_PRM_KEYER_COLOR_BLUE	Read/Write
0x04	CORVIEW_PRM_KEYER_COLOR_PALETTE	Read/Write
0x05	CORVIEW_PRM_KEYER_CHROMA_LO	Read/Write
0x06	CORVIEW_PRM_KEYER_CHROMA_HI	Read/Write
0x07	<i>Reserved</i>	
0x08	<i>Reserved</i>	
0x09	<i>Reserved</i>	
0x0a	<i>Reserved</i>	
0x0b	<i>Reserved</i>	
0x0c	CORVIEW_PRM_HWND	Read/Write
0x0d	CORVIEW_PRM_LUT_NUMBER	Read/Write
0x0e	CORVIEW_PRM_FLIP_X	Read/Write
0x0f	CORVIEW_PRM_FLIP_Y	Read/Write
0x10	CORVIEW_PRM_ROTATE	Read/Write
0x11	CORVIEW_PRM_ZORDER	Read/Write
0x12	CORVIEW_PRM_RANGE	Read/Write
0x13	<i>Reserved</i>	
0x14	CORVIEW_PRM_ROI_SRC_LEFT	Read/Write
0x15	CORVIEW_PRM_ROI_SRC_TOP	Read/Write
0x16	<i>Reserved</i>	
0x17	CORVIEW_PRM_ROI_SRC_HEIGHT	Read/Write
0x18	CORVIEW_PRM_ROI_SRC_WIDTH	Read/Write
0x19	CORVIEW_PRM_ROI_DST_LEFT	Read/Write
0x1a	CORVIEW_PRM_ROI_DST_TOP	Read/Write
0x1b	CORVIEW_PRM_ROI_DST_HEIGHT	Read/Write
0x1c	CORVIEW_PRM_ROI_DST_WIDTH	Read/Write
0x1d	<i>Reserved</i>	
0x1e	CORVIEW_PRM_LUT_MAX	Read Only
0x1f	CORVIEW_PRM_LUT_ENABLE	Read/Write
0x20	CORVIEW_PRM_LUT_FORMAT	Read Only
0x21	CORVIEW_PRM_MODE	Read Only
0x22	CORVIEW_PRM_OVERLAY_MODE	Read/Write
0x23	CORVIEW_PRM_HWND_TITLE	Read/Write
0x24	<i>Reserved</i>	
0x25	<i>Reserved</i>	
0x26	<i>Reserved</i>	
0x27	<i>Reserved</i>	
0x28	CORVIEW_PRM_ZOOM_HORZ_METHOD	Read/Write
0x29	CORVIEW_PRM_ZOOM_VERT_METHOD	Read/Write

---

## **CORVIEW\_PRM\_ALPHA\_BLEND\_CONST**

<b>Description</b>	Sets the alpha blend constants used for alpha blending between source and destination.
<b>Type</b>	CORVIEW_ALPHA_BLEND_CONSTS
<b>Note</b>	This parameter is a structure. The CorViewSetPrmEx function must be used to set the value.

---

## **CORVIEW\_PRM\_ALPHA\_BLEND\_MODE**

<b>Description</b>	Sets the alpha blending mode. Only effective when alpha blending is enabled with the CORVIEW_PRM_OVERLAY_MODE parameter.
<b>Type</b>	UINT32
<b>Values</b>	<p>CORVIEW_VAL_ALPHA_BLEND_SRC_CONST (0x00000001) The CORVIEW_PRM_ALPHA_BLEND_SRC_CONST will be used as the weighing factor for the source pixels..</p> <p>CORVIEW_VAL_ALPHA_BLEND_DST_CONST (0x00000002) The CORVIEW_PRM_ALPHA_BLEND_DST_CONST is used as the weighing factor for the destination pixels. If this feature is not enabled, the weighing factor used for the destination pixel is (100% - CORVIEW_PRM_ALPHA_BLEND_SRC_CONST)</p>

---

## **CORVIEW\_PRM\_ALPHA\_KEY\_MODE**

<b>Description</b>	Used to read or set the alpha keying mode. This value only has an effect when alpha keying is enabled.with the CORVIEW_PRM_OVERLAY_MODE parameter.
<b>Type</b>	UINT32
<b>Values</b>	<p>CORVIEW_VAL_ALPHA_KEY_SRC_NOT_EQUAL (0x00000001) The source pixel is displayed at full (100%) intensity if the alpha value in the source pixel does not equal CORVIEW_PRM_ALPHA_KEY_VALUE.</p> <p>CORVIEW_VAL_ALPHA_KEY_DST_NOT_EQUAL (0x00000002) The destination pixel is displayed at full (100%) intensity, if the alpha value in the destination pixel does not equal CORVIEW_PRM_ALPHA_KEY_VALUE.</p>

---

## **CORVIEW\_PRM\_ALPHA\_KEY\_VALUE**

<b>Description</b>	Sets the value that is compared with the alpha keying bits of the source or destination surface when alpha keying is enabled.
<b>Type</b>	UINT32
<b>Limits</b>	Value limits - maximum alpha value supported by the destination or source pixel format. RGB5551 surface: value can be 0 or 1 RGB8888 surface: value can be 0 to 255.
<b>Note</b>	CORVIEW_PRM_ALPHA_KEY_MODE indicates whether this value is compared with the alpha bits of the source buffer or the alpha bits of the destination buffer

---

## **CORVIEW\_PRM\_FLIP\_X**

<b>Description</b>	Enable/disable X axis vertical flipping of the source image while the view is displayed.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, Enables vertical flipping. FALSE, Disables vertical flipping.
<b>Note</b>	Valid only when CORVIEW_CAP_FLIP includes the CORVIEW_CAP_FLIP_X flag.
<b>See Also</b>	CORVIEW_CAP_FLIP and CORVIEW_PRM_FLIP_Y

---

## CORVIEW\_PRM\_FLIP\_Y

<b>Description</b>	Enable/disable Y axis horizontal flipping of the source image while the view is displayed.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, Enables horizontal flipping. FALSE, Disables horizontal flipping.
<b>Note</b>	Valid only when CORVIEW_CAP_FLIP includes the CORVIEW_CAP_FLIP_Y flag.
<b>See Also</b>	CORVIEW_CAP_FLIP and CORVIEW_PRM_FLIP_X

---

## CORVIEW\_PRM\_HWND

<b>Description</b>	Window handle to be used as the destination view display surface. When specified, the destination rectangle becomes relative to the window's client area rectangle, instead of the whole display surface.
<b>Type</b>	HWND
<b>Values</b>	Valid window handles including NULL. If set to -1, Sapera will automatically create a window running in a separate thread (supported on single monitor configurations only). In this case, CORVIEW_PRM_HWND can be read later to obtain the HWND of the created window.
<b>Notes</b>	Valid only on a system display. This parameter has 64 bits in Sapera LT for 64-bit Windows, therefore to change its value use the CorViewSetPrmEx function instead of CorViewSetPrm.
<b>See also</b>	CORVIEW_PRM_HWND_TITLE

---

## CORVIEW\_PRM\_HWND\_TITLE

<b>Description</b>	Specifies the title of the window created by Sapera if CORVIEW_PRM_HWND is set to -1.
<b>Type</b>	CHAR[128]
<b>Values</b>	Zero-terminated array of characters with a fixed size of 128 bytes.
<b>See Also</b>	CorViewSetPrmEx

---

## CORVIEW\_PRM\_KEYER\_CHROMA\_HI

<b>Description</b>	The upper keying color range used with CORVIEW_VAL_KEYER_TYPE_CHROMA color keyer.
<b>Type</b>	UINT32
<b>Values</b>	<i>Unsigned</i> integer with format dependent on the color mode of the target display.
<b>Note</b>	Colors for all color modes are defined using an UINT32 value, although some of them will not be represented in the full 32 bits.
<b>See Also</b>	CORVIEW_PRM_KEYER_CHROMA_LO

---

## CORVIEW\_PRM\_KEYER\_CHROMA\_LO

<b>Description</b>	The lower keying color range used with a CORVIEW_VAL_KEYER_TYPE_CHROMA color keyer.
<b>Type</b>	UINT32
<b>Values</b>	<i>Unsigned</i> integer with format dependent on the color mode of the target display.
<b>Note</b>	Colors for all color modes are defined using an UINT32 value, although some of them will not be represented in the full 32 bits.
<b>See Also</b>	CORVIEW_PRM_KEYER_CHROMA_HI



---

### CORVIEW\_PRM\_KEYER\_COLOR\_BLUE

<b>Description</b>	The blue component ( 0 to 255 ) of the keying color used with a CORVIEW_VAL_KEYER_TYPE_COLOR color keyer.
<b>Type</b>	UINT32
<b>Note</b>	Used in all color display modes except 256-color.

---

### CORVIEW\_PRM\_KEYER\_COLOR\_GREEN

<b>Description</b>	The green component ( 0 to 255 ) of the keying color used with a CORVIEW_VAL_KEYER_TYPE_COLOR color keyer.
<b>Type</b>	UINT32
<b>Note</b>	Used in all color display modes except 256-color.

---

### CORVIEW\_PRM\_KEYER\_COLOR\_PALETTE

<b>Description</b>	The palette keying index used with a CORVIEW_VAL_KEYER_TYPE_COLOR color keyer.
<b>Type</b>	UINT32
<b>Values</b>	<i>Unsigned</i> integer values [0...255]
<b>Note</b>	Used only in the 256-color display mode.

---

### CORVIEW\_PRM\_KEYER\_COLOR\_RED

<b>Description</b>	The red component ( 0 to 255 ) of the keying color used with a CORVIEW_VAL_KEYER_TYPE_COLOR color keyer.
<b>Type</b>	UINT32
<b>Note</b>	Used in all color display modes except 256-color.

---

### CORVIEW\_PRM\_LUT\_ENABLE

<b>Description</b>	Enable/disable the output LUT after checking CORVIEW_CAP_LUT_ENABLE.
<b>Type</b>	UINT32
<b>Values</b>	TRUE, Enable the output LUT. FALSE, Disable the output LUT.

---

### CORVIEW\_PRM\_LUT\_FORMAT

<b>Description</b>	LUT format
<b>Type</b>	UINT32
<b>Note</b>	Read only parameter.

---

### CORVIEW\_PRM\_LUT\_MAX

<b>Description</b>	Maximum number of LUTs available, based on the current pixel depth and format.
<b>Type</b>	UINT32
<b>Note</b>	Read only parameter.

---

## CORVIEW\_PRM\_LUT\_NUMBER

<b>Description</b>	Selects an active output LUT from among those available.
<b>Type</b>	UINT32
<b>Values</b>	[0...CORVIEW_CAP_LUT - 1]
<b>Note</b>	Valid only when CORVIEW_CAP_LUT is not zero.

---

## CORVIEW\_PRM\_MODE

<b>Description</b>	Specifies the type of transfer between the buffer and the viewer. This parameter reflects the mode specified by the argument in the CorViewNew function. If the mode specified is CORVIEW_VAL_MODE_AUTO_DETECT, then the mode selected by the driver is returned.
<b>Type</b>	UINT32
<b>Values</b>	See CorViewNew
<b>See Also</b>	CorBufferNew, CORVIEW_PRM_OVERLAY_MODE, CORVIEW_PRM_KEYER_COLOR_PALETTE, CORVIEW_PRM_KEYER_COLOR_RED, CORVIEW_PRM_KEYER_COLOR_GREEN, CORVIEW_PRM_KEYER_COLOR_BLUE, CORVIEW_PRM_KEYER_CHROMA_HI and CORVIEW_PRM_KEYER_CHROMA_LO
<b>Note</b>	Read only parameter.

---

## CORVIEW\_PRM\_OVERLAY\_MODE

<b>Description</b>	Specifies the behavior of a view when CORVIEW_PRM_MODE is set to CORVIEW_VAL_MODE_OVERLAY.
<b>Type</b>	UINT32
<b>Values</b>	<p>CORVIEW_VAL_OVERLAY_MODE_ALWAYS_ON_TOP No color keying scheme is in effect. The associated buffer's contents will be displayed directly on the screen using the display adapter's overlay hardware. This is the fastest method, but its drawback is that other windows will not be displayed correctly if they come in front of the Sapera application that has the overlay.</p> <p>CORVIEW_VAL_OVERLAY_MODE_AUTO_COLOR_KEYING A destination key color scheme is enabled, that is, a source buffer pixel will only be displayed if the corresponding pixel on the display surface has the key color. Each time CorViewShow is called, the defined key color is painted on the display surface ROI. Calling CorViewOnPaint will only repaint the key color on the portion of the display surface that has been revealed</p> <p>CORVIEW_VAL_OVERLAY_MODE_MANUAL_COLOR_KEYING Similar to auto-keying mode, but the user is responsible for painting the key color on the display surface. This gives the user more flexibility as to where the overlay image should be displayed. An easy way to paint the key color is to use a video memory off-screen buffer that contains the key color. This buffer can be copied very quickly to the display surface by the display adapter's hardware and thus minimizes the CPU load.</p>
<b>See Also</b>	CorBufferNew, CorViewNew, CORVIEW_PRM_KEYER_COLOR_PALETTE, CORVIEW_PRM_KEYER_COLOR_RED, CORVIEW_PRM_KEYER_COLOR_GREEN, CORVIEW_PRM_KEYER_COLOR_BLUE, CORVIEW_PRM_KEYER_CHROMA_HI and CORVIEW_PRM_KEYER_CHROMA_LO

---

## CORVIEW\_PRM\_RANGE

<b>Description</b>	Specifies how many of the most significant bits are not to be displayed. If the display only uses a subset of the image data (for example, a 32-bit image on an 8-bit display), this parameter's value determines the offset of the subset from the image data high bit.
<b>Type</b>	UINT32
<b>Values</b>	[0...CORVIEW_CAP_RANGE_MAX]
<b>Note</b>	Valid only when CORVIEW_CAP_RANGE is not zero. Useful when a buffer must be viewed on a display which can only display at a lower bit depth than the buffer pixel depth (for example, 16-bit monochrome buffers). Refer to CORVIEW_CAP_RANGE_MAX for the maximum value allowed for this parameter.

---

## CORVIEW\_PRM\_ROTATE

<b>Description</b>	Specifies the angle that the source image is rotated when the view is being displayed.
<b>Type</b>	UINT32
<b>Values</b>	[0...359] If the CORVIEW_CAP_ROTATE capability includes the CORVIEW_VAL_ROTATE_90 flag, only values of 0, 90, 180, and 270 are valid.
<b>Note</b>	Valid only when CORVIEW_CAP_ROTATE is not zero.

---

## CORVIEW\_PRM\_ROI\_DST\_HEIGHT

<b>Description</b>	Height of the destination ROI of the display surface which is associated with the view.
<b>Type</b>	UINT32
<b>Values</b>	[0...display height-CORVIEW_PRM_ROI_DST_TOP] or [0...window client area height-CORVIEW_PRM_ROI_DST_TOP]
<b>Note</b>	Valid only when CORVIEW_CAP_ROI_DST is not zero. By default, the initial source ROI dimensions are the same as those of the source buffer. When the destination ROI dimensions differ from those of the source ROI, the source buffer will be zoomed.

---

## CORVIEW\_PRM\_ROI\_DST\_LEFT

<b>Description</b>	Left edge coordinate of the destination ROI relative to the coordinates of the display surface associated with the view. If a display window is specified, the coordinate is relative to the display window's client area.
<b>Type</b>	UINT32
<b>Values</b>	[0...display width-1] or [0...window client area width-1]
<b>Note</b>	Valid only when CORVIEW_CAP_ROI_DST is not zero. By default, the initial destination ROI dimensions are the same as those of the source buffer.

---

## CORVIEW\_PRM\_ROI\_DST\_TOP

<b>Description</b>	Top edge coordinate of the destination ROI relative to the coordinates of the display surface associated with the view. If a display window is specified, the coordinate is relative to the display window's client area.
<b>Type</b>	UINT32
<b>Values</b>	[0...display height-1] or [0...window client area height-1]
<b>Note</b>	Valid only when CORVIEW_CAP_ROI_DST is not zero. By default, the initial destination ROI dimensions are the same as those of the source buffer.

---

**CORVIEW\_PRM\_ROI\_DST\_WIDTH**

<b>Description</b>	Width of the destination ROI of the display surface associated with the view.
<b>Type</b>	UINT32
<b>Values</b>	[0...display width- CORVIEW_PRM_ROI_DST_LEFT] or [0...window client area width-CORVIEW_PRM_ROI_DST_LEFT]
<b>Note</b>	Valid only when CORVIEW_CAP_ROI_DST is not zero. By default, the initial source ROI dimensions are the same as those of the source buffer. When the destination ROI dimensions differ from those of the source ROI, the source buffer will be zoomed.

---

**CORVIEW\_PRM\_ROI\_SRC\_HEIGHT**

<b>Description</b>	Height of the source ROI of the buffer associated with the view.
<b>Type</b>	UINT32
<b>Values</b>	[0...buffer height-CORVIEW_PRM_ROI_SRC_TOP]
<b>Note</b>	Valid only when CORVIEW_CAP_ROI_SRC is not zero. By default, the initial source ROI dimensions are the same as those of the source buffer. When the source ROI dimensions differ from those of the destination ROI, the source buffer will be zoomed.

---

**CORVIEW\_PRM\_ROI\_SRC\_LEFT**

<b>Description</b>	Left edge coordinate of the source ROI relative to the coordinates of the buffer associated with the view.
<b>Type</b>	UINT32
<b>Values</b>	[0...buffer width-1]
<b>Note</b>	Valid only when CORVIEW_CAP_ROI_SRC is not zero. By default, the initial source ROI dimensions are the same as those of the source buffer.

---

**CORVIEW\_PRM\_ROI\_SRC\_TOP**

<b>Description</b>	Top edge coordinate of the source ROI relative to the coordinates of the buffer associated with the view.
<b>Type</b>	UINT32
<b>Values</b>	[0...buffer height-1]
<b>Note</b>	Valid only when CORVIEW_CAP_ROI_SRC is not zero. By default, the initial source ROI dimensions are the same as those of the source buffer.

---

**CORVIEW\_PRM\_ROI\_SRC\_WIDTH**

<b>Description</b>	Width of the source ROI of the buffer associated with the view.
<b>Type</b>	UINT32
<b>Values</b>	[0...buffer width-CORVIEW_PRM_ROI_SRC_LEFT]
<b>Note</b>	Valid only when CORVIEW_CAP_ROI_SRC is not zero. By default, the initial source ROI dimensions are the same as those of the source buffer. When the source ROI dimensions differ from those of the destination ROI, the source buffer will be zoomed.

---

## CORVIEW\_PRM\_ZOOM\_HORZ\_METHOD

<b>Description</b>	Sets the zooming horizontal method.
<b>Type</b>	UINT32
<b>Values</b>	<p>CORVIEW_VAL_ZOOM_METHOD_SIMPLE Simple zoom using pixel dropping or replication.</p> <p>CORVIEW_VAL_ZOOM_METHOD_INTERPOLATION Interpolated zoom.</p> <p>CORVIEW_VAL_ZOOM_METHOD_POW2 Zoom by a power of 2 (for example, 2x, 4x, 8x, and so forth).</p> <p>CORVIEW_VAL_ZOOM_METHOD_INTEGER Zoom by an integer factor (for example, 2x, 3x, 4x, 5x, and so forth)</p>
<b>See also</b>	CORVIEW_CAP_ZOOM_HORZ_METHOD

---

## CORVIEW\_PRM\_ZOOM\_VERT\_METHOD

<b>Description</b>	Sets the zooming vertical method.
<b>Type</b>	UINT32
<b>Values</b>	<p>CORVIEW_VAL_ZOOM_METHOD_SIMPLE Simple zoom using pixel dropping or replication.</p> <p>CORVIEW_VAL_ZOOM_METHOD_INTERPOLATION Interpolated zoom.</p> <p>CORVIEW_VAL_ZOOM_METHOD_POW2 Zoom by a power of 2 (for example, 2x, 4x, 8x, and so forth).</p> <p>CORVIEW_VAL_ZOOM_METHOD_INTEGER Zoom by an integer factor (for example, 2x, 3x, 4x, 5x, and so forth)</p>
<b>See also</b>	CORVIEW_CAP_ZOOM_VERT_METHOD

---

## CORVIEW\_PRM\_ZORDER

<b>Description</b>	The relative ordering of this view in relation to other views on the same display surface. Used when there is more than one keyed view on a dedicated display, such as an overlay or pass-through.
<b>Type</b>	UINT32
<b>Values</b>	[0...topmost view on this display]
<b>Note</b>	Valid only when CORVIEW_CAP_ZORDER is not zero.

## Functions

Function	Description
CorViewBlit	<i>Copies data between the off-screen/overlay buffers associated with the views</i>
CorViewFree	<i>Releases handle to a view resource</i>
CorViewGetCap	<i>Gets view capability value from a view resource</i>
CorViewGetLut	<i>Gets output LUT values from a view resource</i>
CorViewGetPrm	<i>Gets view parameter value from a view resource</i>
CorViewHide	<i>Stops displaying a view resource</i>
CorViewNew	<i>Creates in the specified server's memory a new view resource</i>
CorViewOnMove	<i>WM_MOVE handler callback function of a view resource</i>
CorViewOnPaint	<i>WM_PAINT handler callback function of a view resource</i>
CorViewOnSize	<i>WM_SIZE handler callback function of a view resource</i>
CorViewSetBuffer	<i>Set a new buffer resource for a view resource</i>
CorViewSetLut	<i>Sets output LUT values to a view resource</i>
CorViewSetPrm	<i>Sets a simple view parameter of a view resource</i>
CorViewSetPrmEx	<i>Sets a complex view parameter of a view resource</i>
CorViewShow	<i>Displays a view resource</i>
CorViewShowWithOps	<i>Displays a view resource using alternate parameters</i>
CorViewUpdatePos	<i>Updates position of a view resource</i>

---

## CorViewBlit

Copies data between the off-screen/overlay buffers associated with the views

**Prototype**      `CORSTATUS CorViewBlit(CORVIEW hSource, CORVIEW hDest, UINT32 ops, CORVIEW_BLIT_DESC *prms);`

**Description**    Copies ("blits") data between the off-screen/overlay buffers associated with the views.

**Input**

<i>hSource</i>	Source view resource handle
<i>hDest</i>	Destination view resource handle
<i>ops</i>	Operations to be applied during the blit. Can be ORed to combine operations. CORVIEW_OPS_SRC_ROI Override the source ROI defined for the source view. CORVIEW_OPS_DST_ROI Override the source ROI defined for the destination view. CORVIEW_OPS_ROTATION Rotate the source image by a given angle into the destination image. CORVIEW_OPS_MIRROR_UP_DOWN Flip the source image vertically into the destination image. CORVIEW_OPS_MIRROR_LEFT_RIGHT Flip the source image horizontally into the destination image CORVIEW_OPS_COLOR_FILL Disregard source buffer contents; fill the destination with a given color. CORVIEW_OPS_SRC_KEY_COLOR Apply a source key color scheme during the blit. Only the source pixels not corresponding to the key color will get copied. CORVIEW_OPS_DST_KEY_COLOR Apply a destination key color scheme during the blit. Only the destination pixels corresponding to the key color will get copied.
<i>prms</i>	Pointer to a structure containing parameters that affect the blit operations. See CORVIEW_BLIT_DESC Structure Definition.

**Output**            None

**Return Value**    `CORSTATUS_OK`  
`CORSTATUS_INCOMPATIBLE_VIEW`, `CORSTATUS_DDRAW_ERROR`,  
`CORSTATUS_ARG_INVALID_VALUE`, `CORSTATUS_ARG_NULL` ( if *prms* is NULL) and  
`CORSTATUS_NOT_IMPLEMENTED`

**Note**              The source and destination views must be associated with either off-screen or overlay buffers. The pixel formats of the buffers should be the same. Not all operations are necessarily supported, alone or combined. Since CorViewBlit uses hardware acceleration (through DirectDraw (Windows XP 32-bit only)), the supported operations may depend on the display adapter's hardware, driver version, and buffer pixel formats. The operations supported are not necessarily the same for overlay buffers as for off-screen buffers.

**See Also**         CorViewNew

---

## CorViewFree

Release handle to a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewFree</b> (CORVIEW <i>hView</i> );
<b>Description</b>	Releases handle to a view resource.
<b>Input</b>	<i>hView</i> View resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_DDRAW_ERROR, CORSTATUS_INVALID_HANDLE and CORSTATUS_RESOURCE_IN_USE
<b>Note</b>	The <i>hView</i> handle is invalid after a call to this function. Only after the view has been destroyed when using this function can the buffer be destroyed. An attempt to do otherwise will cause an error in CorBufferFree. Likewise, the display may not be released before the view using it is destroyed.
<b>See Also</b>	CorViewNew and CorBufferFree

---

## CorViewGetCap

Get view capability value from a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewGetCap</b> (CORVIEW <i>hView</i> , UINT32 <i>cap</i> , UINT32 * <i>value</i> );
<b>Description</b>	Gets view capability value from a view resource
<b>Input</b>	<i>hView</i> View resource handle <i>cap</i> View resource capability requested
<b>Output</b>	<i>value</i> Value of the capability
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>value</i> is NULL), CORSTATUS_CAP_INVALID, CORSTATUS_CAP_NOT_AVAILABLE and CORSTATUS_INVALID_HANDLE
<b>Note</b>	If the capability number passed as the argument does not exist, CORSTATUS_CAP_INVALID is returned. If the capability is not valid on a particular device, CORSTATUS_CAP_NOT_AVAILABLE is returned.
<b>See Also</b>	CorViewGetPrm and CorViewSetPrm

---

## CorViewGetLut

Gets output LUT values from a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewGetLut</b> (CORVIEW <i>hView</i> , CORLUT <i>hLut</i> , UINT32 <i>lutNumber</i> );
<b>Description</b>	Copies the values of the LUT specified by <i>lutNumber</i> into <i>hLut</i> .
<b>Input</b>	<i>hView</i> View resource handle <i>hLut</i> LUT resource handle <i>lutNumber</i> LUT number in view resource
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE, CORSTATUS_CAP_NOT_AVAILABLE, CORSTATUS_INCOMPATIBLE_LUT and CORSTATUS_INVALID_HANDLE
<b>Note</b>	This function will succeed only if the CORVIEW_CAP_LUT capability is TRUE; otherwise, CORSTATUS_CAP_NOT_AVAILABLE is returned. If multiple LUTs are available for the view, the values of the one specified by <i>lutNumber</i> will be copied. The LUT number value range is [0...CORVIEW_PRM_MAX_LUT1].
<b>See Also</b>	CorViewSetLut and CORVIEW_PRM_LUT_NUMBER



---

## CorViewGetPrm

Get view parameter value from a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewGetPrm</b> (CORVIEW <i>hView</i> , UINT32 <i>prm</i> , void * <i>value</i> );
<b>Description</b>	Gets view parameter value from a view resource.
<b>Input</b>	<i>hView</i> View resource handle <i>prm</i> View parameter requested
<b>Output</b>	<i>value</i> Current value of the parameter
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL (if <i>value</i> is NULL), CORSTATUS_INVALID_HANDLE, CORSTATUS_PRM_INVALID and CORSTATUS_PRM_NOT_AVAILABLE
<b>Note</b>	If the parameter number passed as the argument does not exist, CORSTATUS_PRM_INVALID is returned. If the parameter is not valid on a particular device, CORSTATUS_PRM_NOT_AVAILABLE is returned.
<b>See Also</b>	CorViewGetCap and CorViewSetPrm

---

## CorViewHide

Stops displaying a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewHide</b> (CORVIEW <i>hView</i> );
<b>Description</b>	Stops displaying a view resource.
<b>Input</b>	<i>hView</i> View resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_DDRAW_ERROR, CORSTATUS_INVALID_HANDLE
<b>Note</b>	CORSTATUS_DDRAW_ERROR is returned when an error occurs while accessing DirectDraw (Windows XP 32-bit only) implementation.
<b>See Also</b>	CorViewShow

---

## CorViewNew

Create in the specified server's memory a new view resource

<b>Prototype</b>	CORSTATUS <b>CorViewNew</b> (CORSERVER <i>hServer</i> , CORDISPLAY <i>hDisplay</i> , CORBUFFER <i>hBuffer</i> , UINT32 <i>mode</i> , CORVIEW * <i>hView</i> );	
<b>Description</b>	Create a new view resource in a specific mode from the display and buffer parameters.	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>hDisplay</i>	Display resource handle
	<i>hBuffer</i>	Buffer resource handle
	<i>mode</i>	Viewing mode. With Sapera 3.50 or later, use the auto-detect mode. CORVIEW_VAL_MODE_AUTO_DETECT, The appropriate mode will be selected among the three following modes depending on the buffer. CORVIEW_VAL_MODE_DIB, This mode uses a device-independent bitmap to represent and transfer buffer data to the display. This option can only be selected if the buffer is of type contiguous, scatter-gather, or virtual. If the buffer is of one of those types, the auto-detect option will automatically choose this option. CORVIEW_VAL_MODE_OVERLAY, This mode uses the display adapter's overlay hardware to display the overlay buffer. If a keying operation is performed, the overlay buffer will be displayed only if the color of the corresponding pixel, seen on the display, has a specific value or a value within a given range. The default value of the key color can be modified. Furthermore, this is the fastest mode since it does not require any data transfer. Note that this option can only be selected if the buffer is of type <i>overlay</i> , and if it is, the auto-detect option will automatically choose this mode.
<b>Output</b>	<i>hView</i>	View resource handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>hView</i> is NULL), CORSTATUS_DDRAW_ERROR, CORSTATUS_DDRAW_NOT_AVAILABLE, CORSTATUS_INCOMPATIBLE_BUFFER, CORSTATUS_INCOMPATIBLE_LOCATION, CORSTATUS_INVALID_HANDLE and CORSTATUS_NO_MEMORY	
<b>Note</b>	If the buffer cannot be associated with the display or the desired viewing mode is not available, the view is not created and CORSTATUS_DDRAW_ERROR is returned. If the <i>hBuffer</i> or <i>hDisplay</i> parameters are not on the same server as the <i>server</i> parameter, the view is not created and CORSTATUS_INCOMPATIBLE_LOCATION is returned. If the buffer type is not compatible with the mode, the view is not created and CORSTATUS_INCOMPATIBLE_BUFFER is returned. The buffer cannot be destroyed before the view using it is destroyed. An attempt to do so will cause an error in CorBufferFree. This also applies to the display handle.	
<b>See Also</b>	CORBUFFER_PRM_TYPE and CORVIEW_PRM_OVERLAY_MODE	

---

## CorViewOnMove

WM\_MOVE handler callback function of a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewOnMove</b> (CORVIEW <i>hView</i> );
<b>Description</b>	A callback function that should be called in the WM_MOVE message handler of the target window if the display is a system display and CORVIEW_PRM_HWND is not 0.
<b>Input</b>	<i>hView</i> View resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_DDRAW_ERROR and CORSTATUS_INVALID_HANDLE
<b>Note</b>	If CORVIEW_PRM_HWND is 0, CORSTATUS_PRM_INVALID_VALUE is returned. CORSTATUS_DDRAW_ERROR is returned for errors while accessing DirectDraw (Windows XP 32-bit only).
<b>See Also</b>	CorViewHide, CorViewShow and CorViewUpdatePos

---

## CorViewOnPaint

WM\_PAINT handler callback function of a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewOnPaint</b> (CORVIEW <i>hView</i> );
<b>Description</b>	A callback function that should be called in the WM_PAINT message handler of the target window if the display is a system display and CORVIEW_PRM_HWND is not 0.
<b>Input</b>	<i>hView</i> View resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_DDRAW_ERROR and CORSTATUS_INVALID_HANDLE
<b>Note</b>	The only difference with CorViewShow is in the case of an auto-keying overlay. In that case, CorViewOnPaint will repaint the key color only in the region of the view's ROI which has been invalidated since the last call of CorViewOnPaint or CorViewShow; whereas CorViewShow will repaint the key color on the whole ROI. If CORVIEW_PRM_HWND is 0, CORSTATUS_PRM_INVALID_VALUE is returned. CORSTATUS_DDRAW_ERROR is returned when an error occurs while accessing the DirectDraw (Windows XP 32-bit only) implementation.
<b>See Also</b>	CorViewHide, CorViewShow and CorViewUpdatePos

---

## CorViewOnSize

WM\_SIZE handler callback function of a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewOnSize</b> (CORVIEW <i>hView</i> );
<b>Description</b>	A callback function that should be called in the WM_SIZE message handler of the target window if the display is a system display and CORVIEW_PRM_HWND is not 0.
<b>Input</b>	<i>hView</i> View resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_DDRAW_ERROR and CORSTATUS_INVALID_HANDLE
<b>Note</b>	If CORVIEW_PRM_HWND is 0, CORSTATUS_PRM_INVALID_VALUE is returned. CORSTATUS_DDRAW_ERROR is returned for errors while accessing DirectDraw (Windows XP 32-bit only).
<b>See Also</b>	CorViewHide, CorViewShow and CorViewUpdatePos

---

## CorViewSetBuffer

Set a new buffer resource for a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewSetBuffer</b> (CORVIEW <i>hView</i> , CORBUFFER <i>hBuffer</i> );		
<b>Description</b>	Sets a new buffer resource for a view resource		
<b>Input</b>	<i>hView</i>	View resource handle	
	<i>hBuffer</i>	Buffer resource handle	
<b>Notes</b>	New buffer resource must have the same size and format as the buffer resource that has been specified when creating the view resource.		
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE and CORSTATUS_ARG_INVALID		
<b>See Also</b>	CorViewNew		

---

## CorViewSetLut

Sets output LUT values to a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewSetLut</b> (CORVIEW <i>hView</i> , CORLUT <i>hLut</i> , UINT32 <i>lutNumber</i> );		
<b>Description</b>	Copies the values of hLut into the LUT specified by lutNumber.		
<b>Input</b>	<i>hView</i>	View resource handle	
	<i>hLut</i>	LUT resource handle created with CorLutNew or CorLutNewFromFile.	
	<i>lutNumber</i>	LUT number in View resource. If multiple LUTs are available for the View, the values of the one specified by lutNumber will be copied. The <i>lutNumber</i> value range is [0...CORVIEW_CAP_LUT-1].	
<b>Output</b>	None		
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_OUT_OF_RANGE, CORSTATUS_CAP_NOT_AVAILABLE, CORSTATUS_INCOMPATIBLE_LUT, CORSTATUS_INVALID_HANDLE and CORSTATUS_NOT_IMPLEMENTED		
<b>Note</b>	This function will succeed only if the CORVIEW_CAP_LUT capability is TRUE; otherwise, CORSTATUS_CAP_NOT_AVAILABLE is returned.		
<b>See Also</b>	CorViewGetLut and CORVIEW_PRM_LUT_NUMBER		

---

## CorViewSetPrm

Sets a simple view parameter of a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewSetPrm</b> (CORVIEW <i>hView</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );		
<b>Description</b>	Sets a simple view parameter to a new value		
<b>Input</b>	<i>hView</i>	View resource handle	
	<i>prm</i>	View parameter to modify	
	<i>value</i>	New value of the parameter	
<b>Output</b>	None		
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE, CORSTATUS_PRM_INVALID and CORSTATUS_PRM_NOT_AVAILABLE		
<b>See Also</b>	CorViewGetPrm and CorViewGetCap		

---

## CorViewSetPrmEx

Sets a complex view parameter of a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewSetPrmEx</b> (CORVIEW <i>hView</i> , UINT32 <i>param</i> , const void * <i>value</i> );
<b>Description</b>	Sets a complex view parameter to a new value
<b>Input</b>	<i>hView</i> View resource handle <i>param</i> View parameter to modify <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE, CORSTATUS_PRM_INVALID, CORSTATUS_PRM_NOT_AVAILABLE and CORSTATUS_PRM_READ_ONLY
<b>Note</b>	A complex parameter is greater than a UINT32 (like CORVIEW_PRM_HWND_TITLE). If the parameter size is UINT32, use either CorViewSetPrm or CorViewSetPrmEx.
<b>See Also</b>	CorViewGetPrm and CorViewGetCap

---

## CorViewShow

Displays a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewShow</b> (CORVIEW <i>hView</i> );
<b>Description</b>	Displays a view resource.
<b>Input</b>	<i>hView</i> View resource handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE, CORSTATUS_DDRAW_ERROR CORSTATUS_NOT_ACCESSIBLE, CORSTATUS_INCOMPATIBLE_BUFFER
<b>Note</b>	<p>Displays the view using the mode specified at the creation of the view. If the buffer associated with the view is an overlay and the value of CORVIEW_PRM_MODE is CORVIEW_VAL_OVERLAY MODE_AUTO_KEYING, CorViewShow will paint the chosen keying color in the client area of the target window, provided CORVIEW_PRM_HWND is not 0 and the display is a system display.</p> <p>If the buffer associated with the view is an overlay buffer, calling CorViewShow will return an error if the pixel format is not listed in CORDISPLAY_PRM_PIXEL_TYPE_OVERLAY. If the associated buffer is an off-screen buffer, calling CorViewShow may take more time to execute if that buffer's pixel format is not listed in CORDISPLAY_PRM_PIXEL_TYPE_OFFSCREEN. In that case, the conversion of pixel format and copying to display memory is done in software.</p> <p>For multiformat buffers (for example, CORBUFFER_VAL_FORMAT_RGB888_MONO8 and CORBUFFER_VAL_FORMAT_RGB161616_MONO16) the buffer to display, mono or RGB, is set by CORBUFFER_PRM_PAGE. Note, it is not required to use CorViewFree/CorViewNew when switching buffer pages.</p>
<b>See Also</b>	CorViewHide, CorViewShowWithOps, CORVIEW_PRM_MODE and CORVIEW_PRM_OVERLAY_MODE

---

## CorViewShowWithOps

Displays a view resource using alternate parameters

<b>Prototype</b>	CORSTATUS <b>CorViewShowWithOps</b> (CORVIEW <i>hView</i> , UINT32 <i>ops</i> , CORVIEW_BLIT_DESC <i>*prms</i> );		
<b>Description</b>	Displays a view resource using alternate parameters, using the mode specified by the buffer associated with the view.		
<b>Input</b>	<i>hView</i>	View resource handle	
	<i>ops</i>	Blit operations to apply which override the view resource's parameters. Valid values are the same as for the <i>ops</i> parameter of CorViewBlit.	
	<i>prms</i>	Pointer to a structure containing parameters that affect the blit operations. See CORVIEW_BLIT_DESC Structure Definition	
<b>Output</b>	None		
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE, CORSTATUS_DDRAW_ERROR and CORSTATUS_NOT_ACCESSIBLE		
<b>Note</b>	Displays the view using the mode specified by the buffer associated with the view. Calling CorViewShowWithOps for a view whose associated buffer's type is not CORBUFFER_VAL_TYPE_OFFSCREEN or CORBUFFER_VAL_TYPE_OVERLAY, will return an error.  If the buffer associated with the view is an overlay and the value of CORVIEW_PRM_OVERLAY_MODE is CORVIEW_VAL_OVERLAY_MODE_AUTO_KEYING, CorViewShowWithOps will paint the chosen keying color in the client area of the target window, provided CORVIEW_PRM_HWND is not 0 and the display is a system display.		
<b>See Also</b>	CorViewBlit and CorViewHide		

---

## CorViewUpdatePos

Updates the position of a view resource

<b>Prototype</b>	CORSTATUS <b>CorViewUpdatePos</b> (CORVIEW <i>hView</i> );		
<b>Description</b>	Updates the position of the view on the display surface without showing it. CorViewUpdatePos will take into account the current CORVIEW_PRM_ROI_SRC and CORVIEW_PRM_ROI_DST as well as the new target window position if the display is a system display and CORVIEW_PRM_HWND is not 0.		
<b>Input</b>	<i>hView</i>	View resource handle	
<b>Output</b>	None		
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE		
<b>See Also</b>	CorViewHide and CorViewShow		

## CORVIEW\_BLIT\_DESC Structure Definition

```
// CORVIEW_BLIT_DESC Structure Definition
typedef struct
{
    UINT32 roi_src_left;    //roi values are coordinates in pixels,
                           //relative to the respective buffers
    UINT32 roi_src_top;
    UINT32 roi_src_height;
    UINT32 roi_src_width;
    UINT32 roi_dst_left;
    UINT32 roi_dst_top;
    UINT32 roi_dst_height;
    UINT32 roi_dst_width;
    UINT32 rotation_angle; //rotation_angle can take values from 0 to 359
    UINT32 color_fill;     //color_fill should be in the same format as the //destination buffer's pixel format
    UINT32 dst_key_color;  //key_color parameters should be in the same pixel //format as the source and
                           destination buffers
    UINT32 src_key_color;
} CORVIEW_BLIT_DESC, *PCORVIEW_BLIT_DESC;
```

---

# PCI Device Module

The PCI Device Module permits an application to manage the configuration space of PCI devices. This module is not available in Sapera LT for 64-bit Windows.

## Functions

Function	Description
CorPciFindClassCode	<i>Find a PCI device with a specific class code</i>
CorPciFindDevice	<i>Find a PCI device with a specific vendor ID and device ID</i>
CorPciGetByte	<i>Read a byte from the configuration space of a PCI device</i>
CorPciGetData	<i>Read an array of data from the configuration space of a PCI device</i>
CorPciGetDword	<i>Read a double word from the configuration space of a PCI device</i>
CorPciGetInfo	<i>Get PCI BIOS information, such as the number of PCI buses, hardware mechanisms, and version</i>
CorPciGetVGADevice	<i>Get PCI device handle to a device that has VGA class code</i>
CorPciGetWord	<i>Read a word from the configuration space of a PCI device</i>
CorPciNewDevice	<i>Create a new PCI device handle given a PCI bus number, a PCI slot number, and a PCI function number</i>
CorPciPutByte	<i>Write a byte in the configuration space of a PCI device</i>
CorPciPutDword	<i>Write a double word in the configuration space of a PCI device</i>
CorPciPutWord	<i>Write a word in the configuration space of a PCI device</i>
CorPciRelease	<i>Release a PCI device</i>
CorPciSetBusNumber	<i>Force the number of PCI buses in the system</i>

---

## CorPciFindClassCode

Find a PCI device with a specific class code

<b>Prototype</b>	CORSTATUS <b>CorPciFindClassCode</b> ( CORSERVER <i>hServer</i> , UINT32 <i>classcode</i> , UINT16 <i>index</i> , CORPCIDEVICE * <i>hPciDevice</i> );
<b>Description</b>	Find a PCI device with a specific class code
<b>Input</b>	<i>hServer</i> Server handle <i>classCode</i> PCI device class code <i>index</i> PCI device index
<b>Output</b>	<i>hPciDevice</i> PCI device handle
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>hPciDevice</i> is NULL), CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorPciFindDevice, CorPciGetVGADevice and CorPciNewDevice

---

## CorPciFindDevice

Find a PCI device with a specific vendor ID and device ID

<b>Prototype</b>	CORSTATUS <b>CorPciFindDevice</b> ( CORSERVER <i>hServer</i> , UINT16 <i>vendorID</i> , UINT16 <i>deviceID</i> , UINT16 <i>index</i> , CORPCIDEVICE * <i>hPciDevice</i> );		
<b>Description</b>	Find a PCI device with a specific vendor ID and device ID		
<b>Input</b>	<i>hServer</i>	Server handle	
	<i>vendorID</i>	PCI device vendor ID	
	<i>deviceID</i>	PCI device device ID	
	<i>index</i>	PCI device index (usually 0)	
<b>Output</b>	<i>hPciDevice</i>	PCI device handle	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>hPciDevice</i> is NULL)		
<b>Note</b>	PCI device index must be used when more than one PCI device has the same vendor ID and device ID.		
<b>See Also</b>	CorPciFindClassCode, CorPciGetVGADevice and CorPciNewDevice		

---

## CorPciGetByte

Read a byte from the configuration space of a PCI device

<b>Prototype</b>	CORSTATUS <b>CorPciGetByte</b> ( CORPCIDEVICE <i>hPciDevice</i> , UINT16 <i>reg</i> , PUINT8 <i>data</i> );		
<b>Description</b>	Read a byte from the configuration space of a PCI device.		
<b>Input</b>	<i>hPciDevice</i>	PCI device handle	
	<i>reg</i>	Offset in configuration space	
<b>Output</b>	<i>data</i>	Byte read from configuration space	
<b>Return Value</b>	CORSTATUS_OK		
	CORSTATUS_ARG_NULL ( if <i>data</i> is NULL), CORSTATUS_INVALID_HANDLE		
<b>See Also</b>	CorPciGetData, CorPciGetDword and CorPciGetWord		

---

## CorPciGetData

Read an array of data from the configuration space of a PCI device

<b>Prototype</b>	CORSTATUS <b>CorPciGetData</b> ( CORPCIDEVICE <i>hPciDevice</i> , UINT16 <i>basereg</i> , UINT16 <i>nbytes</i> , void* <i>data</i> );		
<b>Description</b>	Read an array of data from the configuration space of a PCI device.		
<b>Input</b>	<i>hPciDevice</i>	PCI device handle	
	<i>basereg</i>	Offset in configuration space	
	<i>nbytes</i>	Number of bytes to read	
<b>Output</b>	<i>data</i>	Data read from configuration space	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_NULL ( if <i>data</i> is NULL), CORSTATUS_INVALID_HANDLE		
<b>See Also</b>	CorPciGetDword and CorPciGetWord		



---

## CorPciGetDword

Read a double word from the configuration space of a PCI device

<b>Prototype</b>	CORSTATUS <b>CorPciGetDword</b> ( CORPCIDEVICE <i>hPciDevice</i> , UINT16 <i>reg</i> , PUINT32 <i>data</i> );	
<b>Description</b>	Read a double word from the configuration space of a PCI device.	
<b>Input</b>	<i>hPciDevice</i>	PCI device handle
	<i>reg</i>	Offset in configuration space
<b>Output</b>	<i>data</i>	Double word read from configuration space
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>data</i> is NULL), CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorPciGetData and CorPciGetWord	

---

## CorPciGetInfo

Get PCI BIOS information

<b>Prototype</b>	CORSTATUS <b>CorPciGetInfo</b> ( CORSERVER <i>hServer</i> , PUINT16 <i>version</i> , PUINT8 <i>mechanism</i> , PUINT8 <i>nBuses</i> );	
<b>Description</b>	Get information such as the number of PCI buses, hardware mechanisms, and version.	
<b>Input</b>	<i>hServer</i>	Server handle
<b>Output</b>	<i>version</i>	BIOS version
	<i>mechanism</i>	Hardware mechanism
	<i>nBuses</i>	Number of PCI buses
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>version</i> , <i>mechanism</i> or <i>nBuses</i> is NULL)	
	CORSTATUS_INVALID_HANDLE	

---

## CorPciGetVGADevice

Gets PCI device handle to a device that has VGA class code

<b>Prototype</b>	CORSTATUS <b>CorPciGetVGADevice</b> ( CORSERVER <i>hServer</i> , UINT16 <i>index</i> , CORPCIDEVICE * <i>hPciDevice</i> );	
<b>Description</b>	Gets PCI device handle to a device that has a VGA class code	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>index</i>	PCI device index (usually 0)
<b>Output</b>	<i>hPciDevice</i>	PCI device handle
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>hPciDevice</i> is NULL) and CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorPciFindClassCode, CorPciFindDevice and CorPciNewDevice	

---

## CorPciGetWord

Read a word from the configuration space of a PCI device

<b>Prototype</b>	CORSTATUS <b>CorPciGetWord</b> ( CORPCIDEVICE <i>hPciDevice</i> , UINT16 <i>reg</i> , PUINT16 <i>data</i> );	
<b>Description</b>	Read a word from the configuration space of a PCI device.	
<b>Input</b>	<i>hPciDevice</i>	PCI device handle
	<i>reg</i>	Offset in configuration space
<b>Output</b>	<i>data</i>	Word read from configuration space
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>data</i> is NULL) and CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorPciGetData and CorPciGetDword	

---

## CorPciNewDevice

Create a PCI device handle given a PCI bus number, a PCI slot number and a PCI function number

<b>Prototype</b>	CORSTATUS <b>CorPciNewDevice</b> ( CORSERVER <i>hServer</i> , UINT8 <i>bus</i> , UINT8 <i>slot</i> , UINT8 <i>func</i> , CORPCIDEVICE * <i>hPciDevice</i> );	
<b>Description</b>	Create a PCI device handle given a PCI bus number, a PCI slot number and a PCI function number	
<b>Input</b>	<i>hServer</i>	Server handle
	<i>bus</i>	Bus number
	<i>slot</i>	Slot number
	<i>func</i>	Function number
<b>Output</b>	<i>hPciDevice</i>	PCI device handle
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_ARG_NULL ( if <i>hPciDevice</i> is NULL) and CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorPciFindClassCode, CorPciFindDevice and CorPciGetVGADevice	

---

## CorPciPutByte

Write a byte in the configuration space of a PCI device

<b>Prototype</b>	CORSTATUS <b>CorPciPutByte</b> ( CORPCIDEVICE <i>hPciDevice</i> , UINT16 <i>reg</i> , UINT8 <i>data</i> );	
<b>Description</b>	Write a byte in the configuration space of a PCI device.	
<b>Input</b>	<i>hPciDevice</i>	PCI device handle
	<i>reg</i>	Offset in configuration space
	<i>data</i>	Byte to write in configuration space
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK	
	CORSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorPciPutDword and CorPciPutWord	

---

## CorPciPutDword

Write a double word in the configuration space of a PCI device

<b>Prototype</b>	CORSTATUS <b>CorPciGetDword</b> ( CORPCIDEVICE <i>hPciDevice</i> , UINT16 <i>reg</i> , PUINT32 <i>data</i> );
<b>Description</b>	Write a double word in the configuration space of a PCI device.
<b>Input</b>	<i>hPciDevice</i> PCI device handle <i>reg</i> Offset in configuration space <i>data</i> Double word to write in configuration space
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorPciPutByte and CorPciPutWord

---

## CorPciPutWord

Write a word in the configuration space of a PCI device

<b>Prototype</b>	CORSTATUS <b>CorPciPutWord</b> ( CORPCIDEVICE <i>hPciDevice</i> , UINT16 <i>reg</i> , UINT16 <i>data</i> );
<b>Description</b>	Write a word in the configuration space of a PCI device.
<b>Input</b>	<i>hPciDevice</i> PCI device handle <i>reg</i> Offset in configuration space <i>data</i> Word to write in configuration space
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorPciPutByte and CorPciPutDword

---

## CorPciRelease

Release a PCI device

<b>Prototype</b>	CORSTATUS <b>CorPciRelease</b> ( CORPCIDEVICE <i>hPciDevice</i> );
<b>Description</b>	Release a PCI device
<b>Input</b>	<i>hPciDevice</i> PCI device handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>See Also</b>	CorPciNewDevice

---

## CorPciSetBusNumber

Force the number of PCI buses in the system

<b>Prototype</b>	CORSTATUS <b>CorPciSetBusNumber</b> ( CORSERVER <i>hServer</i> , PUINT8 <i>nbuses</i> );
<b>Description</b>	Force the number of PCI buses in the system
<b>Input</b>	<i>hServer</i> Server handle <i>nbuses</i> Number of PCI buses
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE
<b>Note</b>	The number of PCI buses can only be incremented.

# Error Messages

## Bit Description

All functions return a 32-bit CORSTATUS value, which is in the following format:

Bits	31-28	27-22	21-20	19-8	7-0
Description	Reserved	Module ID	Level	Info	Status ID

Bit Field	Description
Status ID	8-bits: a CORSTATUS_xxx constant. Where xxx references the status ID number.
Info	12-bits: a CORSTATUS_INFO_xxx constant or CORSTATUS_xxx constant. Refer to the status message descriptions for the Info field returned.
Level	2-bits: a CORSTATUS_LEVEL_xxx: constant.
Module ID	6-bits: a CORSTATUS_MODULE_xxx constant.

The CorManGetStatusTextEx function may be used to extract a description string for each of the bit fields. Refer to the “Error Management” section of the *Sapera LT User’s Manual* for more details.

## Status ID

ID	Message
0x00	CORSTATUS_OK
0x01	CORSTATUS_INVALID_HANDLE
0x0a	CORSTATUS_INCOMPATIBLE_ACQ
0x0b	CORSTATUS_INCOMPATIBLE_BUFFER
0x0d	CORSTATUS_INCOMPATIBLE_CAM
0x0e	CORSTATUS_INCOMPATIBLE_DISPLAY
0x0f	CORSTATUS_INCOMPATIBLE_GRAPHIC
0x10	CORSTATUS_INCOMPATIBLE_KERNEL
0x11	CORSTATUS_INCOMPATIBLE_LUT
0x12	CORSTATUS_INCOMPATIBLE_MANAGER
0x14	CORSTATUS_INCOMPATIBLE_VIC
0x15	CORSTATUS_INCOMPATIBLE_VIEW
0x16	CORSTATUS_INCOMPATIBLE_XFER
0x17	CORSTATUS_INCOMPATIBLE_STRING
0x1a	CORSTATUS_INCOMPATIBLE_FILE
0x1b	CORSTATUS_INCOMPATIBLE_FEATURE
0x1c	CORSTATUS_INCOMPATIBLE_ACQDEVICE
0x1e	CORSTATUS_CAP_INVALID
0x1f	CORSTATUS_CAP_NOT_AVAILABLE
0x20	CORSTATUS_FEATURE_INVALID
0x21	CORSTATUS_FEATURE_NOT_ACCESSIBLE
0x22	CORSTATUS_FEATURE_LOCKED

0x23	CORSTATUS_FEATURE_READ_ONLY
0x24	CORSTATUS_FEATURE_WRITE_ONLY
0x25	CORSTATUS_FEATURE_INVALID_VALUE
0x28	CORSTATUS_PRM_INVALID
0x29	CORSTATUS_PRM_NOT_AVAILABLE
0x2a	CORSTATUS_PRM_OUT_OF_RANGE
0x2b	CORSTATUS_PRM_INVALID_VALUE
0x2c	CORSTATUS_PRM_READ_ONLY
0x2d	CORSTATUS_PRM_MUTUALLY_EXCLUSIVE
0x32	CORSTATUS_ARG_INVALID
0x33	CORSTATUS_ARG_OUT_OF_RANGE
0x34	CORSTATUS_ARG_INCOMPATIBLE
0x35	CORSTATUS_ARG_INVALID_VALUE
0x36	CORSTATUS_ARG_NULL
0x39	CORSTATUS_FILE_OPTIONS_ERROR
0x3a	CORSTATUS_FILE_OPEN_MODE_INVALID
0x3b	CORSTATUS_FILE_SEEK_ERROR
0x3c	CORSTATUS_FILE_CREATE_ERROR
0x3d	CORSTATUS_FILE_OPEN_ERROR
0x3e	CORSTATUS_FILE_READ_ERROR
0x3f	CORSTATUS_FILE_WRITE_ERROR
0x40	CORSTATUS_FILE_CLOSE_ERROR
0x41	CORSTATUS_FILE_FORMAT_UNKNOWN
0x42	CORSTATUS_FILE_FIELD_VALUE_NOT_SUPPORTED
0x43	CORSTATUS_FILE_GET_FIELD_ERROR
0x44	CORSTATUS_FILE_READ_ONLY
0x45	CORSTATUS_FILE_WRITE_ONLY
0x46	CORSTATUS_NOT_IMPLEMENTED
0x47	CORSTATUS_NO_MEMORY
0x48	CORSTATUS_CLIPPING_OCCURED
0x49	CORSTATUS_HARDWARE_ERROR
0x4a	CORSTATUS_SERVICE_NOT_AVAILABLE
0x4b	CORSTATUS_NOT_ACCESSIBLE
0x4c	CORSTATUS_NOT_AVAILABLE
0x4d	CORSTATUS_ROUTING_NOT_IMPLEMENTED
0x4e	CORSTATUS_ROUTING_NOT_AVAILABLE
0x4f	CORSTATUS_ROUTING_IN_USE
0x50	CORSTATUS_INCOMPATIBLE_SIZE
0x51	CORSTATUS_INCOMPATIBLE_FORMAT
0x53	CORSTATUS_INCOMPATIBLE_LOCATION
0x54	CORSTATUS_RESOURCE_IN_USE
0x55	CORSTATUS_RESOURCE_LINKED
0x56	CORSTATUS_SOFTWARE_ERROR
0x57	CORSTATUS_PARAMETERS_LOCKED
0x58	CORSTATUS_XFER_NOT_CONNECTED
0x59	CORSTATUS_XFER_EMPTY_LIST
0x5a	CORSTATUS_XFER_CANT_CYCLE

0x5b	CORSTATUS_ROUTING_NOT_SPECIFIED
0x5d	CORSTATUS_TRANSFER_IN_PROGRESS
0x5f	CORSTATUS_SERVER_NOT_FOUND
0x60	CORSTATUS_CANNOT_SIGNAL_EVENT
0x61	CORSTATUS_NO_MESSAGE
0x62	CORSTATUS_TIMEOUT
0x63	CORSTATUS_INVALID_ALIGNMENT
0x64	CORSTATUS_DDRAW_256_COLORS
0x65	CORSTATUS_PCI_IO_ERROR
0x67	CORSTATUS_EVENT_CREATE_ERROR
0x68	CORSTATUS_BOARD_NOT_READY
0x69	CORSTATUS_XFER_MAX_SIZE
0x6b	CORSTATUS_RESOURCE_LOCKED
0x6c	CORSTATUS_NO_MESSAGING_MEMORY
0x6d	CORSTATUS_DDRAW_NOT_AVAILABLE
0x6e	CORSTATUS_DDRAW_ERROR
0x6f	CORSTATUS_RESOURCE_NOT_LOCKED
0x70	CORSTATUS_DISK_ON_CHIP_ERROR
0x73	CORSTATUS_INSUFFICIENT_BANDWIDTH
0x74	CORSTATUS_FILE_TELL_ERROR
0x75	CORSTATUS_MAX_PROCESS_EXCEEDED
0x76	CORSTATUS_XFER_COUNT_MULT_SRC_FRAME_COUNT
0x77	CORSTATUS_ACQ_CONNECTED_TO_XFER
0x78	CORSTATUS_INSUFFICIENT_BOARD_MEMORY
0x79	CORSTATUS_INSUFFICIENT_RESOURCES
0x7a	CORSTATUS_MISSING_RESOURCE
0x7b	CORSTATUS_NO_DEVICE_FOUND
0x7c	CORSTATUS_RESOURCE_NOT_CONNECTED
0x7d	CORSTATUS_SERVER_DATABASE_FULL
0x7f	CORSTATUS_DEVICE_NOT_CONNECTED
0x80	CORSTATUS_RESOURCE_ACCESS
0x81	CORSTATUS_DEVICE_NOT_RESPONDING
0x82	CORSTATUS_DATA_INVALID
0x83	CORSTATUS_RESOURCE_READ
0x84	CORSTATUS_RESOURCE_WRITE
0x85	CORSTATUS_CONNECTION_DROPPED
0x86	CORSTATUS_EVALUATION_PERIOD_EXPIRED
0x87	CORSTATUS_EXTERNAL_POWER_NOT_PRESENT
0x88	CORSTATUS_CAMERA_POWER_ERROR
0x89	CORSTATUS_REBOOT_REQUIRED

---

### **CORSTATUS\_ACQ\_CONNECTED\_TO\_XFER**

<b>Definition</b>	The resource cannot be modified while the acquisition is connected to a transfer module.
<b>Info</b>	The parameter number.
<b>Note</b>	None

---

**CORSTATUS\_ARG\_INCOMPATIBLE**

<b>Definition</b>	An incompatible argument was passed to a function.
<b>Info</b>	The argument number.
<b>Note</b>	Arguments are numbered starting at 1.

---

**CORSTATUS\_ARG\_INVALID**

<b>Definition</b>	An invalid argument was passed to a function.
<b>Info</b>	The argument number.
<b>Note</b>	Arguments are numbered starting at 1.

---

**CORSTATUS\_ARG\_INVALID\_VALUE**

<b>Definition</b>	An argument with an invalid value was passed to a function.
<b>Info</b>	The argument number.
<b>Note</b>	Arguments are numbered starting at 1.

---

**CORSTATUS\_ARG\_NULL**

<b>Definition</b>	A null argument was passed to a function.
<b>Info</b>	The argument number.
<b>Note</b>	Arguments are numbered starting at 1.

---

**CORSTATUS\_ARG\_OUT\_OF\_RANGE**

<b>Definition</b>	An out-of-range argument was passed to a function.
<b>Info</b>	The argument number.
<b>Note</b>	Arguments are numbered starting at 1.

---

**CORSTATUS\_BOARD\_NOT\_READY**

<b>Definition</b>	Sapera has been unable to bind to the board device driver.
<b>Info</b>	None

---

**CORSTATUS\_CAMERA\_POWER\_ERROR**

<b>Definition</b>	External power is connected, but a hardware error (for example, short-circuit) occurred when applied to the camera
<b>Info</b>	None

---

**CORSTATUS\_CANNOT\_SIGNAL\_EVENT**

<b>Definition</b>	While trying to send a message, the Sapera message engine got an error when signaling an event object.
<b>Info</b>	None

---

**CORSTATUS\_CAP\_INVALID**

<b>Definition</b>	An invalid capability was requested.
<b>Info</b>	The capability number.

---

**CORSTATUS\_CAP\_NOT\_AVAILABLE**

**Definition** An unavailable capability was requested.  
**Info** The capability number.

---

**CORSTATUS\_CLIPPING\_OCCURED**

**Definition** A rectangle clipping occurred while processing a buffer.  
**Info** None

---

**CORSTATUS\_CONNECTION\_DROPPED**

**Definition** Logical connection with a device was lost. This error is generated if a device is disconnected and/or no longer responds.  
**Info** None

---

**CORSTATUS\_DATA\_INVALID**

**Definition** Expected data is invalid. Possible causes can be checksum or protocol errors.  
**Info** None

---

**CORSTATUS\_DEVICE\_NOT\_CONNECTED**

**Definition** The device is not connected.  
**Info** None

---

**CORSTATUS\_DEVICE\_NOT\_RESPONDING**

**Definition** The device is not responding.  
**Info** None

---

**CORSTATUS\_DISK\_ON\_CHIP\_ERROR**

**Definition** There was an error accessing the Disk-On-Chip located on a Sapera board.  
**Info** The Disk-On-Chip error code

---

**CORSTATUS\_DDRAW\_256\_COLORS**

**Definition** The VGA graphics mode must be in 256 colors or more.  
**Info** None

---

**CORSTATUS\_DDRAW\_ERROR**

**Definition** DirectDraw (Windows XP 32-bit only) cannot provide the requested service.  
**Info** None

---

**CORSTATUS\_DDRAW\_NOT\_AVAILABLE**

**Definition** DirectDraw (Windows XP 32-bit only) services are not available.  
**Info** None



---

**CORSTATUS\_EVALUATION\_PERIOD\_EXPIRED**

<b>Definition</b>	No product key has been specified for the currently installed version of Sapera LT, and the evaluation period has expired.
<b>Info</b>	None

---

**CORSTATUS\_EVENT\_CREATE\_ERROR**

<b>Definition</b>	While trying to send a message, the Sapera message engine got an error when creating an event object.
<b>Info</b>	None

---

**CORSTATUS\_EXTERNAL\_POWER\_NOT\_PRESENT**

<b>Definition</b>	No external power is connected to the board
<b>Info</b>	None

---

**CORSTATUS\_FEATURE\_INVALID**

<b>Definition</b>	An invalid feature was passed to a function.
<b>Info</b>	The argument number for the feature.
<b>Note</b>	Arguments are numbered starting at 1.

---

**CORSTATUS\_FEATURE\_INVALID\_VALUE**

<b>Definition</b>	A feature with an invalid value was passed to a function.
<b>Info</b>	The feature index.

---

**CORSTATUS\_FEATURE\_LOCKED**

<b>Definition</b>	A feature is locked (cannot be written).
<b>Info</b>	The feature index.

---

**CORSTATUS\_FEATURE\_NOT\_ACCESSIBLE**

<b>Definition</b>	An error occurred while accessing any intermediate underlying implementation for a feature.
<b>Info</b>	The feature index.

---

**CORSTATUS\_FEATURE\_READ\_ONLY**

<b>Definition</b>	A feature could not be written because it is read only.
<b>Info</b>	The feature index.

---

**CORSTATUS\_FEATURE\_WRITE\_ONLY**

<b>Definition</b>	A feature could not be read because it is write only.
<b>Info</b>	The feature index.

---

**CORSTATUS\_FILE\_CLOSE\_ERROR**

<b>Definition</b>	Error closing file.
<b>Info</b>	None

---

**CORSTATUS\_FILE\_CREATE\_ERROR**

**Definition** Error creating file.  
**Info** None

---

**CORSTATUS\_FILE\_FIELD\_VALUE\_NOT\_SUPPORTED**

**Definition** One or more header field values from the specified image file are not supported.  
**Info** None

---

**CORSTATUS\_FILE\_FORMAT\_UNKNOWN**

**Definition** File format is unknown.  
**Info** None

---

**CORSTATUS\_FILE\_GET\_FIELD\_ERROR**

**Definition** Failed to get header field information from the specified image.  
**Info** None

---

**CORSTATUS\_FILE\_OPEN\_ERROR**

**Definition** Error opening file.  
**Info** None

---

**CORSTATUS\_FILE\_OPEN\_MODE\_INVALID**

**Definition** File open mode is invalid.  
**Info** None

---

**CORSTATUS\_FILE\_OPTIONS\_ERROR**

**Definition** File options is invalid.  
**Info** None

---

**CORSTATUS\_FILE\_READ\_ERROR**

**Definition** Error reading file.  
**Info** None

---

**CORSTATUS\_FILE\_READ\_ONLY**

**Definition** File can only be read.  
**Info** None

---

**CORSTATUS\_FILE\_SEEK\_ERROR**

**Definition** A seek error occurred while accessing the file.  
**Info** None

---

**CORSTATUS\_FILE\_TELL\_ERROR**

<b>Definition</b>	A seek error occurred while trying to set the current position in the specified file.
<b>Info</b>	None

---

**CORSTATUS\_FILE\_WRITE\_ERROR**

<b>Definition</b>	Error writing file.
<b>Info</b>	None

---

**CORSTATUS\_FILE\_WRITE\_ONLY**

<b>Definition</b>	File can only be written.
<b>Info</b>	None

---

**CORSTATUS\_HARDWARE\_ERROR**

<b>Definition</b>	General hardware error. This error is usually fatal.
<b>Info</b>	Hardware specific information about the error.

---

**CORSTATUS\_INCOMPATIBLE\_ACQ**

<b>Definition</b>	An acquisition parameter is incompatible.
<b>Info</b>	The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_ACQDEVICE**

<b>Definition</b>	An acquisition device parameter is incompatible.
<b>Info</b>	The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_BUFFER**

<b>Definition</b>	A buffer is incompatible with another API object, prohibiting the two from functioning together.
<b>Info</b>	The reason for the incompatibility.

---

**CORSTATUS\_INCOMPATIBLE\_CAM**

<b>Definition</b>	A camera parameter is incompatible.
<b>Info</b>	The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_DISPLAY**

<b>Definition</b>	A display parameter is incompatible.
<b>Info</b>	The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_FEATURE**

<b>Definition</b>	A feature parameter is incompatible.
<b>Info</b>	The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_FILE**

**Definition** A file parameter is incompatible.  
**Info** The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_FORMAT**

**Definition** The formats of two or more resources are not compatible, prohibiting them from functioning together.  
**Info** None

---

**CORSTATUS\_INCOMPATIBLE\_GRAPHIC**

**Definition** A graphic parameter is incompatible.  
**Info** The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_KERNEL**

**Definition** A kernel parameter is incompatible.  
**Info** The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_LOCATION**

**Definition** The location of two resources are incompatible.  
**Info** None

---

**CORSTATUS\_INCOMPATIBLE\_LUT**

**Definition** An LUT parameter is incompatible.  
**Info** The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_MANAGER**

**Definition** A manager parameter is incompatible.  
**Info** The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_SIZE**

**Definition** The size of two or more resources are not compatible, prohibiting them from functioning together.  
**Info** None

---

**CORSTATUS\_INCOMPATIBLE\_STRING**

**Definition** An error was detected while parsing the C expression in the string.  
**Info** None

---

**CORSTATUS\_INCOMPATIBLE\_VIC**

**Definition** A VIC parameter is incompatible.  
**Info** The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_VIEW**

**Definition** A view parameter is incompatible.  
**Info** The parameter number.

---

**CORSTATUS\_INCOMPATIBLE\_XFER**

**Definition** A transfer parameter is incompatible.  
**Info** The parameter number.

---

**CORSTATUS\_INSUFFICIENT\_BANDWIDTH**

**Definition** The requested data transfer bandwidth exceeds the hardware capabilities.  
**Info** None

---

**CORSTATUS\_INSUFFICIENT\_BOARD\_MEMORY**

**Definition** There is insufficient memory on the acquisition board.  
**Info** None

---

**CORSTATUS\_INSUFFICIENT\_RESOURCES**

**Definition** A requested or required resource cannot be obtained because there are none available.  
**Info** None

---

**CORSTATUS\_INVALID\_ALIGNMENT**

**Definition** Memory block was not aligned on a 32-bit boundary.  
**Info** None

---

**CORSTATUS\_INVALID\_HANDLE**

**Definition** Invalid handle.  
**Info** CORSTATUS\_MODULE\_xxx constant.

---

**CORSTATUS\_MAX\_PROCESS\_EXCEEDED**

**Definition** The maximum number of processes that can be bound to a driver has been exceeded. A maximum of 16 processes is currently supported.  
**Info** None

---

**CORSTATUS\_MISSING\_RESOURCE**

**Definition** A required supporting DLL resource is missing  
**Info** None

---

**CORSTATUS\_NO\_DEVICE\_FOUND**

**Definition** No Sapera compatible device was found  
**Info** None

---

---

**CORSTATUS\_NO\_MEMORY**

**Definition**      There is not enough memory for the required allocation.  
**Info**              None

---

**CORSTATUS\_NO\_MESSAGE**

**Definition**      Even if the Sopera messaging engine has been signaled, no message is available.  
**Info**              None

---

**CORSTATUS\_NO\_MESSAGING\_MEMORY**

**Definition**      There is not enough messaging memory for the required allocation.  
**Info**              None.  
**Note**              Use the Sopera Configuration utility to increase the amount of messaging memory.

---

**CORSTATUS\_NOT\_ACCESSIBLE**

**Definition**      An error occurred while accessing any intermediate underlying implementation in the process of executing an API function.  
**Info**              None

---

**CORSTATUS\_NOT\_AVAILABLE**

**Definition**      The resource is not available.  
**Info**              None

---

**CORSTATUS\_NOT\_IMPLEMENTED**

**Definition**      The function is not implemented.  
**Info**              None

---

**CORSTATUS\_OK**

**Definition**      No error.  
**Info**              None

---

**CORSTATUS\_PARAMETERS\_LOCKED**

**Definition**      Module's parameters are locked (cannot be written).  
**Info**              None

---

**CORSTATUS\_PCI\_IO\_ERROR**

**Definition**      Reading or writing to the device's PCI configuration space failed.  
**Info**              None

---

**CORSTATUS\_PRM\_INVALID**

**Definition**      An invalid, nonexistent parameter was specified.  
**Info**              None

---

**CORSTATUS\_PRM\_INVALID\_VALUE**

**Definition** A parameter could not be set because the value is invalid.  
**Info** The parameter number.

---

**CORSTATUS\_PRM\_MUTUALLY\_EXCLUSIVE**

**Definition** A parameter could not be set because it is mutually exclusive with another parameter.  
**Info** The parameter number.

---

**CORSTATUS\_PRM\_NOT\_AVAILABLE**

**Definition** A parameter could not be read or written because it is unavailable, usually because the capability governing it is not available.  
**Info** The parameter number.

---

**CORSTATUS\_PRM\_OUT\_OF\_RANGE**

**Definition** A parameter could not be set because the value is out of range.  
**Info** The parameter number.

---

**CORSTATUS\_PRM\_READ\_ONLY**

**Definition** A parameter could not be written because it is read only.  
**Info** The parameter number.

---

**CORSTATUS\_REBOOT\_REQUIRED**

**Definition** A reboot of the computer is required. This can happen after resetting a board.  
**Info** None

---

**CORSTATUS\_RESOURCE\_ACCESS**

**Definition** The resource is not accessible.  
**Info** None

---

**CORSTATUS\_RESOURCE\_IN\_USE**

**Definition** A requested or required resource is already being used by the user or the API.  
**Info** None

---

**CORSTATUS\_RESOURCE\_LINKED**

**Definition** The resource is linked to another resource and cannot be freed.  
**Info** None

---

**CORSTATUS\_RESOURCE\_NOT\_CONNECTED**

**Definition** The resource is not connected  
**Info** None

---

**CORSTATUS\_RESOURCE\_READ**

<b>Definition</b>	Cannot read from the resource. Resource could be a file, socket, dedicated hardware, or other device. This error is usually fatal. Use the Sapera LogViewer utility to see a more descriptive error message.
<b>Info</b>	None

---

**CORSTATUS\_RESOURCE\_WRITE**

<b>Definition</b>	Cannot read from the resource. Resource could be file, socket, dedicated hardware or other device. This error is usually fatal. Use the Sapera LogViewer utility to see a more descriptive error message.
<b>Info</b>	None

---

**CORSTATUS\_RESOURCE\_LOCKED**

<b>Definition</b>	The resource is locked and cannot be modified. Array module functions return this status ID when the parameter LOCKED is set.
<b>Info</b>	None

---

**CORSTATUS\_RESOURCE\_NOT\_LOCKED**

<b>Definition</b>	The resource needs to be locked before use.
<b>Info</b>	None

---

**CORSTATUS\_ROUTING\_IN\_USE**

<b>Definition</b>	The transfer routing (path) is already used.
<b>Info</b>	None

---

**CORSTATUS\_ROUTING\_NOT\_AVAILABLE**

<b>Definition</b>	The transfer routing (path) is not available.
<b>Info</b>	None

---

**CORSTATUS\_ROUTING\_NOT\_IMPLEMENTED**

<b>Definition</b>	The transfer routing (path) is not implemented.
<b>Info</b>	None

---

**CORSTATUS\_ROUTING\_NOT\_SPECIFIED**

<b>Definition</b>	The transfer routing cannot be established because there is no source/destination pair.
<b>Info</b>	None

---

**CORSTATUS\_SERVER\_DATABASE\_FULL**

<b>Definition</b>	The internal database containing the list of servers is full.
<b>Info</b>	None



---

**CORSTATUS\_SERVER\_NOT\_FOUND**

<b>Definition</b>	The requested server was not found. The server name may not be present in the Sapera Server list. Check in the Sapera configuration program to verify the presence of the server. If present, it may not be responding.
<b>Info</b>	None

---

**CORSTATUS\_SERVICE\_NOT\_AVAILABLE**

<b>Definition</b>	Windows service is not running.
<b>Info</b>	None

---

**CORSTATUS\_SOFTWARE\_ERROR**

<b>Definition</b>	General software error.
<b>Info</b>	Software specific information about the error.

---

**CORSTATUS\_TIMEOUT**

<b>Definition</b>	There was no response from a module.
<b>Info</b>	CORSTATUS_MODULE_xxx constant.

---

**CORSTATUS\_TRANSFER\_IN\_PROGRESS**

<b>Definition</b>	Operation could not be performed because a transfer is in progress.
<b>Info</b>	None

---

**CORSTATUS\_XFER\_CANT\_CYCLE**

<b>Definition</b>	No transfer cycle is possible for the current destination resource.
<b>Info</b>	None

---

**CORSTATUS\_XFER\_COUNT\_MULT\_SRC\_FRAME\_COUNT**

<b>Definition</b>	The number of frames to acquire (count argument of function CorXferStart) is not a multiple of the number of frames output by the source. For example, if the source outputs 3 frames per external trigger, the number of frames to acquire needs to be a multiple of 3.
<b>Info</b>	None

---

**CORSTATUS\_XFER\_EMPTY\_LIST**

<b>Definition</b>	There is no data to transfer.
<b>Info</b>	None

---

**CORSTATUS\_XFER\_MAX\_SIZE**

<b>Definition</b>	The size of the requested transfer is greater than the maximum. Use the capability CORXFER_CAP_MAX_XFER_SIZE to get this maximum.
<b>Info</b>	None

---

**CORSTATUS\_XFER\_NOT\_CONNECTED**

<b>Definition</b>	The transfer is not connected.
<b>Info</b>	None

---

## Level

ID	Value	Definition
0x00	CORSTATUS_LEVEL_ERR	Error
0x01	CORSTATUS_LEVEL_FAT	Fatal error
0x02	CORSTATUS_LEVEL_WRN	Warning
0x03	CORSTATUS_LEVEL_INF	Information

---

## Module ID

ID	Value	Module name
0x01	CORSTATUS_MODULE_ACQ	Acquisition module
0x02	CORSTATUS_MODULE_BUFFER	Buffer module
0x04	CORSTATUS_MODULE_CAM	Camera module
0x05	CORSTATUS_MODULE_DISPLAY	Display module
0x07	CORSTATUS_MODULE_GRAPHIC	Graphic module
0x08	CORSTATUS_MODULE_HOST	Host module
0x0a	CORSTATUS_MODULE_LOG	Log module
0x0b	CORSTATUS_MODULE_LUT	LUT module
0x0c	CORSTATUS_MODULE_MANAGER	API control module
0x0d	CORSTATUS_MODULE_MEMORY	Memory management module
0x0e	CORSTATUS_MODULE_PCI	PCI module
0x11	CORSTATUS_MODULE_VIC	VIC module
0x12	CORSTATUS_MODULE_VIEW	View module
0x13	CORSTATUS_MODULE_XFER	Transfer module
0x14	CORSTATUS_MODULE_VDI	Video display interface module
0x15	CORSTATUS_MODULE_SERVER	Server module
0x17	CORSTATUS_MODULE_FILE	File module
0x19	CORSTATUS_MODULE_GIO	General IO module
0x20	CORSTATUS_MODULE_EVENTINFO	Event information module
0x21	CORSTATUS_MODULE_FEATURE	Feature module
0x22	CORSTATUS_MODULE_ACQDEVICE	Acquisition device module

# Macro Definitions

---

## Sapera Macros

This section describes all the macros used in Sapera. The macros should always be used within user applications to ensure code portability.

---

### **VALIDATE\_HANDLE\_ACQ( CORACQ hAcq)**

**Definition**      Validates acquisition module handle  
**Returns**        CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

### **VALIDATE\_HANDLE\_ACQDEVICE( CORACQDEVICE hAcqDevice)**

**Definition**      Validates acquisition device module handle  
**Returns**        CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

### **VALIDATE\_HANDLE\_BUFFER( CORBUFFER hBuffer)**

**Definition**      Validates buffer resource handle  
**Returns**        CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

### **VALIDATE\_HANDLE\_CAM( CORCAM hCam)**

**Definition**      Validates camera resource handle  
**Returns**        CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

### **VALIDATE\_HANDLE\_DISPLAY( CORDISPLAY hDisplay)**

**Definition**      Validates display device handle  
**Returns**        CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

### **VALIDATE\_HANDLE\_EVENTINFO( COREVENTINFO hEventInfo)**

**Definition**      Validates event information resource handle  
**Returns**        CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

### **VALIDATE\_HANDLE\_FEATURE( CORFEATURE hFeature)**

**Definition**      Validates feature resource handle  
**Returns**        CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

### **VALIDATE\_HANDLE\_FILE( CORFILE hFile)**

**Definition**      Validates file resource handle  
**Returns**        CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

**VALIDATE\_HANDLE\_GIO( CORGIO hGIO)**

**Definition**      Validates global input/output device handle  
**Returns**          CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

**VALIDATE\_HANDLE\_GRAPHIC( CORGRAPHIC hGraphic)**

**Definition**      Validates graphic device handle  
**Returns**          CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

**VALIDATE\_HANDLE\_LUT( CORLUT hLut)**

**Definition**      Validates lookup table resource handle  
**Returns**          CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

**VALIDATE\_HANDLE\_PCI\_DEVICE( CORPCIDEVICE hPciDevice)**

**Definition**      Validates PCI device handle  
**Returns**          CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

**VALIDATE\_HANDLE\_VIC( CORVIC hVIC)**

**Definition**      Validates video input conditioning resource handle  
**Returns**          CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

**VALIDATE\_HANDLE\_VIEW( CORVIEW hView)**

**Definition**      Validates view resource handle  
**Returns**          CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

**VALIDATE\_HANDLE\_XFER( CORXFER hXfer)**

**Definition**      Validates transfer device handle  
**Returns**          CORSTATUS\_OK if the handle is valid, CORSTATUS\_INVALID\_HANDLE otherwise

---

**CORHANDLE\_NULL**

**Definition**      Should be used to initialize non-allocated handles.

---

# Data Definitions

## Data Types

This section describes all the data types used in Sopera. They should always be used in your applications to ensure code portability.

### BOOLEAN

8-bits unsigned integer

### CORDATA

```
typedef union
{
    INT32 mono;
    struct {
        INT32 red;
        INT32 green;
        INT32 blue;
    } rgb;
    struct {
        INT32 h;
        INT32 s;
        INT32 i;
    } hsi;
    struct {
        INT32 h;
        INT32 s;
        INT32 v;
    } hsv;
    struct {
        INT32 y;
        INT32 u;
        INT32 v;
    } yuv;
    struct {
        INT32 x;
        INT32 y;
    } point;
    FLOAT flt;
    struct {
        UINT16 alpha;
        UINT16 red;
        UINT16 green;
        UINT16 blue;
    } rgba;
    struct {
        FLOAT real;
        FLOAT imag;
    } cplx;
    struct {
        FLOAT x;
        FLOAT y;
    } fpoint;
    struct {
        FLOAT red;
        FLOAT green;
        FLOAT blue;
    } frgb;
} CORDATA, *PCORDATA;
```

---

## CORPOINT

```
typedef struct {  
    INT32 x;  
    INT32 y;  
} CRL_POINT, *PCRL_POINT;
```

---

## CORSTATUS

32-bits unsigned integer

---

## INT8

8-bits signed integer

---

## INT16

16-bits signed integer

---

## INT32

32-bits signed integer

---

## PBOOLEAN

Pointer to an 8-bit unsigned integer

---

## PCORCALLBACK

```
typedef CORSTATUS (CCONV *PCORCALLBACK) (void *context, UINT32 eventType, UINT32 eventCount);
```

---

## PCOREVENTINFOCALLBACK

```
typedef CORSTATUS (CCONV *PCOREVENTINFOCALLBACK) (void *context, COREVENTINFO hEventInfo);
```

---

## PCORMANCALLBACK

```
typedef CORSTATUS (CCONV *PCORMANCALLBACK) (UINT32 cmd, void *inData, UINT32 inDataSize, void *outData, UINT32 outDataSize);
```

---

## PINT8

Pointer to an 8-bits signed integer

---

## PINT16

Pointer to a 16-bits signed integer

---

## PINT32

Pointer to a 32-bits signed integer

---

## PUINT8

Pointer to an 8-bits unsigned integer

---

## PUINT16

Pointer to a 16-bits unsigned integer

---

## PUINT32

Pointer to a 32-bits unsigned integer

---

## UINT8

8-bits unsigned integer

---

## UINT16

16-bits unsigned integer

---

## UINT32

32-bits unsigned integer

---

# Data Formats

This section describes all the data formats supported in Sapera. These formats are used by the Buffer, Kernel, File, and Acquisition modules. Each of these modules refers to these formats with different parameter names, although they are completely compatible. For example, the following assignment is acceptable.

```
UINT32 format;
CorBufferGetPrm(hBuffer, CORBUFFER_Prm_FORMAT, &format); // Read buffer format
CorAcqSetPrm(hAcq, CORACQ_Prm_OUTPUT_FORMAT, format); // Force it to Acq
```

## Data Formats:

<a href="#">BICOLOR88</a>	<a href="#">INT32</a>	<a href="#">RGB8888</a>	<a href="#">UINT16</a>
<a href="#">BICOLOR1616</a>	<a href="#">MONO1</a>	<a href="#">RGB101010</a>	<a href="#">UINT32</a>
<a href="#">COMPLEX</a>	<a href="#">MONO8</a>	<a href="#">RGB161616</a>	<a href="#">UYVY</a>
<a href="#">FLOAT</a>	<a href="#">MONO16</a>	<a href="#">RGB161616_MONO16</a>	<a href="#">YUV</a>
<a href="#">FPOINT</a>	<a href="#">MONO32</a>	<a href="#">RGB16161616</a>	<a href="#">YUY2</a>
<a href="#">HSI</a>	<a href="#">POINT</a>	<a href="#">RGBP8</a>	<a href="#">YVYU</a>
<a href="#">HSIP8</a>	<a href="#">RGB5551</a>	<a href="#">RGBP16</a>	<a href="#">YUYV</a>
<a href="#">HSV</a>	<a href="#">RGB565</a>	<a href="#">RGRB888</a>	<a href="#">Y411</a>
<a href="#">INT8</a>	<a href="#">RGB888</a>	<a href="#">UINT1</a>	
<a href="#">INT16</a>	<a href="#">RGB888_MONO8</a>	<a href="#">UINT8</a>	

## AIA Pixel Format Naming Convention (PFNC) Equivalents

PFNC Format	Sapera Data Format	Buffer Byte Alignment (bit order is little endian)																																
RGBG8 BGRG8	<a href="#">BICOLOR88</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>R<sub>1</sub></td><td>G<sub>1</sub></td><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>2</sub></td><td>G<sub>3</sub></td><td>B<sub>2</sub></td><td>G<sub>4</sub></td></tr></table> <p>Or</p> <table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>G<sub>2</sub></td><td>B<sub>2</sub></td><td>G<sub>3</sub></td><td>R<sub>2</sub></td><td>G<sub>4</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	G <sub>1</sub>	R <sub>2</sub>	G <sub>3</sub>	B <sub>2</sub>	G <sub>4</sub>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	G <sub>2</sub>	B <sub>2</sub>	G <sub>3</sub>	R <sub>2</sub>	G <sub>4</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7																											
R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	G <sub>1</sub>	R <sub>2</sub>	G <sub>3</sub>	B <sub>2</sub>	G <sub>4</sub>																											
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7																											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	G <sub>2</sub>	B <sub>2</sub>	G <sub>3</sub>	R <sub>2</sub>	G <sub>4</sub>																											
RGBG16 BGRG16	<a href="#">BICOLOR1616</a>	<table><tr><td>Byte 0-1</td><td>Byte 2-3</td><td>Byte 4-5</td><td>Byte 6-7</td></tr><tr><td>R<sub>1</sub></td><td>G<sub>1</sub></td><td>B<sub>1</sub></td><td>G<sub>2</sub></td></tr></table> <p>Or</p> <table><tr><td>Byte 0-1</td><td>Byte 2-3</td><td>Byte 4-5</td><td>Byte 6-7</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>G<sub>2</sub></td></tr></table>	Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	G <sub>2</sub>	Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	G <sub>2</sub>																
Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7																															
R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	G <sub>2</sub>																															
Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7																															
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	G <sub>2</sub>																															
ISHa8	<a href="#">HSI</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>I<sub>1</sub></td><td>S<sub>1</sub></td><td>H<sub>1</sub></td><td>A<sub>1</sub></td><td>I<sub>2</sub></td><td>S<sub>2</sub></td><td>H<sub>2</sub></td><td>A<sub>2</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	I <sub>1</sub>	S <sub>1</sub>	H <sub>1</sub>	A <sub>1</sub>	I <sub>2</sub>	S <sub>2</sub>	H <sub>2</sub>	A <sub>2</sub>																
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7																											
I <sub>1</sub>	S <sub>1</sub>	H <sub>1</sub>	A <sub>1</sub>	I <sub>2</sub>	S <sub>2</sub>	H <sub>2</sub>	A <sub>2</sub>																											
HSI8_Planar	<a href="#">HSIP8</a>	<table><tr><td>Page 0</td><td>Page 1</td><td>Page 2</td></tr><tr><td>H<sub>1</sub></td><td>S<sub>1</sub></td><td>I<sub>1</sub></td></tr></table>	Page 0	Page 1	Page 2	H <sub>1</sub>	S <sub>1</sub>	I <sub>1</sub>																										
Page 0	Page 1	Page 2																																
H <sub>1</sub>	S <sub>1</sub>	I <sub>1</sub>																																
VSHa8	<a href="#">HSV</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>V<sub>1</sub></td><td>S<sub>1</sub></td><td>H<sub>1</sub></td><td>A<sub>1</sub></td><td>V<sub>2</sub></td><td>S<sub>2</sub></td><td>H<sub>2</sub></td><td>A<sub>2</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	V <sub>1</sub>	S <sub>1</sub>	H <sub>1</sub>	A <sub>1</sub>	V <sub>2</sub>	S <sub>2</sub>	H <sub>2</sub>	A <sub>2</sub>																
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7																											
V <sub>1</sub>	S <sub>1</sub>	H <sub>1</sub>	A <sub>1</sub>	V <sub>2</sub>	S <sub>2</sub>	H <sub>2</sub>	A <sub>2</sub>																											
MONO1	<a href="#">MONO1</a>	<table><tr><td colspan="8">Byte 0</td><td colspan="8">Byte 1</td></tr><tr><td>Y<sub>8</sub></td><td>Y<sub>7</sub></td><td>Y<sub>6</sub></td><td>Y<sub>5</sub></td><td>Y<sub>4</sub></td><td>Y<sub>3</sub></td><td>Y<sub>2</sub></td><td>Y<sub>1</sub></td><td>Y<sub>16</sub></td><td>Y<sub>15</sub></td><td>Y<sub>14</sub></td><td>Y<sub>13</sub></td><td>Y<sub>12</sub></td><td>Y<sub>11</sub></td><td>Y<sub>10</sub></td><td>Y<sub>9</sub></td></tr></table>	Byte 0								Byte 1								Y <sub>8</sub>	Y <sub>7</sub>	Y <sub>6</sub>	Y <sub>5</sub>	Y <sub>4</sub>	Y <sub>3</sub>	Y <sub>2</sub>	Y <sub>1</sub>	Y <sub>16</sub>	Y <sub>15</sub>	Y <sub>14</sub>	Y <sub>13</sub>	Y <sub>12</sub>	Y <sub>11</sub>	Y <sub>10</sub>	Y <sub>9</sub>
Byte 0								Byte 1																										
Y <sub>8</sub>	Y <sub>7</sub>	Y <sub>6</sub>	Y <sub>5</sub>	Y <sub>4</sub>	Y <sub>3</sub>	Y <sub>2</sub>	Y <sub>1</sub>	Y <sub>16</sub>	Y <sub>15</sub>	Y <sub>14</sub>	Y <sub>13</sub>	Y <sub>12</sub>	Y <sub>11</sub>	Y <sub>10</sub>	Y <sub>9</sub>																			
MONO8	<a href="#">MONO8</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td></tr><tr><td>Y<sub>1</sub></td><td>Y<sub>2</sub></td><td>Y<sub>3</sub></td><td>Y<sub>4</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>																								
Byte 0	Byte 1	Byte 2	Byte 3																															
Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>																															
MONO16	<a href="#">MONO16</a>	<table><tr><td>Byte 0-1</td><td>Byte 2-3</td><td>Byte 4-5</td><td>Byte 6-7</td></tr><tr><td>Y<sub>1</sub></td><td>Y<sub>2</sub></td><td>Y<sub>3</sub></td><td>Y<sub>4</sub></td></tr></table>	Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>																								
Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7																															
Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>																															
MONO32	<a href="#">MONO32</a>	<table><tr><td>Byte 0-3</td><td>Byte 4-7</td><td>Byte 8-11</td><td>Byte 12-15</td></tr><tr><td>Y<sub>1</sub></td><td>Y<sub>2</sub></td><td>Y<sub>3</sub></td><td>Y<sub>4</sub></td></tr></table>	Byte 0-3	Byte 4-7	Byte 8-11	Byte 12-15	Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>																								
Byte 0-3	Byte 4-7	Byte 8-11	Byte 12-15																															
Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>																															

BayerGR8	<a href="#">MONO8</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td></tr><tr><td>Y<sub>1</sub></td><td>Y<sub>2</sub></td><td>Y<sub>3</sub></td><td>Y<sub>4</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>								
Byte 0	Byte 1	Byte 2	Byte 3															
Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>															
BayerRG8																		
BayerGB8																		
BayerBG8																		
BayerGR10	<a href="#">MONO16</a>	<table><tr><td>Byte 0-1</td><td>Byte 2-3</td><td>Byte 4-5</td><td>Byte 6-7</td></tr><tr><td>Y<sub>1</sub></td><td>Y<sub>2</sub></td><td>Y<sub>3</sub></td><td>Y<sub>4</sub></td></tr></table>	Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>								
Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7															
Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>															
BayerRG10																		
BayerGB10																		
BayerBG10																		
BGRa5551	<a href="#">RGB5551</a>	<table><tr><td>Bit 4:0</td><td>Bit 9:5</td><td>Bit 14:10</td><td>Bit 15</td><td>Bit 4:0</td><td>Bit 9:5</td><td>Bit 14:10</td><td>Bit 15</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>A<sub>1</sub></td><td>B<sub>2</sub></td><td>G<sub>2</sub></td><td>R<sub>2</sub></td><td>A<sub>2</sub></td></tr></table>	Bit 4:0	Bit 9:5	Bit 14:10	Bit 15	Bit 4:0	Bit 9:5	Bit 14:10	Bit 15	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	A <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	A <sub>2</sub>
Bit 4:0	Bit 9:5	Bit 14:10	Bit 15	Bit 4:0	Bit 9:5	Bit 14:10	Bit 15											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	A <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	A <sub>2</sub>											
BGR565	<a href="#">RGB565</a>	<table><tr><td>Bit 4:0</td><td>Bit 10:5</td><td>Bit 15:11</td><td>Bit 20:16</td><td>Bit 26:21</td><td>Bit 31:27</td><td>Bit 4:0</td><td>Bit 10:5</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>B<sub>2</sub></td><td>G<sub>2</sub></td><td>R<sub>2</sub></td><td>B<sub>3</sub></td><td>G<sub>3</sub></td></tr></table>	Bit 4:0	Bit 10:5	Bit 15:11	Bit 20:16	Bit 26:21	Bit 31:27	Bit 4:0	Bit 10:5	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	B <sub>3</sub>	G <sub>3</sub>
Bit 4:0	Bit 10:5	Bit 15:11	Bit 20:16	Bit 26:21	Bit 31:27	Bit 4:0	Bit 10:5											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	B <sub>3</sub>	G <sub>3</sub>											
BGR8	<a href="#">RGB888</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>B<sub>2</sub></td><td>G<sub>2</sub></td><td>R<sub>2</sub></td><td>B<sub>3</sub></td><td>G<sub>3</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	B <sub>3</sub>	G <sub>3</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	B <sub>3</sub>	G <sub>3</sub>											
BGRY8	<a href="#">RGB888_MONO8</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>Y<sub>1</sub></td><td>B<sub>2</sub></td><td>G<sub>2</sub></td><td>R<sub>2</sub></td><td>Y<sub>2</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	Y <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	Y <sub>2</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	Y <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	Y <sub>2</sub>											
BGRa8	<a href="#">RGB8888</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>A<sub>1</sub></td><td>B<sub>2</sub></td><td>G<sub>2</sub></td><td>R<sub>2</sub></td><td>A<sub>2</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	A <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	A <sub>2</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	A <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	A <sub>2</sub>											
BGR10p	<a href="#">RGB101010</a>	<table><tr><td>Bit 9:0</td><td>Bit 19:10</td><td>Bit 29:20</td><td>Bit 31:30</td><td>Bit 9:0</td><td>Bit 19:10</td><td>Bit 29:20</td><td>Bit 31:30</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>Not Used</td><td>B<sub>2</sub></td><td>G<sub>2</sub></td><td>R<sub>2</sub></td><td>Not Used</td></tr></table>	Bit 9:0	Bit 19:10	Bit 29:20	Bit 31:30	Bit 9:0	Bit 19:10	Bit 29:20	Bit 31:30	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	Not Used	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	Not Used
Bit 9:0	Bit 19:10	Bit 29:20	Bit 31:30	Bit 9:0	Bit 19:10	Bit 29:20	Bit 31:30											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	Not Used	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	Not Used											
BGR16	<a href="#">RGB161616</a>	<table><tr><td>Byte 0-1</td><td>Byte 2-3</td><td>Byte 4-5</td><td>Byte 6-7</td><td>Byte 8-9</td><td>Byte 10-11</td><td>Byte 12-13</td><td>Byte 14-15</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>B<sub>2</sub></td><td>G<sub>2</sub></td><td>R<sub>2</sub></td><td>B<sub>3</sub></td><td>G<sub>3</sub></td></tr></table>	Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Byte 8-9	Byte 10-11	Byte 12-13	Byte 14-15	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	B <sub>3</sub>	G <sub>3</sub>
Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Byte 8-9	Byte 10-11	Byte 12-13	Byte 14-15											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	B <sub>3</sub>	G <sub>3</sub>											
BGRY16	<a href="#">RGB161616_MONO16</a>	<table><tr><td>Byte 0-1</td><td>Byte 2-3</td><td>Byte 4-5</td><td>Byte 6-7</td><td>Byte 8-9</td><td>Byte 10-11</td><td>Byte 12-13</td><td>Byte 14-15</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>Y<sub>1</sub></td><td>B<sub>2</sub></td><td>G<sub>2</sub></td><td>R<sub>2</sub></td><td>Y<sub>2</sub></td></tr></table>	Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Byte 8-9	Byte 10-11	Byte 12-13	Byte 14-15	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	Y <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	Y <sub>2</sub>
Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Byte 8-9	Byte 10-11	Byte 12-13	Byte 14-15											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	Y <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	Y <sub>2</sub>											
BGRa16	<a href="#">RGB16161616</a>	<table><tr><td>Byte 0-1</td><td>Byte 2-3</td><td>Byte 4-5</td><td>Byte 6-7</td><td>Byte 8-9</td><td>Byte 10-11</td><td>Byte 12-13</td><td>Byte 14-15</td></tr><tr><td>B<sub>1</sub></td><td>G<sub>1</sub></td><td>R<sub>1</sub></td><td>A<sub>1</sub></td><td>B<sub>2</sub></td><td>G<sub>2</sub></td><td>R<sub>2</sub></td><td>A<sub>2</sub></td></tr></table>	Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Byte 8-9	Byte 10-11	Byte 12-13	Byte 14-15	B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	A <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	A <sub>2</sub>
Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Byte 8-9	Byte 10-11	Byte 12-13	Byte 14-15											
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	A <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	A <sub>2</sub>											
RGB8_Planar	<a href="#">RGBP8</a>	<table><tr><td>Page 0</td><td>Page 1</td><td>Page 2</td></tr><tr><td>R<sub>1</sub></td><td>G<sub>1</sub></td><td>B<sub>1</sub></td></tr></table>	Page 0	Page 1	Page 2	R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>										
Page 0	Page 1	Page 2																
R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>																
RGB16_Planar	<a href="#">RGBP16</a>	<table><tr><td>Page 0</td><td>Page 1</td><td>Page 2</td></tr><tr><td>R<sub>1</sub></td><td>G<sub>1</sub></td><td>B<sub>1</sub></td></tr></table>	Page 0	Page 1	Page 2	R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>										
Page 0	Page 1	Page 2																
R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>																
RGB8	<a href="#">RGBR888</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>R<sub>1</sub></td><td>G<sub>1</sub></td><td>B<sub>1</sub></td><td>R<sub>2</sub></td><td>G<sub>2</sub></td><td>B<sub>2</sub></td><td>R<sub>3</sub></td><td>G<sub>3</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	R <sub>2</sub>	G <sub>2</sub>	B <sub>2</sub>	R <sub>3</sub>	G <sub>3</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7											
R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	R <sub>2</sub>	G <sub>2</sub>	B <sub>2</sub>	R <sub>3</sub>	G <sub>3</sub>											
YUV422_8_UYVY	<a href="#">UYVY</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>U<sub>1</sub></td><td>Y<sub>1</sub></td><td>V<sub>1</sub></td><td>Y<sub>2</sub></td><td>U<sub>2</sub></td><td>Y<sub>3</sub></td><td>V<sub>2</sub></td><td>Y<sub>4</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	U <sub>1</sub>	Y <sub>1</sub>	V <sub>1</sub>	Y <sub>2</sub>	U <sub>2</sub>	Y <sub>3</sub>	V <sub>2</sub>	Y <sub>4</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7											
U <sub>1</sub>	Y <sub>1</sub>	V <sub>1</sub>	Y <sub>2</sub>	U <sub>2</sub>	Y <sub>3</sub>	V <sub>2</sub>	Y <sub>4</sub>											
YUVa8	<a href="#">YUV</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>Y<sub>1</sub></td><td>U<sub>1</sub></td><td>V<sub>1</sub></td><td>A<sub>1</sub></td><td>Y<sub>2</sub></td><td>U<sub>2</sub></td><td>V<sub>2</sub></td><td>A<sub>2</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	Y <sub>1</sub>	U <sub>1</sub>	V <sub>1</sub>	A <sub>1</sub>	Y <sub>2</sub>	U <sub>2</sub>	V <sub>2</sub>	A <sub>2</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7											
Y <sub>1</sub>	U <sub>1</sub>	V <sub>1</sub>	A <sub>1</sub>	Y <sub>2</sub>	U <sub>2</sub>	V <sub>2</sub>	A <sub>2</sub>											
YUV422_8	<a href="#">YUY2</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>Y<sub>1</sub></td><td>U<sub>1</sub></td><td>Y<sub>2</sub></td><td>V<sub>1</sub></td><td>Y<sub>3</sub></td><td>U<sub>2</sub></td><td>Y<sub>4</sub></td><td>V<sub>2</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	Y <sub>1</sub>	U <sub>1</sub>	Y <sub>2</sub>	V <sub>1</sub>	Y <sub>3</sub>	U <sub>2</sub>	Y <sub>4</sub>	V <sub>2</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7											
Y <sub>1</sub>	U <sub>1</sub>	Y <sub>2</sub>	V <sub>1</sub>	Y <sub>3</sub>	U <sub>2</sub>	Y <sub>4</sub>	V <sub>2</sub>											
YUV8_VYU	<a href="#">VYU</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>Y<sub>1</sub></td><td>V<sub>1</sub></td><td>Y<sub>2</sub></td><td>U<sub>1</sub></td><td>Y<sub>3</sub></td><td>V<sub>2</sub></td><td>Y<sub>4</sub></td><td>U<sub>2</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	Y <sub>1</sub>	V <sub>1</sub>	Y <sub>2</sub>	U <sub>1</sub>	Y <sub>3</sub>	V <sub>2</sub>	Y <sub>4</sub>	U <sub>2</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7											
Y <sub>1</sub>	V <sub>1</sub>	Y <sub>2</sub>	U <sub>1</sub>	Y <sub>3</sub>	V <sub>2</sub>	Y <sub>4</sub>	U <sub>2</sub>											
YUV422_8	<a href="#">YUYV</a>	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>Y<sub>1</sub></td><td>U<sub>1</sub></td><td>Y<sub>2</sub></td><td>V<sub>1</sub></td><td>Y<sub>3</sub></td><td>U<sub>2</sub></td><td>Y<sub>4</sub></td><td>V<sub>2</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	Y <sub>1</sub>	U <sub>1</sub>	Y <sub>2</sub>	V <sub>1</sub>	Y <sub>3</sub>	U <sub>2</sub>	Y <sub>4</sub>	V <sub>2</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7											
Y <sub>1</sub>	U <sub>1</sub>	Y <sub>2</sub>	V <sub>1</sub>	Y <sub>3</sub>	U <sub>2</sub>	Y <sub>4</sub>	V <sub>2</sub>											
YUV411_8_UYVY	<a href="#">Y411</a>	<table><tr><td>Byte 0</td><td>Byte 3</td><td>Byte 6</td><td>Byte 9</td></tr><tr><td>Y<sub>1</sub> Y<sub>2</sub> U<sub>1</sub> Y<sub>3</sub> Y<sub>4</sub> V<sub>1</sub> Y<sub>5</sub> Y<sub>6</sub> U<sub>5</sub> Y<sub>7</sub> Y<sub>8</sub> V<sub>5</sub> U<sub>2</sub> Y<sub>7</sub> V<sub>2</sub> Y<sub>8</sub></td><td></td><td></td><td></td></tr></table>	Byte 0	Byte 3	Byte 6	Byte 9	Y <sub>1</sub> Y <sub>2</sub> U <sub>1</sub> Y <sub>3</sub> Y <sub>4</sub> V <sub>1</sub> Y <sub>5</sub> Y <sub>6</sub> U <sub>5</sub> Y <sub>7</sub> Y <sub>8</sub> V <sub>5</sub> U <sub>2</sub> Y <sub>7</sub> V <sub>2</sub> Y <sub>8</sub>											
Byte 0	Byte 3	Byte 6	Byte 9															
Y <sub>1</sub> Y <sub>2</sub> U <sub>1</sub> Y <sub>3</sub> Y <sub>4</sub> V <sub>1</sub> Y <sub>5</sub> Y <sub>6</sub> U <sub>5</sub> Y <sub>7</sub> Y <sub>8</sub> V <sub>5</sub> U <sub>2</sub> Y <sub>7</sub> V <sub>2</sub> Y <sub>8</sub>																		



---

## BICOLOR88

Related Parameter Values	CORBUFFER_VAL_FORMAT_BICOLOR88 CORACQ_VAL_OUTPUT_FORMAT_BICOLOR88
Number of Components	2
Number of Bits	8 per component, 32 total
Value Range	[0...255] ( <i>unsigned</i> )
Bit Organization	The bit organization is set using the parameter CORBUFFER_PRM_COLOR_ALIGNMENT. Possible values are <a href="#">CORBUFFER_VAL_COLOR_ALIGN_RGBG</a> or <a href="#">CORBUFFER_VAL_COLOR_ALIGN_BGRG</a> 1 pixel is generated for 2 components (RG or BG) therefore the buffer width is twice the size of resulting image.

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	G <sub>1</sub>	R <sub>2</sub>	G <sub>3</sub>	B <sub>2</sub>	G <sub>4</sub>

Or

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	G <sub>2</sub>	B <sub>2</sub>	G <sub>3</sub>	R <sub>2</sub>	G <sub>4</sub>

**Note** Represents a RGB color value.

---

## BICOLOR1616

Related Parameter Values	CORBUFFER_VAL_FORMAT_BICOLOR16 CORACQ_VAL_OUTPUT_FORMAT_BICOLOR16
Number of Components	2
Number of Bits	16 per component, 64 total
Value Range	[0...65535] ( <i>unsigned</i> )
Bit Organization	The bit organization is set using the parameter CORBUFFER_PRM_COLOR_ALIGNMENT. Possible values are <a href="#">CORBUFFER_VAL_COLOR_ALIGN_RGBG</a> or <a href="#">CORBUFFER_VAL_COLOR_ALIGN_BGRG</a> 1 pixel is generated for 2 components (RG or BG) therefore the buffer width is twice the size of resulting image.

Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7
R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	G <sub>2</sub>

Or

Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	G <sub>2</sub>

**Note** Represents a RGB color value.

---

## COMPLEX

Related Parameter Values	CORBUFFER_VAL_FORMAT_COMPLEX
Number of Components	2
Number of Bits	32 per component, 64 total
Value Range	Maximum representable: $\pm 3.402823466 \times 10^{38}$ Minimum positive value: $1.175494351 \times 10^{-38}$
Bit Organization	0-31: Real component 32-63: Imaginary component
Note	Represents a pair of floating-point numbers. This data format is always <i>signed</i> .

---

## FLOAT

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_FLOAT CORKERNEL_VAL_FORMAT_FLOAT
<b>Number of Components</b>	1
<b>Number of Bits</b>	32
<b>Value Range</b>	Maximum representable: $\pm 3.402823466 \times 10^{+38}$ Minimum positive value: $1.175494351 \times 10^{-38}$
<b>Note</b>	Represents a single floating-point number. This data format is always <i>signed</i> .

---

## FPOINT

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_FPOINT
<b>Number of Components</b>	2
<b>Number of Bits</b>	32 per component, 64 total
<b>Value Range</b>	Maximum representable: $\pm 3.402823466 \times 10^{+38}$ Minimum positive value: $1.175494351 \times 10^{-38}$
<b>Bit Organization</b>	0-31: X component 32-63: Y component
<b>Note</b>	Represents a pair of float. It is usually used for storing image coordinates. This data format is always <i>signed</i> .

---

## HSI

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_HSI
<b>Number of Components</b>	3
<b>Number of Bits</b>	8 per component, 32 total
<b>Value Range</b>	[0...255]
<b>Bit Organization</b>	0-7: Intensity component 8-15: Saturation component 16-23: Hue component 24-31: Alpha channel

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
I <sub>1</sub>	S <sub>1</sub>	H <sub>1</sub>	A <sub>1</sub>	I <sub>2</sub>	S <sub>2</sub>	H <sub>2</sub>	A <sub>2</sub>

<b>Note</b>	Represents a HSI color value.
-------------	-------------------------------

---

## HSIP8

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_HSIP8
<b>Number of Components</b>	1
<b>Number of Pages</b>	3

Page 0	Page 1	Page 2
H <sub>1</sub>	S <sub>1</sub>	I <sub>1</sub>

<b>Number of Bits</b>	8 per component
<b>Value Range</b>	[0...255]
<b>Note</b>	Represents a planar HSI color value.

---

## HSV

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_HSV

**Number of Components** 3

**Number of Bits** 8 per component, 32 total

**Value Range** [0...255]

**Bit Organization**  
0-7: Value component  
8-15: Saturation component  
16-23: Hue component  
24-31: Alpha channel

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
V <sub>1</sub>	S <sub>1</sub>	H <sub>1</sub>	A <sub>1</sub>	V <sub>2</sub>	S <sub>2</sub>	H <sub>2</sub>	A <sub>2</sub>

**Note** Represents a HSV color value.

---

## INT8

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_INT8

**Number of Components** 1

**Number of Bits** 8

**Value Range** [-128...127]

**Note** Represents a single monochrome value.

---

## INT16

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_INT16

**Number of Components** 1

**Number of Bits** 16 (pixel depth can range from 9 to 16)

**Value Range** [-32768,32767]

**Note** Represents a single monochrome value.

---

## INT32

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_INT32  
CORKERNEL\_VAL\_FORMAT\_INT32

**Number of Components** 1

**Number of Bits** 32

**Value Range** [-2147483648...2147483647]

**Note** Represents a single monochrome value.

---

## MONO1

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_MONO1

**Number of Components** 1

**Number of Bits** 1

Byte 0							
Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	...	Y <sub>30</sub>	Y <sub>31</sub>	Y <sub>32</sub>	

**Value Range** [0...1] (*unsigned*)

**Note** Represents a single monochrome value.

---

## MONO8

Related Parameter Values	CORBUFFER_VAL_FORMAT_MONO8 CORACQ_VAL_OUTPUT_FORMAT_MONO8								
Number of Components	1								
Number of Bits	8								
	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td></tr><tr><td>Y<sub>1</sub></td><td>Y<sub>2</sub></td><td>Y<sub>3</sub></td><td>Y<sub>4</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>
Byte 0	Byte 1	Byte 2	Byte 3						
Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>						
Value Range	[0...255] ( <i>unsigned</i> ) [-128...127] ( <i>signed</i> )								
Note	Represents a single monochrome value.								

---

## MONO16

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_MONO16 CORACQ_VAL_OUTPUT_FORMAT_MONO16			
<b>Number of Components</b>	1			
<b>Number of Bits</b>	16 (pixel depth can range from 9 to 16)			
	Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7
	Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>
<b>Value Range</b>	[0...65535] ( <i>unsigned</i> ) [-32768,32767] ( <i>signed</i> )			
<b>Note</b>	Represents a single monochrome value.			

---

## MONO32

Related Parameter Values	CORBUFFER_VAL_FORMAT_MONO32			
	CORKERNEL_VAL_FORMAT_MONO32			
	CORACQ_VAL_OUTPUT_FORMAT_MONO32			
Number of Components	1			
Number of Bits	32			
	Byte 0-3	Byte 4-7	Byte 8-11	Byte 12-15
	Y <sub>1</sub>	Y <sub>2</sub>	Y <sub>3</sub>	Y <sub>4</sub>
Value Range	[0...4294967295] ( <i>unsigned</i> )			
	[-2147483648...2147483647] ( <i>signed</i> )			
Note	Represents a single monochrome value.			

---

## POINT

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_POINT
<b>Number of Components</b>	2
<b>Number of Bits</b>	32 per component, 64 total
<b>Value Range</b>	[-2147483648...2147483647]
<b>Bit Organization</b>	0-31: X component 32-63: Y component
<b>Note</b>	Represents a pair of integers. It is usually used for storing image coordinates. This data format is always <i>signed</i> .

---

## RGB5551

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_RGB5551  
CORACQ\_VAL\_OUTPUT\_FORMAT\_RGB5551

**Number of Components** 3

**Number of Bits** 5 per component, 16 total

**Value Range** [0...31] (*unsigned*)  
[-16...15] (*signed*)

**Bit Organization** 0-4: Blue component  
5-9: Green component  
10-14: Red component  
15: 1-bit alpha channel

Bit 4:0	Bit 9:5	Bit 14:10	Bit 15	Bit 4:0	Bit 9:5	Bit 14:10	Bit 15
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	A <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	A <sub>2</sub>

**Note** Represents a RGB color value.

---

## RGB565

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_RGB565  
CORACQ\_VAL\_OUTPUT\_FORMAT\_RGB565

**Number of Components** 3

**Number of Bits** 5, 6, 5 (for red, green and blue components respectively), 16 total

**Value Range** Red/blue: [0...31] (*unsigned*), [-16...15] (*signed*)  
Green: [0...63] (*unsigned*), [-32...31] (*signed*)

**Bit Organization** 0-4: Blue component  
5-10: Green component  
11-15: Red component

Bit 4:0	Bit 10:5	Bit 15:11	Bit 20:16	Bit 26:21	Bit 31:27	Bit 4:0	Bit 10:5
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	B <sub>3</sub>	G <sub>3</sub>

**Note** Represents a RGB color value.

---

## RGB888

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_RGB888  
CORACQ\_VAL\_OUTPUT\_FORMAT\_RGB888

**Number of Components** 3

**Number of Bits** 8 per component, 24 total

**Value Range** [0...255] (*unsigned*)  
[-128...127] (*signed*)

**Bit Organization** 0-7: Blue component  
8-15: Green component  
16-23: Red component

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	B <sub>3</sub>	G <sub>3</sub>

**Note** Represents a RGB color value with the blue component stored first.

---

## RGB888\_MONO8

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_RGB888_MONO8
	CORACQ_VAL_OUTPUT_FORMAT_RGB888_MONO8
<b>Number of Components</b>	4
<b>Number of Bits</b>	8 per component, 32 total
<b>Value Range</b>	[0...255] ( <i>unsigned</i> ) [-128...127] ( <i>signed</i> )
<b>Bit Organization</b>	0-7: Blue component 8-15: Green component 16-23: Red component 24-31: IR (mono) component

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	Y <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	Y <sub>2</sub>

**Note** Represents an 8-bit multiformat buffer with RGB and IR (mono) components.

---

## RGB8888

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_RGB8888
	CORACQ_VAL_OUTPUT_FORMAT_RGB8888
<b>Number of Components</b>	3
<b>Number of Bits</b>	8 per component, 32 total
<b>Value Range</b>	[0...255] ( <i>unsigned</i> ) [-128...127] ( <i>signed</i> )
<b>Bit Organization</b>	0-7: Blue component 8-15: Green component 16-23: Red component 24-31: Alpha channel

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	A <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	A <sub>2</sub>

**Note** Represents a RGB color value.

---

## RGB101010

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_RGB101010
	CORACQ_VAL_OUTPUT_FORMAT_RGB101010
<b>Number of Components</b>	3
<b>Number of Bits</b>	10 per component, 32 total
<b>Value Range</b>	[0...1023] ( <i>unsigned</i> ) [-512...511] ( <i>signed</i> )
<b>Bit Organization</b>	0-9: Blue component 10-19: Green component 20-29: Red component 30-31: Not used

Bit 9:0	Bit 19:10	Bit 29:20	Bit 31:30	Bit 9:0	Bit 19:10	Bit 29:20	Bit 31:30
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	Not Used	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	Not Used

**Note** Represents a RGB color value.

---

## RGB161616

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_RGB161616
	CORACQ_VAL_OUTPUT_FORMAT_RGB161616
<b>Number of Components</b>	3
<b>Number of Bits</b>	16 per component, 48 total (pixel depth can range from 9 to 16)
<b>Value Range</b>	[0...65535] ( <i>unsigned</i> ) [-32768...32767] ( <i>signed</i> )
<b>Bit Organization</b>	0-15: Blue component 16-31: Green component 32-47: Red component

Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Byte 8-9	Byte 10-11	Byte 12-13	Byte 14-15
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	B <sub>3</sub>	G <sub>3</sub>

**Note** Represents a RGB color value.

---

## RGB161616\_MONO16

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_RGB161616_MONO16
	CORACQ_VAL_OUTPUT_FORMAT_RGB161616_MONO16
<b>Number of Components</b>	4
<b>Number of Bits</b>	16 per component, 64 total (pixel depth can range from 9 to 16)
<b>Value Range</b>	[0...65535] ( <i>unsigned</i> ) [-32768...32767] ( <i>signed</i> )
<b>Bit Organization</b>	0-15: Blue component 16-31: Green component 32-47: Red component 48-63: IR (mono) component

Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Byte 8-9	Byte 10-11	Byte 12-13	Byte 14-15
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	Y <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	Y <sub>2</sub>

**Note** Represents a 16-bit multiformat buffer with RGB and IR (mono) components.

---

## RGB16161616

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_RGB16161616
	CORACQ_VAL_OUTPUT_FORMAT_RGB161616
<b>Number of Components</b>	4
<b>Number of Bits</b>	16 per component, 64 total (pixel depth can range from 9 to 16)
<b>Value Range</b>	[0...65535] ( <i>unsigned</i> ) [-32768...32767] ( <i>signed</i> )
<b>Bit Organization</b>	0-15: Blue component 16-31: Green component 32-47: Red component 48-63: Alpha component

Byte 0-1	Byte 2-3	Byte 4-5	Byte 6-7	Byte 8-9	Byte 10-11	Byte 12-13	Byte 14-15
B <sub>1</sub>	G <sub>1</sub>	R <sub>1</sub>	A <sub>1</sub>	B <sub>2</sub>	G <sub>2</sub>	R <sub>2</sub>	A <sub>2</sub>

**Note** Represents a RGBA color value.

---

## RGBP8

Related Parameter Values	CORBUFFER_VAL_FORMAT_RGBP8 CORACQ_VAL_OUTPUT_FORMAT_RGBP8		
Number of Components	1		
Number of Pages	3		
	Page 0	Page 1	Page 2
	R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>
Number of Bits	8		
Value Range	[0...255]		
Note	Represents a planar RGB value		

---

## RGBP16

Related Parameter Values	CORBUFFER_VAL_FORMAT_RGBP16 CORACQ_VAL_OUTPUT_FORMAT_RGBP16		
Number of Components	1		
Number of Pages	3		
	Page 0	Page 1	Page 2
	R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>
Number of Bits	16 (pixel depth can range from 9 to 16)		
Value Range	[0...65535]		
Note	Represents a planar RGB value		

---

## RGBR888

Related Parameter Values	CORBUFFER_VAL_FORMAT_RGBR888 CORACQ_VAL_OUTPUT_FORMAT_RGBR888																
Number of Components	3																
Number of Bits	8 per component, 24 total																
Value Range	[0...255] ( <i>unsigned</i> ) [-128...127] ( <i>signed</i> )																
Bit Organization	0-7: Red component 8-15: Green component 16-23: Blue component																
	<table><tr><td>Byte 0</td><td>Byte 1</td><td>Byte 2</td><td>Byte 3</td><td>Byte 4</td><td>Byte 5</td><td>Byte 6</td><td>Byte 7</td></tr><tr><td>R<sub>1</sub></td><td>G<sub>1</sub></td><td>B<sub>1</sub></td><td>R<sub>2</sub></td><td>G<sub>2</sub></td><td>B<sub>2</sub></td><td>R<sub>3</sub></td><td>G<sub>3</sub></td></tr></table>	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7	R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	R <sub>2</sub>	G <sub>2</sub>	B <sub>2</sub>	R <sub>3</sub>	G <sub>3</sub>
Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7										
R <sub>1</sub>	G <sub>1</sub>	B <sub>1</sub>	R <sub>2</sub>	G <sub>2</sub>	B <sub>2</sub>	R <sub>3</sub>	G <sub>3</sub>										
Note	Represents a RGB color value with the red component stored first.																

---

## UINT1

Related Parameter Values	CORBUFFER_VAL_FORMAT_UINT1 CORBUFFER_VAL_FORMAT_BINARY
Number of Components	1
Number of Bits	1
Value Range	[0...1]
Note	Represents a single monochrome value.



---

### UINT8

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_UINT8
<b>Number of Components</b>	1
<b>Number of Bits</b>	8
<b>Value Range</b>	[0...255]
<b>Note</b>	Represents a single monochrome value.

---

### UINT16

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_UINT16
<b>Number of Components</b>	1
<b>Number of Bits</b>	16 (pixel depth can range from 9 to 16)
<b>Value Range</b>	[0...65535]
<b>Note</b>	Represents a single monochrome value.

---

### UINT32

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_UINT32
<b>Number of Components</b>	1
<b>Number of Bits</b>	32
<b>Value Range</b>	[0...4294967295]
<b>Note</b>	Represents a single monochrome value.

---

### UYVY

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_UYVY CORACQ_VAL_OUTPUT_FORMAT_UYVY							
<b>Number of Components</b>	3							
<b>Number of Bits</b>	8 per component (16 per element)							
<b>Value Range</b>	Y: [0...255] U: [-128...127] V: [-128...127]							
<b>Bit Organization</b>	First element: 0–7: $U_0$ 8–15: $Y_0$ Second element: 0-7: $V_0$ 8-15: $Y_1$							
	Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
	$U_1$	$Y_1$	$V_1$	$Y_2$	$U_2$	$Y_3$	$V_2$	$Y_4$
<b>Note</b>	This is a 4:2:2 subsampled format in which for every two luminance components (Y) there is one set of color components (U, V). At least two consecutive elements (an UINT32) are needed to retrieve all the information for the individual components.							

---

## YUV

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_YUV

**Number of Components** 3

**Number of Bits** 8 per component, 32 total

**Value Range** [0...255]

**Bit Organization**  
0-7: Y component  
8-15: U component  
16-23: V component  
24-31: Alpha channel

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
Y <sub>1</sub>	U <sub>1</sub>	V <sub>1</sub>	A <sub>1</sub>	Y <sub>2</sub>	U <sub>2</sub>	V <sub>2</sub>	A <sub>2</sub>

**Note** Represents a YUV color value.

---

## YUY2

**Related Parameter Values** CORBUFFER\_VAL\_FORMAT\_YUY2  
CORACQ\_VAL\_OUTPUT\_FORMAT\_YUY2

**Number of Components** 3

**Number of Bits** 8 per component (16 per element)

**Value Range**  
Y: [0...255]  
U: [-128...127]  
V: [-128...127]

**Bit Organization**  
First element:  
0-7: Y<sub>0</sub>  
8-15: U<sub>0</sub>  
Second element:  
0-7: Y<sub>1</sub>  
8-15: V<sub>0</sub>

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
Y <sub>1</sub>	U <sub>1</sub>	Y <sub>2</sub>	V <sub>1</sub>	Y <sub>3</sub>	U <sub>2</sub>	Y <sub>4</sub>	V <sub>2</sub>

**Note** Alias for the YUYV format.  
This is a 4:2:2 subsampled format in which for every two luminance components (Y) there is one set of color components (U, V). At least two consecutive elements (an UINT32) are needed to retrieve all the information for the individual components.

---

## YVYU

<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_YVYU CORACQ_VAL_OUTPUT_FORMAT_YVYU
<b>Number of Components</b>	3
<b>Number of Bits</b>	8 per component, effectively 16 per element
<b>Value Range</b>	Y: [0...255] U: [-128...127] V: [-128...127]
<b>Bit Organization</b>	First element: 0–7: $Y_0$ 8–15: $V_0$ Second element: 0–7: $Y_1$ 8–15: $U_0$

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
$Y_1$	$V_1$	$Y_2$	$U_1$	$Y_3$	$V_2$	$Y_4$	$U_2$

**Note** This is a 4:2:2 subsampled format in which for every two luminance components (Y) there is one set of color components (U, V). At least two consecutive elements (an UINT32) are needed to retrieve all the information for the individual components.

---

## YUYV


<b>Related Parameter Values</b>	CORBUFFER_VAL_FORMAT_YUYV CORACQ_VAL_OUTPUT_FORMAT_YUYV
<b>Number of Components</b>	3
<b>Number of Bits</b>	8 per component (16 per element)
<b>Value Range</b>	Y: [0...255] U: [-128...127] V: [-128...127]
<b>Bit Organization</b>	First element: 0–7: $Y_0$ 8–15: $U_0$ Second element: 0–7: $Y_1$ 8–15: $V_0$

Byte 0	Byte 1	Byte 2	Byte 3	Byte 4	Byte 5	Byte 6	Byte 7
$Y_1$	$U_1$	$Y_2$	$V_1$	$Y_3$	$U_2$	$Y_4$	$V_2$

**Note** Alias for the YUY2 format.  
This is a 4:2:2 subsampled format in which for every two luminance components (Y) there is one set of color components (U, V). At least two consecutive elements (an UINT32) are needed to retrieve all the information for the individual components.

Y411

Related Parameter Values	CORBUFFER_VAL_FORMAT_Y411 CORACQ_VAL_OUTPUT_FORMAT_Y411
Number of Components	3
Number of Bits	8 per component (12 bits average per pixel)
Value Range	Y: [0...255] U: [-128...127] V: [-128...127]
Bit Organization	First element: 0-7: Y <sub>0</sub> 8-15: Y <sub>1</sub> 16-23: U <sub>0</sub> Second element: 24-31: Y <sub>3</sub> 0-7: Y <sub>4</sub> 8-15: V <sub>0</sub>



**Note** This is a 4:1:1 subsampled format in which for every four luminance components (Y) there is one set of color components (U, V). At least 6 consecutive bytes are needed to retrieve all the information for the individual components, for 12 bits average per pixel.

# Appendix A: Server Management

---

## The Server Database

---

The section *Working with Handles* gives only a quick overview of how Sapera manages servers. Additional issues often need to be considered, especially when running in a Windows environment. Some basic knowledge of the Sapera Server database is required in order to explain these concepts.

---

When Windows boots up, a list of all available Sapera Servers is built into Sapera's Manager module on the host computer. This list is called the "*Server database*". It contains the following types and numbers of entries:

- The 'System' entry is always present in the database. It corresponds to the host computer.
- For any Sapera-compatible board (for example, Xcelera-CL PX4) physically present in the system, there is at least one entry in the database. This entry is represented by the name "BoardName\_x" where "x" is a numerical value ranging from 1 to the number of boards of this type (for example, Xcelera-CL\_PX4\_1, Xcelera-CL\_PX4\_2, ...).
- For any Sapera-compatible camera (for example, Genie) accessible from the system, there is at least one entry in the database. This entry is represented by the name "CameraName\_x" where "x" is a numerical value ranging from 1 to the number of boards of this type (for example, Genie\_M640\_1, Genie\_M640\_2, ...).

The database is made available to all application programs that are using Sapera. Use the **SapConf.exe** program to look up the contents of the database.


Note that not all servers are listed in the database. When running multiple Win32 applications at the same time, a new server is dynamically created for each application for the duration of the process only. The server for the first process will have the same name as the server listed in the database for the current Win32 environment. For example, on the host, the name corresponds to the "System" server. Servers for all other processes running Sapera applications are not part of the database.

Although servers listed in the database have recognized names that can be used directly, this is not the case for servers corresponding to Win32 applications. Sapera, however, permits each server to be assigned an alias in the form of a text string that will allow applications to retrieve any needed server handle at all times.

---

## Server Management Diagram

The diagram below illustrates server management in a system containing one Xcelera-CL PX4, and having access to two Genie M640 cameras. The Sapera Server is the first Sapera process initiated and inherits the name "System". This is followed by two other applications running on the same platform and being assigned the names "System\_P1" and "System\_P2" respectively. These servers are not included in the database.



---

## Getting a Server Handle (revisited)

The previous information in this section illustrated the basics of getting server handles. The following looks more extensively into the different methods of getting server handles.

### Get the server corresponding to the currently running Win32 process:

```
CORSTATUS status;           // Declare status code
CORSERVER hCurrentServer;    // Declare a server handle

// Initialize Sapera API
status = CorManOpen();

// Get the server handle for this process
status = CorManGetLocalServer(&hCurrentServer);
```

### Use the following method if the server's database index is known:

```
CORSTATUS status;           // Declare status code
UINT32 nCount;              // Declare a server count
UINT32 nIndex;              // Declare a server index
char szName[64];            // Declare a character string for returned name
CORSERVER hServer;          // Declare a server handle

// Initialize Sapera API
status = CorManOpen();

// Get the number of servers in the database
status = CorManGetServerCount(&nCount);

// Get the server handle from a database index
// The indices start at 0 (which is always 'System')
status = CorManGetServerByIndex(nIndex, szName, &hServer);
```

### Use the server's database name directly if it is known:

```
CORSTATUS status;           // Declare status code
CORSERVER hGenieServer;      // Declare a server handle

// Initialize Sapera API
status = CorManOpen();

// Get the server handle by specifying its database name
status = CorManGetServerByName("Genie_M640_1", &hGenieServer);
```

# Appendix B: File Formats

---

## Buffer file formats

This section describes some buffer file formats supported in the Spera File Module as implemented by the functions CorFileLoad and CorFileSave.

---

### CORFILE\_VAL\_FORMAT\_CRC

Teledyne DALSA file format

Offset	Size	Description
0	UINT32	Magic Number (must be 0x1A435243)
4-12	UINT32	Reserved
16	UINT32	Buffer width in pixels
20	UINT32	Buffer height in lines
24	UINT32	ROI's horizontal minimum
28	UINT32	ROI's vertical minimum
32	UINT32	ROI's horizontal length
36	UINT32	ROI's vertical length
40-60	UNIT32	Reserved
64	UINT32	Number of bytes per pixel
68	UINT32	Number of bits per pixel
72	UINT32	Number of planes
76-152	UNIT32	Reserved
156	M	Buffer data

Where **M** is given by the following expression:

(**ROI's horizontal length** × **ROI's vertical length** × **Number of bytes per pixel** × **Number of planes**)

---

### CORFILE\_VAL\_FORMAT\_RAW

Raw file format

Offset	Size	Description
N	M	Buffer data

**N** (in bytes) is the location of the buffer data.

**M** is given by the following expression:

( **horizontal buffer length** × **vertical buffer length** × **Number of bytes per pixel**)



---

## CORFILE\_VAL\_FORMAT\_BMP

### Windows Bitmap file format

Offset	Size	Description
0	UINT16	Magic Number (must be ASCII "BM")
2	UINT32	Size in bytes of the file
6	UINT16	Reserved
8	UINT16	Reserved
10	UINT32	Byte offset in files where image begins
14	UINT32	Size of the BITMAPINFO header
18	INT32	Image width in pixels
22	INT32	Image height in pixels
26	UINT16	Number of image planes, must be 1
28	UINT16	Total bits per pixels, 1, 4, 8, 16, 24, 32
30	UINT32	Compression type BI_RGB – none BI_RLE4 – RLE 4 bit BI_RLE8 – RLE 8 bit BI_BITFIELDS - Bitfields
34	UINT32	Size in bytes of compressed image, or zero
38	INT32	Horizontal resolution, in pixel/meter
42	INT32	Vertical resolution, in pixel/meter
46	UINT32	Number of colors used
50	UINT32	Number of important colors
54	RGBQUAD * N	Color map
54+4*N	M	Bitmap Data

- Where **N** is the number of colors used and **M** the number of bitmap data in bytes.
- If bpp (bits per pixel) is 24, N = 0.
- If bpp is 16 or 32,  
If the compression specification is BI\_BITFIELDS (Bitfields), N = 3.  
If the compression specification is BI\_RGB (uncompressed), N = 0.
- Otherwise, N = (1 << bpp).

## Buffer Data Formats Supported as Input by FileSave Functions

Buffer Data Format	File Format						
	BMP	TIF	CRC	RAW	JPEG	JPEG 2000	AVI uncompressed
BICOLOR88	X <sup>(1)</sup>	X <sup>(1)</sup>	X	X			
BICOLOR1616	X <sup>(1)</sup>	X <sup>(1)</sup>	X	X			
COMPLEX			X	X			
FLOAT			X	X			
FPOINT			X	X			
HSI			X	X			
HSIP8			X	X			
HSV			X	X			
INT8	X <sup>(2)</sup>	X	X	X		X	
INT16	X <sup>(2)</sup>	X	X	X		X	
INT32			X	X			
INT64			X	X			
MONO1	X	X	X	X			X
MONO8	X	X	X	X	X	X	X
MONO16	X <sup>(2)</sup>	X	X	X	X <sup>(2)</sup>	X	X <sup>(2)</sup>
MONO32			X	X			
MONO64			X	X			
POINT			X	X			
RGB5551	X	X <sup>(2)</sup>	X	X			X
RGB565	X	X <sup>(2)</sup>	X	X		X	
RGB888	X	X	X	X	X	X	X
RGB888_MONO8			X	X			
RGB8888	X	X <sup>(2)</sup>	X	X	X	X	X
RGB101010	X	X <sup>(4)</sup>	X	X		X	
RGB161616	X <sup>(3)</sup>	X	X	X		X	
RGB161616_MONO16			X	X			
RGB16161616	X <sup>(3)</sup>	X <sup>(4)</sup>	X	X			
RGBP8	X <sup>(2)</sup>	X <sup>(2)</sup>	X	X		X	
RGBP16	X <sup>(3)</sup>	X <sup>(4)</sup>	X	X			
RGBR888	X <sup>(2)</sup>	X <sup>(2)</sup>	X	X	X <sup>(2)</sup>	X <sup>(2)</sup>	X <sup>(2)</sup>
UINT1	X	X	X	X			X
UINT8	X	X	X	X	X	X	X
UINT16	X <sup>(2)</sup>	X	X	X	X <sup>(2)</sup>	X	X <sup>(2)</sup>
UINT32			X	X			
UINT64			X	X			
UYVY	X <sup>(2)</sup>	X <sup>(2)</sup>	X	X	X <sup>(2)</sup>	X <sup>(2)</sup>	X <sup>(2)</sup>
YUV			X	X			
YUY2	X <sup>(2)</sup>	X <sup>(2)</sup>	X	X	X <sup>(2)</sup>	X <sup>(2)</sup>	X <sup>(2)</sup>
YVYU	X <sup>(2)</sup>	X <sup>(2)</sup>	X	X	X <sup>(2)</sup>	X <sup>(2)</sup>	X <sup>(2)</sup>
YUYV	X <sup>(2)</sup>	X <sup>(2)</sup>	X	X	X <sup>(2)</sup>	X <sup>(2)</sup>	X <sup>(2)</sup>
Y211			X	X			
Y411			X	X			

<sup>(1)</sup> Buffer data are converted to RGB888 format prior to being saved into file.

<sup>(2)</sup> Buffer data are converted to MONO8 (equivalent to UINT8) format prior to being saved into file.

<sup>(3)</sup> Buffer data are converted to RGB101010 format prior to being saved into file.

<sup>(4)</sup> Buffer data are converted to RGB161616 format prior to being saved into file.

---

## LUT File Format

This section describes the LUT file format used in the LUT module. See the CorLutLoad and CorLutSave functions.

Offset	Size	Description
0	UINT32	Lut format
4-8	UINT32	Reserved
12	UINT32	Number of entries
16-40	UINT32	Reserved
44	M	LUT data

where **M** is given by the field Size of LUT in bytes.

# Appendix C: Obsolete Modules

The Graphics module has been deprecated and is no longer officially supported. However, the module will continue to compile.

---

## Graphic Module [Obsolete]

This module performs graphic operations on buffer resources.

### Capabilities [Obsolete]

ID	Capability
0x00	CORGRAPHIC_CAP_FILL
0x01	CORGRAPHIC_CAP_TEXT

---

#### CORGRAPHIC\_CAP\_FILL [Obsolete]

**Description** Specifies whether the graphic device supports area filling.  
**Type** UINT32  
**Values** TRUE, The graphic device supports area filling.  
FALSE, The graphic device does not support area filling.

---

#### CORGRAPHIC\_CAP\_TEXT [Obsolete]

**Description** Specifies whether the graphic device supports text drawing.  
**Type** UINT32  
**Values** TRUE, The graphic device supports text drawing.  
FALSE, The graphic device does not support text drawing.

### Parameters [Obsolete]

ID	Parameter	Attribute
0x00	CORGRAPHIC_PRM_OPM	Read/Write
0x01	<i>Not defined</i>	
0x02	CORGRAPHIC_PRM_BKCOLOR	Read/Write
0x03	CORGRAPHIC_PRM_COLOR	Read/Write
0x04	CORGRAPHIC_PRM_FONTSIZE	Read/Write
0x05	CORGRAPHIC_PRM_FONTNAME	Read/Write
0x06	CORGRAPHIC_PRM_LABEL	Read Only
0x07	CORGRAPHIC_PRM_TEXTALIGN	Read/Write
0x08	CORGRAPHIC_PRM_CLIP_ENABLE	Read/Write

---

**CORGRAPHIC\_PRM\_OPM [Obsolete]**

<b>Description</b>	Operation mode
<b>Type</b>	UINT32
<b>Values</b>	CORGRAPHIC_VAL_OPM_REP, destination= CORGRAPHIC_PRM_COLOR CORGRAPHIC_VAL_OPM_XOR, destination= source ^ CORGRAPHIC_PRM_COLOR CORGRAPHIC_VAL_OPM_AND, destination= source & CORGRAPHIC_PRM_COLOR CORGRAPHIC_VAL_OPM_OR, destination= source   CORGRAPHIC_PRM_COLOR CORGRAPHIC_VAL_OPM_T, When enabled, a pixel operation that yields a 0 value is considered transparent, and will not overwrite the current value of the destination pixel.
<b>Note</b>	CORGRAPHIC_VAL_OPM_T can be ORed with one of the other operation mode.

---

**CORGRAPHIC\_PRM\_BKCOLOR [Obsolete]**

<b>Description</b>	Background color (monochrome or color value)
<b>Type</b>	<i>CORDATA</i>
<b>Note</b>	See Data Types for <i>CORDATA</i> definition.

---

**CORGRAPHIC\_PRM\_CLIP\_ENABLE [Obsolete]**

<b>Description</b>	Enables or disables clipping.
<b>Type</b>	<i>CORDATA</i>
<b>Values</b>	TRUE, Enable FALSE, Disable
<b>Note</b>	Default value is FALSE

---

**CORGRAPHIC\_PRM\_COLOR [Obsolete]**

<b>Description</b>	Foreground color (monochrome or color value)
<b>Type</b>	<i>CORDATA</i>
<b>Note</b>	See Data Types for <i>CORDATA</i> definition.

---

**CORGRAPHIC\_PRM\_FONTSIZE [Obsolete]**

<b>Description</b>	Font scaling factor
<b>Type</b>	UINT32
<b>Note</b>	Text can only be up-scaled using this parameter.

---

**CORGRAPHIC\_PRM\_FONTNAME [Obsolete]**

<b>Description</b>	Graphic font file name
<b>Type</b>	CHAR[128]
<b>Values</b>	Zero-terminated array of characters specifying the path and filename of the font file to be used when drawing text.

---

**CORGRAPHIC\_PRM\_LABEL [Obsolete]**

<b>Description</b>	The graphic device's string ID.
<b>Type</b>	CHAR[128]
<b>Values</b>	Zero-terminated array of characters width a fixed size of 128 bytes.
<b>Note</b>	CORGRAPHIC_PRM_LABEL is a read-only parameter.

---

**CORGRAPHIC\_PRM\_TEXTALIGN [Obsolete]**

<b>Description</b>	Horizontal alignment of text
<b>Type</b>	UINT32
<b>Values</b>	CORGRAPHIC_VAL_TEXTALIGN_L, Align text with the left margin CORGRAPHIC_VAL_TEXTALIGN_C, Center text CORGRAPHIC_VAL_TEXTALIGN_R, Align text with the right margin
<b>Note</b>	The default text alignment mode is CORGRAPHIC_VAL_TEXTALIGN_L

## Functions [Obsolete]

Function	Description
CorGraphicArc	<i>Draws an arc in a buffer resource using a graphic device</i>
CorGraphicCircle	<i>Draws a circle in a buffer resource using a graphic device</i>
CorGraphicClear	<i>Clears an area of a buffer resource using a graphic device</i>
CorGraphicDot	<i>Draws a dot in a buffer resource using a graphic device</i>
CorGraphicDots	<i>Draws a series of dots in a buffer resource using a graphic device</i>
CorGraphicDrawVector	<i>Draws a vector in a buffer resource using a graphic device</i>
CorGraphicEllipse	<i>Draws an ellipse in a buffer resource using a graphic device</i>
CorGraphicFill	<i>Fills an enclosed area in a buffer resource using a graphic device</i>
CorGraphicGetCap	<i>Gets capability value from a graphic device</i>
CorGraphicGetCount	<i>Gets the number of graphic devices on a server</i>
CorGraphicGetHandle	<i>Gets a handle to a graphic device</i>
CorGraphicGetPrm	<i>Gets parameter value from a graphic device</i>
CorGraphicGrid	<i>Draws a grid in a buffer resource using a graphic device</i>
CorGraphicLine	<i>Draws a line in a buffer resource using a graphic device</i>
CorGraphicRect	<i>Draws a rectangle in a buffer resource using a graphic device</i>
CorGraphicRelease	<i>Releases handle to a graphic device</i>
CorGraphicReset	<i>Resets a graphic device</i>
CorGraphicResetModule	<i>Reset resources associated with the server graphic device</i>
CorGraphicSetFont	<i>Sets the font to be used by a graphic device</i>
CorGraphicSetPrm	<i>Sets a simple graphic parameter of a graphic device</i>
CorGraphicSetPrmEx	<i>Sets a complex graphic parameter of a graphic device</i>
CorGraphicTarget	<i>Draws a crosshair in a buffer resource using a graphic device</i>
CorGraphicText	<i>Draws text in a buffer resource using a graphic device</i>
CorGraphicTextEx	<i>Draws text in a buffer resource at any angle using a graphic device</i>

---

## CorGraphicArc [Obsolete]

Draw an arc in a buffer resource using a graphic device

<b>Prototype</b>	CORSTATUS <b>CorGraphicArc</b> (CORGRAPHIC <i>hGraphic</i> , CORBUFFER <i>hBuffer</i> , UINT32 <i>x</i> , UINT32 <i>y</i> , UINT32 <i>xRadius</i> , UINT32 <i>yRadius</i> , UINT32 <i>startAngle</i> , UINT32 <i>endAngle</i> , BOOLEAN <i>fill</i> );	
<b>Description</b>	Draws an arc in a specified buffer resource using a graphic device. The arc is actually a segment of an ellipse described by the parameters <i>xRadius</i> and <i>yRadius</i> .	
<b>Input</b>	<i>hGraphic</i>	Graphic resource handle
	<i>hBuffer</i>	Buffer resource handle
	<i>x</i>	X-coordinate of ellipse's origin
	<i>y</i>	Y-coordinate of ellipse's origin
	<i>xRadius</i>	Horizontal radius of ellipse
	<i>yRadius</i>	Vertical radius of ellipse
	<i>startAngle</i>	Angle of ellipse that will define the arc's starting point
	<i>endAngle</i>	Angle of ellipse that will define the arc's ending point
	<i>fill</i>	Arc is filled if <i>fill</i> has a value of TRUE
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID, CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	

---

## CorGraphicCircle [Obsolete]

Draw a circle in a buffer resource using a graphic device

<b>Prototype</b>	CORSTATUS <b>CorGraphicCircle</b> (CORGRAPHIC <i>hGraphic</i> , CORBUFFER <i>hBuffer</i> , UINT32 <i>x</i> , UINT32 <i>y</i> , UINT32 <i>radius</i> , BOOLEAN <i>fill</i> );	
<b>Description</b>	Draws a circle in a specified buffer resource.	
<b>Input</b>	<i>hGraphic</i>	Graphic resource handle
	<i>hBuffer</i>	Buffer resource handle
	<i>x</i>	X-coordinate of circle's origin
	<i>y</i>	Y-coordinate of circle's origin
	<i>radius</i>	Circle radius
	<i>fill</i>	Circle is filled if <i>fill</i> has a value of TRUE
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE, CORSTATUS_ARG_INVALID and CORSTATUS_ARG_OUT_OF_RANGE	

---

## CorGraphicClear [Obsolete]

Clear an area of a buffer resource using a graphic device

<b>Prototype</b>	CORSTATUS <b>CorGraphicClear</b> (CORGRAPHIC <i>hGraphic</i> , CORBUFFER <i>hBuffer</i> , UINT32 <i>x1</i> , UINT32 <i>y1</i> , UINT32 <i>x2</i> , UINT32 <i>y2</i> );	
<b>Description</b>	Clears a rectangular area in a specified buffer resource using a graphic device. The rectangular area is defined by giving the coordinates for a starting corner and an ending corner.	
<b>Input</b>	<i>hGraphic</i>	Graphic resource handle
	<i>hBuffer</i>	Buffer resource handle
	<i>x1</i>	X-coordinate of the starting corner
	<i>y1</i>	Y-coordinate of the starting corner
	<i>x2</i>	X-coordinate of the ending corner
	<i>y2</i>	Y-coordinate of the ending corner
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INCOMPATIBLE, CORSTATUS_ARG_INVALID, CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	

---

## CorGraphicDot [Obsolete]

Draw a dot in a buffer resource using a graphic device

<b>Prototype</b>	CORSTATUS <b>CorGraphicDot</b> (CORGRAPHIC <i>hGraphic</i> , CORBUFFER <i>hBuffer</i> , UINT32 <i>x</i> , UINT32 <i>y</i> );	
<b>Description</b>	Draws a dot in a specified buffer resource using a graphic device.	
<b>Input</b>	<i>hGraphic</i>	Graphic resource handle
	<i>hBuffer</i>	Buffer resource handle
	<i>x</i>	Dot's x-coordinate
	<i>y</i>	Dot's y-coordinate
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID, CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	



---

## CorGraphicDots [Obsolete]

Draw a series of dots in a buffer resource using a graphic device

**Prototype**     `CORSTATUS CorGraphicDots(CORGRAPHIC hGraphic, CORBUFFER hBuffer, UINT32 x,  
UINT32 y, CORBUFFER hDots, UINT32 nPixels);`

**Description**     Draws a series of dots in a specified buffer resource using a graphic device.

**Input**

<i>hGraphic</i>	Graphic resource handle
<i>hBuffer</i>	Buffer resource handle
<i>x</i>	First dot's X-coordinate
<i>y</i>	First dot's Y-coordinate
<i>hDots</i>	Series of bytes defining the path to follow. Each byte represents the direction to the next adjacent pixel to draw, as indicated in the table below:

Value	1	2	3	4	5	6	7	8
Direction	E	NE	N	NW	W	SW	S	SE

A value of zero or any value greater than 8 is interpreted as not moving, causing the previous element to be drawn again.

<i>nPixels</i>	Amount of dots to plot in the given direction
----------------	-----------------------------------------------

**Output**     None

**Return Value**   `CORSTATUS_OK`  
`CORSTATUS_ARG_INVALID`, `CORSTATUS_ARG_OUT_OF_RANGE` and  
`CORSTATUS_INVALID_HANDLE`

---

## CorGraphicDrawVector [Obsolete]

Draw a vector in a buffer resource using a graphic device

**Prototype**     `CORSTATUS CorGraphicDrawVector(CORGRAPHIC hGraphic, CORBUFFER hBuffer,  
CORBUFFER vector, INT32 min, INT32 max, UINT32 n);`

**Description**     The CorGraphicDrawVector operator accepts vectors of integer numbers, floating point numbers, or vectors of points. Point input data is plotted using the (*x*,*y*) coordinate of the data. Scalar data is plotted using the vector index (starting from 0) as the X coordinate and the element value as the Y coordinate.

**Input**

<i>hGraphic</i>	Graphic resource handle
<i>hBuffer</i>	Buffer resource handle
<i>vector</i>	Vector to draw
<i>min</i>	Minimum Y value to be plotted
<i>max</i>	Maximum Y value to be plotted
<i>n</i>	Number of values to be plotted

**Output**     None

**Return Value**   `CORSTATUS_OK`  
`CORSTATUS_ARG_INVALID`, `CORSTATUS_ARG_OUT_OF_RANGE` and  
`CORSTATUS_INVALID_HANDLE`

---

### CorGraphicEllipse [Obsolete]

Draw an ellipse in a buffer resource using a graphic device

**Prototype**     CONSTATUS **CorGraphicEllipse**(CORGRAPHIC *hGraphic*, CORBUFFER *hBuffer*, UINT32 *x*, UINT32 *y*, UINT32 *xRadius*, UINT32 *yRadius*, BOOLEAN *fill*);

**Description**   Draws an ellipse in a specified buffer resource using a graphic device.

**Input**           *hGraphic*     Graphic resource handle  
                  *hBuffer*     Buffer resource handle  
                  *x*            X-coordinate of ellipse's origin  
                  *y*            Y-coordinate of ellipse's origin  
                  *xRadius*     Horizontal radius of ellipse  
                  *yRadius*     Vertical radius of ellipse  
                  *fill*         The ellipse is filled if *fill* has a value of TRUE

**Output**          None

**Return Value**   CONSTATUS\_OK  
                  CONSTATUS\_ARG\_INVALID, CONSTATUS\_ARG\_OUT\_OF\_RANGE and  
                  CONSTATUS\_INVALID\_HANDLE

---

### CorGraphicFill [Obsolete]

Fill an enclosed area in a buffer resource using a graphic device

**Prototype**     CONSTATUS **CorGraphicFill**(CORGRAPHIC *hGraphic*, CORBUFFER *hBuffer*, UINT32 *xSeed*, UINT32 *ySeed*);

**Description**   Fills an enclosed area in a specified buffer resource using a graphic device.

**Input**           *hGraphic*     Graphic resource handle  
                  *hBuffer*     Buffer resource handle  
                  *xSeed*        X-coordinate of seed point  
                  *ySeed*        Y-coordinate of seed point

**Output**          None

**Return Value**   CONSTATUS\_OK  
                  CONSTATUS\_ARG\_INVALID, CONSTATUS\_ARG\_OUT\_OF\_RANGE and  
                  CONSTATUS\_INVALID\_HANDLE, CONSTATUS\_NO\_MEMORY

---

### CorGraphicGetCap [Obsolete]

Gets graphic capability value from a graphic device

**Prototype**     CONSTATUS **CorGraphicGetCap**(CORGRAPHIC *hGraphic*, UINT32 *cap*, void *\*value*);

**Description**   Gets a graphic capability value from a graphic device.

**Input**           *hGraphic*     Graphic resource handle  
                  *cap*           Graphic device capability requested  
                  *value*         Value of the capability

**Output**          None

**Return Value**   CONSTATUS\_ARG\_NULL ( if *value* is NULL),  
                  CONSTATUS\_CAP\_INVALID, CONSTATUS\_CAP\_NOT\_AVAILABLE and  
                  CONSTATUS\_INVALID\_HANDLE

---

### CorGraphicGetCount [Obsolete]

Get the number of graphic devices on a server

**Prototype**     CORSTATUS **CorGraphicGetCount**(CORSERVER *hServer*, UINT32 *\*count*);

**Description**   Gets the number of graphic devices on a server.

**Input**           *hServer*     Server handle

**Output**          *count*       Number of graphic devices

**Note**           The content of count is 0 when there is no graphic device available.

**Return Value**   CORSTATUS\_OK  
                  CORSTATUS\_ARG\_NULL ( if *count* is NULL),  
                  CORSTATUS\_INVALID\_HANDLE

---

### CorGraphicGetHandle [Obsolete]

Get a handle to a graphic device

**Prototype**     CORSTATUS **CorGraphicGetHandle**(CORSERVER *hServer*, UINT32 *index*, CORGRAPHIC *\*hGraphic*);

**Description**   Gets an handle to a graphic device.

**Input**           *hServer*     Server handle  
                  *index*       Specifies which graphic device to select. Valid values are in the range [0...count-1], where *count* is the value returned by CorGraphicGetCount.

**Output**          *hGraphic*   Graphic resource handle

**Return Value**   CORSTATUS\_OK  
                  CORSTATUS\_ARG\_NULL ( if *hGraphic* is NULL),  
                  CORSTATUS\_ARG\_OUT\_OF\_RANGE, CORSTATUS\_INVALID\_HANDLE and  
                  CORSTATUS\_NO\_MEMORY

**See Also**       CorGraphicGetCount and CorGraphicRelease

---

### CorGraphicGetPrm [Obsolete]

Get graphic parameter value from a graphic device

**Prototype**     CORSTATUS **CorGraphicGetPrm**(CORGRAPHIC *hGraphic*, UINT32 *prm*, void *\*value*);

**Description**   Gets graphic parameter value from a graphic device.

**Input**           *hGraphic*   Graphic resource handle  
                  *prm*       Graphic parameter requested

**Output**          *value*       Current value of the parameter

**Return Value**   CORSTATUS\_OK  
                  CORSTATUS\_ARG\_NULL ( if *value* is NULL),  
                  CORSTATUS\_INVALID\_HANDLE, CORSTATUS\_PRM\_INVALID

**See Also**       CorGraphicSetPrm and CorGraphicSetPrmEx

---

## CorGraphicGrid [Obsolete]

Draws a grid in a buffer resource using a graphic device

<b>Prototype</b>	CORSTATUS <b>CorGraphicGrid</b> (CORGRAPHIC <i>hGraphic</i> , CORBUFFER <i>hBuffer</i> , UINT32 <i>x1</i> , UINT32 <i>y1</i> , UINT32 <i>x2</i> , UINT32 <i>y2</i> , UINT32 <i>nx</i> , UINT32 <i>ny</i> );	
<b>Description</b>	Draws a grid in a buffer resource by defining a rectangular area's start and end corners, and the horizontal and vertical grid spacing.	
<b>Input</b>	<i>hGraphic</i>	Graphic resource handle
	<i>hBuffer</i>	Buffer resource handle
	<i>x1</i>	X-coordinate of the starting corner
	<i>y1</i>	Y-coordinate of the starting corner
	<i>x2</i>	X-coordinate of the ending corner
	<i>y2</i>	Y-coordinate of the ending corner
	<i>nx</i>	Horizontal grid spacing
	<i>ny</i>	Vertical grid spacing
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INCOMPATIBLE, CORSTATUS_ARG_INVALID, CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	

---

## CorGraphicLine [Obsolete]

Draws a line in a buffer resource using a graphic device

<b>Prototype</b>	CORSTATUS <b>CorGraphicLine</b> (CORGRAPHIC <i>hGraphic</i> , CORBUFFER <i>buffer</i> , UINT32 <i>x1</i> , UINT32 <i>y1</i> , UINT32 <i>x2</i> , UINT32 <i>y2</i> );	
<b>Description</b>	Draws a line in a specified buffer resource using a graphic device.	
<b>Input</b>	<i>hGraphic</i>	Graphic resource handle
	<i>hBuffer</i>	Buffer resource handle
	<i>x1</i>	X-coordinate of the line's starting point
	<i>y1</i>	Y-coordinate of the line's starting point
	<i>x2</i>	X-coordinate of the line's ending point
	<i>y2</i>	Y-coordinate of the line's ending point
<b>Output</b>	None	
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_ARG_INVALID, CORSTATUS_ARG_OUT_OF_RANGE and CORSTATUS_INVALID_HANDLE	

---

## CorGraphicRect [Obsolete]

Draws a rectangle in a buffer resource using a graphic device

<b>Prototype</b>	CONSTSTATUS <b>CorGraphicRect</b> (CORGRAPHIC <i>hGraphic</i> , CORBUFFER <i>buffer</i> , UINT32 <i>x1</i> , UINT32 <i>y1</i> , UINT32 <i>x2</i> , UINT32 <i>y2</i> , BOOLEAN <i>fill</i> );	
<b>Description</b>	Draws a rectangular area in a specified buffer resource using a graphic device. The rectangle is defined by giving the coordinates for a starting corner and an ending corner.	
<b>Input</b>	<i>hGraphic</i>	Graphic resource handle
	<i>hBuffer</i>	Buffer resource handle
	<i>x1</i>	X-coordinate of the starting corner
	<i>y1</i>	Y-coordinate of the starting corner
	<i>x2</i>	X-coordinate of the ending corner
	<i>y2</i>	Y-coordinate of the ending corner
	<i>fill</i>	Rectangle is filled if <i>fill</i> has a value of TRUE
<b>Output</b>	None	
<b>Return Value</b>	CONSTSTATUS_OK CONSTSTATUS_ARG_INCOMPATIBLE, CONSTSTATUS_ARG_INVALID, CONSTSTATUS_ARG_OUT_OF_RANGE and CONSTSTATUS_INVALID_HANDLE	

---

## CorGraphicRelease [Obsolete]

Release handle to graphic device

<b>Prototype</b>	CONSTSTATUS <b>CorGraphicRelease</b> (CORGRAPHIC <i>hGraphic</i> );	
<b>Description</b>	Releases handle to graphic device.	
<b>Input</b>	<i>hGraphic</i>	Graphic resource handle
<b>Output</b>	None	
<b>Return Value</b>	CONSTSTATUS_OK CONSTSTATUS_INVALID_HANDLE	
<b>See Also</b>	CorGraphicGetHandle	

---

## CorGraphicReset [Obsolete]

Reset a graphic device

<b>Prototype</b>	CONSTSTATUS <b>CorGraphicReset</b> (CORGRAPHIC <i>hGraphic</i> );	
<b>Description</b>	Resets a graphic device. Restores the default graphic parameters of the specified device.	
<b>Input</b>	<i>hGraphic</i>	Graphic resource handle
<b>Output</b>	None	
<b>Return Value</b>	CONSTSTATUS_OK CONSTSTATUS_INVALID_HANDLE	

---

## CorGraphicResetModule [Obsolete]

Reset the resources associated with the server's graphic device(s)

<b>Prototype</b>	CORSTATUS <b>CorGraphicResetModule</b> (CORSERVER <i>hServer</i> );
<b>Description</b>	Resets the resources associated with the server's graphic device(s). Releases all resources (handle, memory) currently allocated. When using this function, make certain that no other application is currently using any graphic resource. This function should be used with caution.
<b>Input</b>	<i>hServer</i> Server handle
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE

---

## CorGraphicSetFont [Obsolete]

Set the font to be used by a graphic device

<b>Prototype</b>	CORSTATUS <b>CorGraphicSetFont</b> (CORGRAPHIC <i>hGraphic</i> , const char * <i>fontName</i> , const void * <i>fontData</i> , UINT32 <i>fontDataSize</i> );
<b>Description</b>	Sets the font to be used by a graphic device.
<b>Input</b>	<i>hGraphic</i> Graphic resource handle <i>fontName</i> String specifying the path and filename of a binary font file to be used or the name to be attribute to the font in <i>fontData</i> array. <i>fontData</i> Array which contains the font to be used ( <i>fontDataSize</i> ). Must be <i>NULL</i> when <i>fontName</i> contains the path and filename of a binary font file. <i>fontDataSize</i> Size of <i>fontData</i> array (in bytes). Should be 0 when <i>fontName</i> contains the path and filename of a binary font file.
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_FILE_OPEN_ERROR, CORSTATUS_FILE_READ_ERROR, CORSTATUS_INVALID_HANDLE and CORSTATUS_NO_MEMORY
<b>Note</b>	If <i>fontData</i> is <i>NULL</i> , <i>fontName</i> must contains the path and filename of a binary font file.

---

## CorGraphicSetPrm [Obsolete]

Set a simple graphic parameter of a graphic device

<b>Prototype</b>	CORSTATUS <b>CorGraphicSetPrm</b> (CORGRAPHIC <i>hGraphic</i> , UINT32 <i>prm</i> , UINT32 <i>value</i> );
<b>Description</b>	Sets a simple graphic parameter of a graphic device.
<b>Input</b>	<i>hGraphic</i> Graphic resource handle <i>prm</i> Graphic parameter to set <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CORSTATUS_OK CORSTATUS_INVALID_HANDLE and CORSTATUS_PRM_INVALID
<b>Note</b>	A simple parameter fits inside an UINT32. For complex parameters use CorGraphicSetPrmEx.
<b>See Also</b>	CorGraphicGetPrm

---

### CorGraphicSetPrmEx [Obsolete]

Set a complex graphic parameter of a graphic device

<b>Prototype</b>	<code>CONSTSTATUS CorGraphicSetPrmEx(CORGRAPHIC <i>hGraphic</i>, UINT32 <i>prm</i>, const void *<i>value</i>);</code>
<b>Description</b>	Sets the value of a specified graphic parameter.
<b>Input</b>	<i>hGraphic</i> Graphic resource handle <i>prm</i> Graphic parameter to set <i>value</i> New value of the parameter
<b>Output</b>	None
<b>Return Value</b>	CONSTSTATUS_OK CONSTSTATUS_ARG_NULL ( if <i>value</i> is NULL), CONSTSTATUS_INVALID_HANDLE and CONSTSTATUS_PRM_INVALID
<b>Note</b>	A complex parameter is one whose size is greater than an UINT32. If the parameter size is UINT32, use either CorGraphicSetPrm or CorGraphicSetPrmEx.
<b>See Also</b>	CorGraphicGetPrm

---

### CorGraphicTarget [Obsolete]

Draws a crosshair in a buffer resource using a graphic device

<b>Prototype</b>	<code>CONSTSTATUS CorGraphicTarget(CORGRAPHIC <i>hGraphic</i>, CORBUFFER <i>hBuffer</i>, UINT32 <i>x</i>, UINT32 <i>y</i>);</code>
<b>Description</b>	Draw a crosshair in a specified buffer resource using a graphic device.
<b>Input</b>	<i>hGraphic</i> Graphic resource handle <i>hBuffer</i> Buffer resource handle <i>x</i> Target center X coordinate <i>y</i> Target center Y coordinate
<b>Output</b>	None
<b>Return Value</b>	CONSTSTATUS_OK CONSTSTATUS_ARG_INVALID, CONSTSTATUS_ARG_OUT_OF_RANGE and CONSTSTATUS_INVALID_HANDLE

---

### CorGraphicText [Obsolete]

Draw text in a buffer resource using a graphic device

<b>Prototype</b>	<code>CONSTSTATUS CorGraphicText(CORGRAPHIC <i>hGraphic</i>, CORBUFFER <i>hBuffer</i>, UINT32 <i>x</i>, UINT32 <i>y</i>, const char <i>text</i>[]);</code>
<b>Description</b>	Draws text in a specified buffer resource using a graphic device.
<b>Input</b>	<i>hGraphic</i> Graphic resource handle <i>hBuffer</i> Buffer resource handle <i>x</i> X-coordinate for text origin <i>y</i> Y-coordinate for text origin <i>text</i> Text string to draw
<b>Output</b>	None  CONSTSTATUS_ARG_INVALID, CONSTSTATUS_ARG_NULL ( if <i>text</i> is NULL), CONSTSTATUS_ARG_OUT_OF_RANGE, CONSTSTATUS_INVALID_HANDLE and CONSTSTATUS_PRM_INVALID_VALUE
<b>See Also</b>	CorGraphicTextEx

---

## CorGraphicTextEx [Obsolete]

Draw text in a buffer at any angle using a graphic device

**Prototype**     `CORSTATUS CorGraphicTextEx(CORGRAPHIC hGraphic, CORBUFFER hBuffer, UINT32 x, UINT32 y, UINT32 angle, const char text[]);`

**Description**     Draws text in a specified buffer at a specified angle using a graphic device.

**Input**

<i>hGraphic</i>	Graphic resource handle
<i>hBuffer</i>	Buffer resource handle
<i>x</i>	X-coordinate for text origin
<i>y</i>	Y-coordinate for text origin
<i>angle</i>	Angle at which to rotate text
<i>text</i>	Text string to draw

**Output**     None

**Return Value**     `CORSTATUS_OK`  
`CORSTATUS_ARG_INVALID`, `CORSTATUS_ARG_NULL` ( if *text* is `NULL`), `CORSTATUS_ARG_OUT_OF_RANGE`, `CORSTATUS_INVALID_HANDLE` and `CORSTATUS_PRM_INVALID_VALUE`

**See Also**     `CorGraphicText`



# Contact Information



The following sections provide sales and technical support contact information.

---

## Sales Information

Visit our web site:

[www.teledynedalsa.com/corp/contact/](http://www.teledynedalsa.com/corp/contact/)

Email:

<mailto:info@teledynedalsa.com>

---

## Technical Support

Submit any support question or request via our web site:

Technical support form via our web page:	
Support requests for imaging product installations	<a href="http://www.teledynedalsa.com/imaging/support">http://www.teledynedalsa.com/imaging/support</a>
Support requests for imaging applications	
Camera support information	
Product literature and driver updates	

When encountering hardware or software problems, please have the following documents included in your support request:

- The Spera Log Viewer .txt file
- The PCI Diagnostic PciDiag.txt file (for frame grabbers)
- The Device Manager BoardInfo.txt file (for frame grabbers)



Note, the Spera Log Viewer and PCI Diagnostic tools are available from the Windows start menu shortcut **Start • All Programs • Teledyne DALSA • Spera LT**. The Device Manager utility is available as part of the driver installation for your Teledyne DALSA device and is available from the Windows start menu shortcut **Start • All Programs • Teledyne DALSA • <Device Name> • Device Manager**.